

BIOMETRIC EVALUATION COMMON FRAMEWORK

PROGRAMMER'S GUIDE

VERSION 0.1

WAYNE SALAMON
GREGORY FIUMARA

IMAGE GROUP
INFORMATION ACCESS DIVISION
INFORMATION TECHNOLOGY LABORATORY

NIST
National Institute of
Standards and Technology
U.S. Department of Commerce

JANUARY 9, 2014

Contents

1	Introduction	1
1.1	Rationale	1
2	Overview	3
3	Framework	5
4	Memory	7
4.1	AutoBuffer	7
4.2	AutoArray	8
4.3	IndexedBuffer	9
5	Error Handling	11
5.1	Biometric Evaluation Exceptions	11
5.2	Signal Handling	11
6	Input/Output	15
6.1	Utility	15
6.2	Record Management	15
6.3	Logging	17
6.4	Properties	18
6.5	Compressor	18
7	Time and Timing	21
7.1	Elapsed Time	21
7.2	Limiting Execution Time	21
8	Process Information	23
8.1	Process Statistics	23
8.2	Process Management	25
8.2.1	Manager	25
8.2.2	Worker	25
8.2.3	WorkerController	27
8.2.4	Communications	28
9	System	31
10	Image	33
10.1	The Image Namespace	33
10.2	The Image Class	33
10.3	Raw Image	34
10.4	JPEG	34

10.5	JPEGL	34
10.6	JPEG2000	34
10.7	NetPBM	35
10.8	PNG	35
10.9	WSQ	35
11	Text	37
12	Feature	39
12.1	ANSI/NIST Features	39
12.2	ISO/INCITS Features	39
13	Finger	41
13.1	ANSI/NIST Minutiae Data Record	41
13.1.1	ANSI/NIST Finger Views	42
13.1.2	ISO/INCITS Finger Views	43
14	View	45
15	Data Interchange	47
15.1	ANSI/NIST Data Records	47
15.2	INCITS Data Records	50
15.2.1	Finger Views	50
	References	51
A	Namespace Index	53
A.1	Namespace List	53
B	Hierarchical Index	55
B.1	Class Hierarchy	55
C	Class Index	59
C.1	Class List	59
D	Namespace Documentation	65
D.1	BiometricEvaluation::Error Namespace Reference	65
D.1.1	Detailed Description	66
D.1.2	Function Documentation	66
D.1.2.1	errorStr	66
D.2	BiometricEvaluation::Finger Namespace Reference	66
D.2.1	Detailed Description	67
D.2.2	Function Documentation	68
D.2.2.1	operator<<	68
D.3	BiometricEvaluation::Framework Namespace Reference	68
D.3.1	Detailed Description	68
D.3.2	Function Documentation	68
D.3.2.1	getMajorVersion	68
D.3.2.2	getMinorVersion	69
D.3.2.3	getCompiler	69
D.3.2.4	getCompileDate	69
D.3.2.5	getCompileTime	69
D.3.2.6	getCompilerVersion	69

D.4	BiometricEvaluation::Image Namespace Reference	69
D.4.1	Detailed Description	71
D.4.2	Function Documentation	71
D.4.2.1	operator<<	71
D.4.2.2	distance	71
D.5	BiometricEvaluation::IO Namespace Reference	71
D.5.1	Detailed Description	72
D.5.2	Typedef Documentation	72
D.5.2.1	ManifestMap	72
D.5.2.2	PropertiesMap	72
D.6	BiometricEvaluation::IO::Utility Namespace Reference	73
D.6.1	Detailed Description	73
D.6.2	Function Documentation	74
D.6.2.1	removeDirectory	74
D.6.2.2	removeDirectory	74
D.6.2.3	copyDirectoryContents	74
D.6.2.4	setAsideName	75
D.6.2.5	getFileSize	75
D.6.2.6	fileExists	76
D.6.2.7	validateRootName	76
D.6.2.8	constructAndCheckPath	76
D.6.2.9	makePath	77
D.6.2.10	readFile	77
D.6.2.11	writeFile	77
D.6.2.12	writeFile	78
D.6.2.13	isReadable	78
D.6.2.14	isWritable	78
D.6.2.15	createTemporaryFile	79
D.6.2.16	createTemporaryFile	79
D.7	BiometricEvaluation::Memory Namespace Reference	80
D.7.1	Detailed Description	80
D.8	BiometricEvaluation::Process Namespace Reference	81
D.8.1	Detailed Description	81
D.8.2	Typedef Documentation	81
D.8.2.1	ParameterList	81
D.9	BiometricEvaluation::System Namespace Reference	81
D.9.1	Detailed Description	82
D.9.2	Function Documentation	82
D.9.2.1	getCPUCount	82
D.9.2.2	getRealMemorySize	82
D.9.2.3	getLoadAverage	83
D.10	BiometricEvaluation::Text Namespace Reference	83
D.10.1	Detailed Description	83
D.10.2	Function Documentation	83
D.10.2.1	digest	83
D.10.2.2	digest	84
D.10.2.3	split	84
D.10.2.4	filename	85
D.10.2.5	dirname	85
D.11	BiometricEvaluation::Time Namespace Reference	85
D.11.1	Detailed Description	86

D.12	BiometricEvaluation::View Namespace Reference	86
D.12.1	Detailed Description	86
D.12.2	Function Documentation	87
D.12.2.1	operator<<	87
E	Class Documentation	89
E.1	BiometricEvaluation::Finger::AN2KViewCapture::AmputatedBandaged Class Reference . . .	89
E.1.1	Detailed Description	89
E.1.2	Member Enumeration Documentation	89
E.1.2.1	Kind	89
E.2	BiometricEvaluation::Feature::AN2K7Minutiae Class Reference	89
E.2.1	Detailed Description	91
E.2.2	Constructor & Destructor Documentation	91
E.2.2.1	AN2K7Minutiae	91
E.2.2.2	AN2K7Minutiae	91
E.2.3	Member Function Documentation	92
E.2.3.1	convertPatternClassification	92
E.2.3.2	convertPatternClassification	92
E.2.3.3	convertEncodingMethod	92
E.2.3.4	getPatternClassificationSet	93
E.2.3.5	getOriginatingFingerprintReadingSystem	93
E.2.3.6	convertCoordinate	93
E.3	BiometricEvaluation::Finger::AN2KMinutiaeDataRecord Class Reference	94
E.3.1	Detailed Description	94
E.3.2	Constructor & Destructor Documentation	94
E.3.2.1	AN2KMinutiaeDataRecord	94
E.3.2.2	AN2KMinutiaeDataRecord	95
E.3.3	Member Function Documentation	95
E.3.3.1	getAN2K7Minutiae	95
E.3.3.2	getImpressionType	95
E.3.3.3	getRegisteredVendorBlock	95
E.4	BiometricEvaluation::View::AN2KViewVariableResolution::AN2KQualityMetric Struct Reference	96
E.4.1	Detailed Description	96
E.5	BiometricEvaluation::DataInterchange::AN2KRecord Class Reference	96
E.5.1	Detailed Description	98
E.5.2	Member Typedef Documentation	98
E.5.2.1	DomainName	98
E.5.2.2	CharacterSet	98
E.5.3	Constructor & Destructor Documentation	98
E.5.3.1	AN2KRecord	98
E.5.3.2	AN2KRecord	98
E.5.4	Member Function Documentation	99
E.5.4.1	recordLocations	99
E.5.4.2	recordLocations	99
E.5.4.3	getVersionNumber	99
E.5.4.4	getDate	99
E.5.4.5	getDestinationAgency	100
E.5.4.6	getOriginatingAgency	100
E.5.4.7	getTransactionControlNumber	100
E.5.4.8	getNativeScanningResolution	100
E.5.4.9	getNominalTransmittingResolution	100

	E.5.4.10	getFingerLatentCount	100
	E.5.4.11	getFingerLatents	100
	E.5.4.12	getFingerCaptureCount	101
	E.5.4.13	getFingerCaptures	101
	E.5.4.14	getMinutiaeDataRecordSet	101
	E.5.4.15	getPriority	101
	E.5.4.16	getDomainName	101
	E.5.4.17	getGreenwichMeanTime	102
	E.5.4.18	getDirectoryOfCharacterSets	102
E.6		BiometricEvaluation::Finger::AN2KView Class Reference	102
	E.6.1	Detailed Description	103
	E.6.2	Constructor & Destructor Documentation	103
		E.6.2.1 AN2KView	103
		E.6.2.2 AN2KView	104
	E.6.3	Member Function Documentation	104
		E.6.3.1 convertPosition	104
		E.6.3.2 populateFGP	105
		E.6.3.3 convertFingerImageCode	105
		E.6.3.4 getMinutiaeDataRecordSet	105
		E.6.3.5 getPositions	105
		E.6.3.6 getImpressionType	106
		E.6.3.7 addMinutiaeDataRecord	106
		E.6.3.8 setPositions	106
		E.6.3.9 setImpressionType	106
E.7		BiometricEvaluation::View::AN2KView Class Reference	106
	E.7.1	Detailed Description	108
	E.7.2	Constructor & Destructor Documentation	109
		E.7.2.1 AN2KView	109
		E.7.2.2 AN2KView	109
	E.7.3	Member Function Documentation	109
		E.7.3.1 convertDeviceMonitoringMode	109
		E.7.3.2 convertCompressionAlgorithm	109
		E.7.3.3 getImage	110
		E.7.3.4 getImageSize	110
		E.7.3.5 getImageResolution	110
		E.7.3.6 getImageDepth	110
		E.7.3.7 getCompressionAlgorithm	111
		E.7.3.8 getScanResolution	111
		E.7.3.9 getMinutiaeDataRecordSet	111
		E.7.3.10 getRecordType	111
		E.7.3.11 getAN2KRecord	111
E.8		BiometricEvaluation::Finger::AN2KViewCapture Class Reference	111
	E.8.1	Detailed Description	113
	E.8.2	Constructor & Destructor Documentation	113
		E.8.2.1 AN2KViewCapture	113
		E.8.2.2 AN2KViewCapture	114
	E.8.3	Member Function Documentation	114
		E.8.3.1 convertAmputatedBandaged	114
		E.8.3.2 convertFingerSegmentPosition	114
		E.8.3.3 convertAlternateFingerSegmentPosition	114
		E.8.3.4 extractNISTQuality	115

E.8.3.5	getNISTQualityMetric	115
E.8.3.6	getSegmentationQualityMetric	115
E.8.3.7	getAmputatedBandaged	115
E.8.3.8	getFingerSegmentPositionSet	116
E.8.3.9	getAlternateFingerSegmentPositionSet	116
E.8.3.10	getFingerprintQualityMetric	116
E.9	BiometricEvaluation::Finger::AN2KViewFixedResolution Class Reference	116
E.9.1	Detailed Description	117
E.9.2	Constructor & Destructor Documentation	117
E.9.2.1	AN2KViewFixedResolution	117
E.9.2.2	AN2KViewFixedResolution	117
E.10	BiometricEvaluation::Finger::AN2KViewLatent Class Reference	118
E.10.1	Constructor & Destructor Documentation	118
E.10.1.1	AN2KViewLatent	119
E.10.1.2	AN2KViewLatent	119
E.10.2	Member Function Documentation	119
E.10.2.1	getLatentQualityMetric	119
E.11	BiometricEvaluation::Finger::AN2KViewVariableResolution Class Reference	119
E.11.1	Detailed Description	120
E.11.2	Constructor & Destructor Documentation	121
E.11.2.1	AN2KViewVariableResolution	121
E.11.2.2	AN2KViewVariableResolution	121
E.11.3	Member Function Documentation	121
E.11.3.1	getPositions	121
E.11.3.2	getImpressionType	122
E.11.3.3	getPrintPositionCoordinates	122
E.11.3.4	convertPrintPositionCoordinate	122
E.11.3.5	getPositionDescriptors	122
E.11.3.6	parsePositionDescriptors	123
E.12	BiometricEvaluation::View::AN2KViewVariableResolution Class Reference	123
E.12.1	Detailed Description	124
E.12.2	Constructor & Destructor Documentation	124
E.12.2.1	AN2KViewVariableResolution	124
E.12.2.2	AN2KViewVariableResolution	125
E.12.3	Member Function Documentation	125
E.12.3.1	extractQuality	125
E.12.3.2	getSourceAgency	125
E.12.3.3	getCaptureDate	125
E.12.3.4	getComment	125
E.12.3.5	getUserDefinedField	126
E.12.3.6	parseUserDefinedField	126
E.12.3.7	getQualityMetric	126
E.13	BiometricEvaluation::Finger::ANSI2004View Class Reference	127
E.13.1	Detailed Description	128
E.13.2	Constructor & Destructor Documentation	128
E.13.2.1	ANSI2004View	128
E.13.2.2	ANSI2004View	128
E.13.3	Member Function Documentation	128
E.13.3.1	readCoreDeltaData	128
E.14	BiometricEvaluation::Finger::ANSI2007View Class Reference	129
E.14.1	Detailed Description	130

E.14.2	Constructor & Destructor Documentation	130
E.14.2.1	ANSI2007View	130
E.14.2.2	ANSI2007View	130
E.14.3	Member Function Documentation	131
E.14.3.1	readCoreDeltaData	131
E.15	BiometricEvaluation::IO::ArchiveRecordStore Class Reference	131
E.15.1	Detailed Description	132
E.15.2	Constructor & Destructor Documentation	133
E.15.2.1	ArchiveRecordStore	133
E.15.2.2	ArchiveRecordStore	133
E.15.2.3	~ArchiveRecordStore	133
E.15.3	Member Function Documentation	134
E.15.3.1	getSpaceUsed	134
E.15.3.2	sync	134
E.15.3.3	insert	134
E.15.3.4	remove	135
E.15.3.5	read	135
E.15.3.6	replace	135
E.15.3.7	length	136
E.15.3.8	flush	136
E.15.3.9	sequence	137
E.15.3.10	setCursorAtKey	137
E.15.3.11	changeName	138
E.15.3.12	needsVacuum	138
E.15.3.13	needsVacuum	138
E.15.3.14	vacuum	139
E.15.3.15	getArchiveName	139
E.15.3.16	getManifestName	139
E.15.4	Member Data Documentation	139
E.15.4.1	OFFSET_RECORD_REMOVED	139
E.16	BiometricEvaluation::Memory::AutoArray< T > Class Template Reference	139
E.16.1	Detailed Description	141
E.16.2	Member Typedef Documentation	141
E.16.2.1	value_type	141
E.16.2.2	size_type	141
E.16.2.3	iterator	141
E.16.2.4	const_iterator	141
E.16.2.5	reference	141
E.16.2.6	const_reference	141
E.16.3	Constructor & Destructor Documentation	141
E.16.3.1	AutoArray	142
E.16.3.2	AutoArray	142
E.16.3.3	~AutoArray	142
E.16.4	Member Function Documentation	142
E.16.4.1	operator T *	142
E.16.4.2	operator const T *	142
E.16.4.3	operator[]	143
E.16.4.4	operator[]	143
E.16.4.5	at	143
E.16.4.6	at	144
E.16.4.7	begin	144

E.16.4.8	begin	144
E.16.4.9	end	144
E.16.4.10	end	145
E.16.4.11	size	145
E.16.4.12	resize	145
E.16.4.13	copy	145
E.16.4.14	copy	146
E.16.4.15	swap	146
E.16.4.16	swap	146
E.16.4.17	operator=	146
E.17	BiometricEvaluation::Memory::AutoBuffer< T > Class Template Reference	147
E.17.1	Member Typedef Documentation	147
E.17.1.1	value_type	147
E.18	BiometricEvaluation::DataInterchange::AN2KRecord::CharacterSet Struct Reference	148
E.18.1	Constructor & Destructor Documentation	148
E.18.1.1	CharacterSet	148
E.18.2	Member Data Documentation	148
E.18.2.1	identifier	148
E.18.2.2	commonName	149
E.18.2.3	version	149
E.19	BiometricEvaluation::IO::CompressedRecordStore Class Reference	149
E.19.1	Detailed Description	150
E.19.2	Constructor & Destructor Documentation	150
E.19.2.1	CompressedRecordStore	150
E.19.2.2	CompressedRecordStore	150
E.19.2.3	CompressedRecordStore	151
E.19.3	Member Function Documentation	151
E.19.3.1	getSpaceUsed	151
E.19.3.2	sync	152
E.19.3.3	insert	152
E.19.3.4	remove	152
E.19.3.5	read	153
E.19.3.6	replace	153
E.19.3.7	length	153
E.19.3.8	flush	154
E.19.3.9	sequence	154
E.19.3.10	setCursorAtKey	155
E.19.3.11	changeName	155
E.19.4	Member Data Documentation	155
E.19.4.1	BACKING_STORE	156
E.19.4.2	COMPRESSOR_TYPE_KEY	156
E.20	BiometricEvaluation::Image::CompressionAlgorithm Class Reference	156
E.20.1	Detailed Description	156
E.21	BiometricEvaluation::IO::Compressor Class Reference	156
E.21.1	Detailed Description	158
E.21.2	Member Enumeration Documentation	158
E.21.2.1	Kind	158
E.21.3	Constructor & Destructor Documentation	158
E.21.3.1	Compressor	158
E.21.3.2	~Compressor	158
E.21.4	Member Function Documentation	158

E.21.4.1	kindToString	158
E.21.4.2	stringToKind	159
E.21.4.3	compress	159
E.21.4.4	compress	160
E.21.4.5	compress	160
E.21.4.6	compress	161
E.21.4.7	compress	161
E.21.4.8	compress	161
E.21.4.9	decompress	162
E.21.4.10	decompress	162
E.21.4.11	decompress	163
E.21.4.12	decompress	163
E.21.4.13	decompress	164
E.21.4.14	decompress	164
E.21.4.15	setOption	164
E.21.4.16	setOption	165
E.21.4.17	getOption	165
E.21.4.18	getOptionAsInteger	165
E.21.4.19	removeOption	166
E.21.4.20	createCompressor	166
E.21.5	Member Data Documentation	166
E.21.5.1	GZIPTYPE	166
E.22	BiometricEvaluation::Error::ConversionError Class Reference	166
E.22.1	Detailed Description	167
E.22.2	Constructor & Destructor Documentation	167
E.22.2.1	ConversionError	167
E.22.2.2	ConversionError	167
E.23	BiometricEvaluation::Image::Coordinate Struct Reference	167
E.23.1	Detailed Description	168
E.23.2	Constructor & Destructor Documentation	168
E.23.2.1	Coordinate	168
E.23.3	Member Data Documentation	168
E.23.3.1	x	168
E.23.3.2	y	168
E.23.3.3	xDistance	168
E.23.3.4	yDistance	168
E.24	BiometricEvaluation::Feature::CorePoint Struct Reference	168
E.24.1	Detailed Description	169
E.25	BiometricEvaluation::Error::DataError Class Reference	169
E.25.1	Detailed Description	169
E.25.2	Constructor & Destructor Documentation	169
E.25.2.1	DataError	169
E.25.2.2	DataError	169
E.26	BiometricEvaluation::IO::DBRecordStore Class Reference	170
E.26.1	Detailed Description	170
E.26.2	Constructor & Destructor Documentation	171
E.26.2.1	DBRecordStore	171
E.26.2.2	DBRecordStore	171
E.26.3	Member Function Documentation	171
E.26.3.1	getSpaceUsed	171
E.26.3.2	sync	172

E.26.3.3	insert	172
E.26.3.4	remove	172
E.26.3.5	read	173
E.26.3.6	replace	173
E.26.3.7	length	173
E.26.3.8	flush	174
E.26.3.9	sequence	174
E.26.3.10	setCursorAtKey	175
E.26.3.11	changeName	175
E.27	BiometricEvaluation::Feature::DeltaPoint Struct Reference	176
E.27.1	Detailed Description	176
E.28	BiometricEvaluation::View::AN2KView::DeviceMonitoringMode Class Reference	176
E.28.1	Detailed Description	176
E.28.2	Member Enumeration Documentation	177
E.28.2.1	Kind	177
E.29	BiometricEvaluation::DataInterchange::AN2KRecord::DomainName Struct Reference	177
E.29.1	Detailed Description	177
E.29.2	Constructor & Destructor Documentation	177
E.29.2.1	DomainName	177
E.29.3	Member Data Documentation	178
E.29.3.1	identifier	178
E.29.3.2	version	178
E.30	BiometricEvaluation::Feature::AN2K7Minutiae::EncodingMethod Class Reference	178
E.30.1	Detailed Description	178
E.31	BiometricEvaluation::Feature::AN2K7Minutiae::PatternClassification::Entry Struct Reference	178
E.31.1	Constructor & Destructor Documentation	178
E.31.1.1	Entry	178
E.31.2	Member Data Documentation	179
E.31.2.1	standard	179
E.31.2.2	code	179
E.32	BiometricEvaluation::Error::Exception Class Reference	179
E.32.1	Detailed Description	180
E.32.2	Constructor & Destructor Documentation	180
E.32.2.1	Exception	180
E.32.2.2	Exception	181
E.32.3	Member Function Documentation	181
E.32.3.1	getInfo	181
E.33	BiometricEvaluation::Error::FileError Class Reference	181
E.33.1	Detailed Description	181
E.33.2	Constructor & Destructor Documentation	181
E.33.2.1	FileError	181
E.33.2.2	FileError	182
E.34	BiometricEvaluation::IO::FileRecordStore Class Reference	182
E.34.1	Detailed Description	183
E.34.2	Constructor & Destructor Documentation	183
E.34.2.1	FileRecordStore	183
E.34.2.2	FileRecordStore	183
E.34.3	Member Function Documentation	184
E.34.3.1	getSpaceUsed	184
E.34.3.2	insert	184
E.34.3.3	remove	184

E.34.3.4	read	185
E.34.3.5	replace	185
E.34.3.6	length	186
E.34.3.7	flush	186
E.34.3.8	sequence	186
E.34.3.9	setCursorAtKey	187
E.34.3.10	changeName	187
E.35	BiometricEvaluation::Finger::FingerImageCode Class Reference	188
E.35.1	Detailed Description	188
E.36	BiometricEvaluation::Feature::AN2K7Minutiae::FingerprintReadingSystem Struct Reference	188
E.36.1	Detailed Description	188
E.36.2	Member Data Documentation	188
E.36.2.1	name	188
E.36.2.2	method	189
E.36.2.3	equipment	189
E.37	BiometricEvaluation::Finger::AN2KViewCapture::FingerSegmentPosition Struct Reference	189
E.37.1	Detailed Description	189
E.37.2	Constructor & Destructor Documentation	189
E.37.2.1	FingerSegmentPosition	189
E.37.3	Member Data Documentation	189
E.37.3.1	fingerPosition	190
E.37.3.2	coordinates	190
E.38	BiometricEvaluation::Process::ForkManager Class Reference	190
E.38.1	Detailed Description	191
E.38.2	Constructor & Destructor Documentation	191
E.38.2.1	ForkManager	191
E.38.3	Member Function Documentation	191
E.38.3.1	addWorker	191
E.38.3.2	startWorkers	191
E.38.3.3	startWorker	192
E.38.3.4	stopWorker	192
E.38.3.5	broadcastSignal	193
E.38.3.6	responsibleFor	193
E.38.3.7	setNotWorking	193
E.38.3.8	getIsWorkingStatus	193
E.38.4	Member Data Documentation	194
E.38.4.1	FORKMANAGERS	194
E.39	BiometricEvaluation::Process::ForkWorkerController Class Reference	194
E.39.1	Detailed Description	195
E.39.2	Member Function Documentation	195
E.39.2.1	isWorking	195
E.39.2.2	reset	195
E.39.2.3	getPID	195
E.39.2.4	_stop	196
E.39.3	Friends And Related Function Documentation	196
E.39.3.1	ForkManager::startWorkers	196
E.39.3.2	ForkManager::startWorker	196
E.39.3.3	ForkManager::stopWorker	197
E.39.3.4	ForkManager::addWorker	197
E.40	BiometricEvaluation::IO::GZip Class Reference	197
E.40.1	Detailed Description	199

E.40.2	Member Function Documentation	199
E.40.2.1	compress	199
E.40.2.2	compress	199
E.40.2.3	compress	200
E.40.2.4	compress	200
E.40.2.5	compress	201
E.40.2.6	compress	201
E.40.2.7	decompress	202
E.40.2.8	decompress	202
E.40.2.9	decompress	202
E.40.2.10	decompress	203
E.40.2.11	decompress	203
E.40.2.12	decompress	204
E.40.3	Member Data Documentation	204
E.40.3.1	COMPRESSION_LEVEL	204
E.40.3.2	COMPRESSION_STRATEGY	204
E.40.3.3	COMPRESSION_METHOD	204
E.40.3.4	INPUT_DATA_TYPE	204
E.40.3.5	WINDOW_BITS	204
E.40.3.6	MEMORY_LEVEL	205
E.40.3.7	CHUNK_SIZE	205
E.41	BiometricEvaluation::Image::Image Class Reference	205
E.41.1	Detailed Description	206
E.41.2	Constructor & Destructor Documentation	207
E.41.2.1	Image	207
E.41.2.2	Image	207
E.41.3	Member Function Documentation	207
E.41.3.1	getCompressionAlgorithm	207
E.41.3.2	getResolution	208
E.41.3.3	getData	208
E.41.3.4	getRawData	208
E.41.3.5	getRawGrayscaleData	208
E.41.3.6	getDimensions	209
E.41.3.7	getDepth	209
E.41.3.8	valueInColorspace	209
E.41.3.9	openImage	210
E.41.3.10	openImage	210
E.41.3.11	openImage	210
E.41.3.12	getCompressionAlgorithm	211
E.41.3.13	getCompressionAlgorithm	211
E.41.3.14	getCompressionAlgorithm	212
E.41.3.15	setResolution	212
E.41.3.16	setDimensions	212
E.41.3.17	setDepth	213
E.41.4	Member Data Documentation	213
E.41.4.1	bitsPerComponent	213
E.41.4.2	_raw_data	213
E.42	BiometricEvaluation::Finger::Impression Class Reference	213
E.42.1	Detailed Description	213
E.43	BiometricEvaluation::Feature::INCITSMinutiae Class Reference	213
E.43.1	Detailed Description	215

E.43.2	Constructor & Destructor Documentation	216
E.43.2.1	INCITSMinutiae	216
E.43.3	Member Function Documentation	216
E.43.3.1	setMinutiaPoints	216
E.43.3.2	setRidgeCountItems	216
E.43.3.3	setCorePointSet	216
E.43.3.4	setDeltaPointSet	216
E.44	BiometricEvaluation::Finger::INCITSView Class Reference	217
E.44.1	Detailed Description	219
E.44.2	Constructor & Destructor Documentation	219
E.44.2.1	INCITSView	219
E.44.2.2	INCITSView	220
E.44.3	Member Function Documentation	220
E.44.3.1	convertPosition	220
E.44.3.2	convertImpression	221
E.44.3.3	getPosition	221
E.44.3.4	getImpressionType	221
E.44.3.5	getQuality	221
E.44.3.6	getCaptureEquipmentID	221
E.44.3.7	isAppendixFCompliant	222
E.44.3.8	getImage	222
E.44.3.9	getImageSize	222
E.44.3.10	getImageResolution	222
E.44.3.11	getImageDepth	222
E.44.3.12	getCompressionAlgorithm	222
E.44.3.13	getScanResolution	223
E.44.3.14	getFMRData	223
E.44.3.15	getFIRData	223
E.44.3.16	setMinutiaeData	223
E.44.3.17	setPosition	223
E.44.3.18	setImpressionType	224
E.44.3.19	setQuality	224
E.44.3.20	setViewNumber	224
E.44.3.21	setCaptureEquipmentID	224
E.44.3.22	setCBEFFProductIDs	224
E.44.3.23	setAppendixFCompliance	225
E.44.3.24	setImageSize	225
E.44.3.25	setImageResolution	225
E.44.3.26	setScanResolution	225
E.44.3.27	setImageData	225
E.44.3.28	readFMRHeader	226
E.44.3.29	readFVMR	226
E.44.3.30	readMinutiaeDataPoints	226
E.44.3.31	readExtendedDataBlock	227
E.44.3.32	readRidgeCountData	227
E.44.3.33	readCoreDeltaData	227
E.45	BiometricEvaluation::Memory::IndexedBuffer Class Reference	228
E.45.1	Detailed Description	229
E.45.2	Constructor & Destructor Documentation	229
E.45.2.1	IndexedBuffer	229
E.45.3	Member Function Documentation	229

E.45.3.1	getSize	229
E.45.3.2	getIndex	229
E.45.3.3	setIndex	230
E.45.3.4	scanU8Val	230
E.45.3.5	scanU16Val	230
E.45.3.6	scanBeU16Val	230
E.45.3.7	scanU32Val	231
E.45.3.8	scanBeU32Val	231
E.45.3.9	scanU64Val	231
E.45.3.10	scan	231
E.45.3.11	operator[]	232
E.45.3.12	operator[]	232
E.46	BiometricEvaluation::Finger::ISO2005View Class Reference	232
E.46.1	Detailed Description	233
E.46.2	Constructor & Destructor Documentation	234
E.46.2.1	ISO2005View	234
E.46.2.2	ISO2005View	234
E.46.3	Member Function Documentation	234
E.46.3.1	readCoreDeltaData	234
E.47	BiometricEvaluation::Image::JPEG Class Reference	235
E.47.1	Detailed Description	235
E.47.2	Member Function Documentation	235
E.47.2.1	getRawGrayscaleData	235
E.47.2.2	getRawData	236
E.47.2.3	isJPEG	236
E.48	BiometricEvaluation::Image::JPEG2000 Class Reference	237
E.48.1	Detailed Description	237
E.48.2	Constructor & Destructor Documentation	237
E.48.2.1	JPEG2000	237
E.48.3	Member Function Documentation	238
E.48.3.1	getRawData	238
E.48.3.2	getRawGrayscaleData	238
E.48.3.3	isJPEG2000	239
E.49	BiometricEvaluation::Image::JPEGGL Class Reference	239
E.49.1	Detailed Description	240
E.49.2	Member Function Documentation	240
E.49.2.1	getRawGrayscaleData	240
E.49.2.2	getRawData	240
E.49.2.3	isJPEGGL	241
E.50	BiometricEvaluation::IO::ListRecordStore Class Reference	241
E.50.1	Constructor & Destructor Documentation	242
E.50.1.1	ListRecordStore	242
E.50.1.2	~ListRecordStore	242
E.50.2	Member Function Documentation	242
E.50.2.1	insert	242
E.50.2.2	remove	242
E.50.2.3	read	243
E.50.2.4	replace	243
E.50.2.5	length	244
E.50.2.6	flush	244
E.50.2.7	sync	244

E.50.2.8	sequence	245
E.50.2.9	setCursorAtKey	245
E.50.2.10	changeName	246
E.50.2.11	getSpaceUsed	246
E.50.3	Member Data Documentation	246
E.50.3.1	SOURCERECORDSTOREPROPERTY	246
E.50.3.2	KEYLISTFILENAME	246
E.51	BiometricEvaluation::IO::LogCabinet Class Reference	247
E.51.1	Detailed Description	247
E.51.2	Constructor & Destructor Documentation	247
E.51.2.1	LogCabinet	247
E.51.2.2	LogCabinet	248
E.51.3	Member Function Documentation	248
E.51.3.1	newLogSheet	248
E.51.3.2	getName	248
E.51.3.3	getDescription	249
E.51.3.4	getCount	249
E.51.3.5	remove	249
E.52	BiometricEvaluation::IO::LogSheet Class Reference	249
E.52.1	Detailed Description	251
E.52.2	Constructor & Destructor Documentation	251
E.52.2.1	LogSheet	251
E.52.2.2	LogSheet	252
E.52.2.3	~LogSheet	252
E.52.2.4	LogSheet	252
E.52.3	Member Function Documentation	252
E.52.3.1	write	252
E.52.3.2	writeComment	253
E.52.3.3	newEntry	253
E.52.3.4	getCurrentEntry	253
E.52.3.5	resetCurrentEntry	253
E.52.3.6	getCurrentEntryNumber	253
E.52.3.7	sync	254
E.52.3.8	setAutoSync	254
E.52.3.9	sequence	254
E.52.3.10	trim	254
E.52.3.11	mergeLogSheets	255
E.52.3.12	operator=	255
E.52.3.13	updateCursor	255
E.52.4	Member Data Documentation	255
E.52.4.1	CommentDelimiter	255
E.52.4.2	EntryDelimiter	256
E.52.4.3	DescriptionTag	256
E.52.4.4	BE_LOGSHEET_SEQ_START	256
E.52.4.5	BE_LOGSHEET_SEQ_NEXT	256
E.52.4.6	_entryNumber	256
E.52.4.7	_theLogFile	256
E.52.4.8	_autoSync	256
E.52.4.9	_sequenceFile	256
E.52.4.10	_cursor	256
E.53	BiometricEvaluation::Process::Manager Class Reference	256

E.53.1	Detailed Description	258
E.53.2	Member Function Documentation	258
E.53.2.1	addWorker	258
E.53.2.2	getNumCompletedWorkers	258
E.53.2.3	getNumActiveWorkers	258
E.53.2.4	getTotalWorkers	259
E.53.2.5	startWorkers	259
E.53.2.6	startWorker	259
E.53.2.7	reset	260
E.53.2.8	stopWorker	260
E.53.2.9	waitForMessage	261
E.53.2.10	getNextMessage	261
E.53.2.11	broadcastMessage	261
E.53.3	Member Data Documentation	262
E.53.3.1	_workers	262
E.53.3.2	_pendingExit	262
E.54	BiometricEvaluation::IO::ManifestEntry Struct Reference	262
E.54.1	Detailed Description	262
E.54.2	Member Data Documentation	262
E.54.2.1	offset	262
E.54.2.2	size	262
E.55	BiometricEvaluation::Error::MemoryError Class Reference	262
E.55.1	Detailed Description	263
E.55.2	Constructor & Destructor Documentation	263
E.55.2.1	MemoryError	263
E.55.2.2	MemoryError	263
E.56	BiometricEvaluation::Feature::Minutiae Class Reference	263
E.56.1	Detailed Description	264
E.57	BiometricEvaluation::Feature::MinutiaeFormat Class Reference	264
E.57.1	Detailed Description	264
E.58	BiometricEvaluation::Feature::MinutiaeType Class Reference	264
E.58.1	Detailed Description	265
E.59	BiometricEvaluation::Feature::MinutiaPoint Struct Reference	265
E.59.1	Detailed Description	265
E.60	BiometricEvaluation::Image::NetPBM Class Reference	265
E.60.1	Detailed Description	266
E.60.2	Member Function Documentation	266
E.60.2.1	getRawData	266
E.60.2.2	getRawGrayscaleData	267
E.60.2.3	isNetPBM	267
E.60.2.4	skipLine	268
E.60.2.5	skipComment	268
E.60.2.6	getNextValue	268
E.60.2.7	ASCIIBitmapTo8Bit	269
E.60.2.8	ASCIIPixmapToBinaryPixmap	269
E.60.2.9	BinaryBitmapTo8Bit	270
E.61	BiometricEvaluation::Error::NotImplemented Class Reference	270
E.61.1	Detailed Description	270
E.61.2	Constructor & Destructor Documentation	270
E.61.2.1	NotImplemented	271
E.61.2.2	NotImplemented	271

E.62	BiometricEvaluation::Error::ObjectDoesNotExist Class Reference	271
E.62.1	Detailed Description	271
E.62.2	Constructor & Destructor Documentation	271
E.62.2.1	ObjectDoesNotExist	271
E.62.2.2	ObjectDoesNotExist	271
E.63	BiometricEvaluation::Error::ObjectExists Class Reference	271
E.63.1	Detailed Description	272
E.63.2	Constructor & Destructor Documentation	272
E.63.2.1	ObjectExists	272
E.63.2.2	ObjectExists	272
E.64	BiometricEvaluation::Error::ObjectIsClosed Class Reference	272
E.64.1	Detailed Description	273
E.64.2	Constructor & Destructor Documentation	273
E.64.2.1	ObjectIsClosed	273
E.64.2.2	ObjectIsClosed	273
E.65	BiometricEvaluation::Error::ObjectIsOpen Class Reference	273
E.65.1	Detailed Description	273
E.65.2	Constructor & Destructor Documentation	273
E.65.2.1	ObjectIsOpen	273
E.65.2.2	ObjectIsOpen	274
E.66	BiometricEvaluation::Memory::OrderedMap< Key, T > Class Template Reference	274
E.66.1	Detailed Description	275
E.66.2	Constructor & Destructor Documentation	275
E.66.2.1	OrderedMap	275
E.66.2.2	~OrderedMap	275
E.66.3	Member Function Documentation	275
E.66.3.1	push_back	275
E.66.3.2	erase	276
E.66.3.3	erase	276
E.66.3.4	begin	276
E.66.3.5	begin	276
E.66.3.6	end	276
E.66.3.7	end	276
E.66.3.8	size	277
E.66.3.9	keyExists	277
E.66.3.10	find	277
E.66.3.11	operator[]	277
E.67	BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T > Class Template Reference	278
E.67.1	Detailed Description	279
E.67.2	Constructor & Destructor Documentation	279
E.67.2.1	OrderedMapConstIterator	279
E.67.2.2	OrderedMapConstIterator	279
E.67.2.3	~OrderedMapConstIterator	279
E.67.3	Member Function Documentation	279
E.67.3.1	operator*	279
E.67.3.2	operator->	280
E.67.3.3	operator++	280
E.67.3.4	operator++	280
E.67.3.5	operator--	280
E.67.3.6	operator--	280
E.67.3.7	operator==	280

E.67.3.8	operator!=	281
E.68	BiometricEvaluation::Memory::OrderedMapIterator< Key, T > Class Template Reference	281
E.68.1	Detailed Description	282
E.68.2	Constructor & Destructor Documentation	282
E.68.2.1	OrderedMapIterator	282
E.68.2.2	~OrderedMapIterator	282
E.68.3	Member Function Documentation	282
E.68.3.1	operator*	282
E.68.3.2	operator->	283
E.68.3.3	operator++	283
E.68.3.4	operator++	283
E.68.3.5	operator--	283
E.68.3.6	operator--	283
E.68.3.7	operator==	283
E.68.3.8	operator!=	283
E.69	BiometricEvaluation::Error::ParameterError Class Reference	284
E.69.1	Detailed Description	284
E.69.2	Constructor & Destructor Documentation	284
E.69.2.1	ParameterError	284
E.69.2.2	ParameterError	284
E.70	BiometricEvaluation::Finger::PatternClassification Class Reference	284
E.70.1	Detailed Description	285
E.71	BiometricEvaluation::Feature::AN2K7Minutiae::PatternClassification Class Reference	285
E.71.1	Detailed Description	285
E.72	BiometricEvaluation::Image::PNG Class Reference	285
E.72.1	Detailed Description	286
E.72.2	Member Function Documentation	286
E.72.2.1	getRawData	286
E.72.2.2	getRawGrayscaleData	286
E.72.2.3	isPNG	287
E.73	BiometricEvaluation::Finger::Position Class Reference	287
E.73.1	Detailed Description	288
E.74	BiometricEvaluation::Process::POSIXThreadManager Class Reference	288
E.74.1	Detailed Description	288
E.74.2	Constructor & Destructor Documentation	288
E.74.2.1	POSIXThreadManager	289
E.74.3	Member Function Documentation	289
E.74.3.1	addWorker	289
E.74.3.2	startWorkers	289
E.74.3.3	startWorker	289
E.74.3.4	stopWorker	290
E.75	BiometricEvaluation::Process::POSIXThreadWorkerController Class Reference	290
E.75.1	Detailed Description	291
E.75.2	Member Function Documentation	291
E.75.2.1	reset	291
E.75.2.2	isWorking	291
E.76	BiometricEvaluation::Finger::AN2KViewVariableResolution::PrintPositionCoordinate Struct Reference	291
E.76.1	Detailed Description	292
E.76.2	Constructor & Destructor Documentation	292
E.76.2.1	PrintPositionCoordinate	292

E.76.3	Member Data Documentation	292
E.76.3.1	fingerView	292
E.76.3.2	segment	292
E.76.3.3	coordinates	292
E.77	BiometricEvaluation::IO::Properties Class Reference	293
E.77.1	Detailed Description	294
E.77.2	Member Typedef Documentation	294
E.77.2.1	const_iterator	294
E.77.3	Constructor & Destructor Documentation	294
E.77.3.1	Properties	294
E.77.3.2	Properties	294
E.77.3.3	~Properties	295
E.77.4	Member Function Documentation	295
E.77.4.1	setProperty	295
E.77.4.2	setPropertyFromInteger	295
E.77.4.3	setPropertyFromDouble	295
E.77.4.4	removeProperty	296
E.77.4.5	getProperty	296
E.77.4.6	getPropertyAsInteger	296
E.77.4.7	getPropertyAsDouble	297
E.77.4.8	begin	297
E.77.4.9	end	297
E.77.4.10	getMode	297
E.77.4.11	initWithBuffer	298
E.77.4.12	initWithBuffer	298
E.78	BiometricEvaluation::IO::PropertiesFile Class Reference	298
E.78.1	Detailed Description	299
E.78.2	Constructor & Destructor Documentation	299
E.78.2.1	PropertiesFile	299
E.78.2.2	~PropertiesFile	300
E.78.3	Member Function Documentation	300
E.78.3.1	sync	300
E.78.3.2	changeName	300
E.79	BiometricEvaluation::Image::Raw Class Reference	300
E.79.1	Detailed Description	301
E.79.2	Member Function Documentation	301
E.79.2.1	getRawData	301
E.79.2.2	getRawGrayscaleData	301
E.80	BiometricEvaluation::IO::RecordStore Class Reference	302
E.80.1	Detailed Description	304
E.80.2	Constructor & Destructor Documentation	305
E.80.2.1	RecordStore	305
E.80.2.2	RecordStore	305
E.80.3	Member Function Documentation	305
E.80.3.1	getName	305
E.80.3.2	getDescription	306
E.80.3.3	getCount	306
E.80.3.4	changeName	306
E.80.3.5	changeDescription	306
E.80.3.6	getSpaceUsed	307
E.80.3.7	sync	307

E.80.3.8	insert	307
E.80.3.9	insert	308
E.80.3.10	remove	308
E.80.3.11	read	308
E.80.3.12	read	309
E.80.3.13	replace	309
E.80.3.14	replace	310
E.80.3.15	length	310
E.80.3.16	flush	311
E.80.3.17	sequence	311
E.80.3.18	sequence	312
E.80.3.19	setCursorAtKey	312
E.80.3.20	openRecordStore	313
E.80.3.21	createRecordStore	313
E.80.3.22	removeRecordStore	314
E.80.3.23	mergeRecordStores	314
E.80.3.24	containsKey	315
E.80.3.25	genKeySegName	315
E.80.3.26	setProperties	315
E.80.3.27	getProperties	316
E.80.4	Member Data Documentation	316
E.80.4.1	INVALIDKEYCHARS	316
E.80.4.2	KEY_SEGMENT_SEPARATOR	316
E.80.4.3	KEY_SEGMENT_START	316
E.80.4.4	CONTROLFILENAME	316
E.80.4.5	NAMEPROPERTY	316
E.80.4.6	DESCRIPTIONPROPERTY	316
E.80.4.7	COUNTPROPERTY	316
E.80.4.8	TYPEPROPERTY	316
E.80.4.9	BERKELEYDBTYPE	317
E.80.4.10	ARCHIVETYPE	317
E.80.4.11	FILETYPE	317
E.80.4.12	SQLITETYPE	317
E.80.4.13	COMPRESSEDTYPE	317
E.80.4.14	LISTTYPE	317
E.80.4.15	DEFAULTTYPE	317
E.80.4.16	RSREADONLYERROR	317
E.80.4.17	BE_RECSTORE_SEQ_START	317
E.80.4.18	BE_RECSTORE_SEQ_NEXT	317
E.81	BiometricEvaluation::View::AN2KView::RecordType Class Reference	317
E.81.1	Detailed Description	318
E.82	BiometricEvaluation::Image::Resolution Struct Reference	318
E.82.1	Detailed Description	318
E.82.2	Member Enumeration Documentation	318
E.82.2.1	Kind	318
E.82.3	Constructor & Destructor Documentation	319
E.82.3.1	Resolution	319
E.82.4	Member Data Documentation	319
E.82.4.1	xRes	319
E.82.4.2	yRes	319
E.82.4.3	units	319

E.83 BiometricEvaluation::Feature::RidgeCountExtractionMethod Class Reference	319
E.83.1 Detailed Description	320
E.84 BiometricEvaluation::Feature::RidgeCountItem Struct Reference	320
E.84.1 Detailed Description	320
E.85 BiometricEvaluation::Error::SignalManager Class Reference	320
E.85.1 Detailed Description	321
E.85.2 Constructor & Destructor Documentation	321
E.85.2.1 SignalManager	321
E.85.2.2 SignalManager	321
E.85.3 Member Function Documentation	322
E.85.3.1 setSignalSet	322
E.85.3.2 clearSignalSet	322
E.85.3.3 setDefaultSignalSet	322
E.85.3.4 sigHandled	322
E.85.3.5 start	322
E.85.3.6 stop	323
E.85.3.7 setSigHandled	323
E.85.3.8 clearSigHandled	323
E.85.4 Member Data Documentation	323
E.85.4.1 _canSigJump	323
E.85.4.2 _sigJumpBuf	323
E.86 BiometricEvaluation::Image::Size Struct Reference	323
E.86.1 Detailed Description	324
E.86.2 Constructor & Destructor Documentation	324
E.86.2.1 Size	324
E.86.3 Member Data Documentation	324
E.86.3.1 xSize	324
E.86.3.2 ySize	324
E.87 BiometricEvaluation::IO::SQLiteRecordStore Class Reference	324
E.87.1 Detailed Description	326
E.87.2 Member Function Documentation	326
E.87.2.1 changeName	326
E.87.2.2 changeDescription	326
E.87.2.3 getSpaceUsed	326
E.87.2.4 insert	327
E.87.2.5 remove	327
E.87.2.6 read	327
E.87.2.7 replace	328
E.87.2.8 length	328
E.87.2.9 flush	329
E.87.2.10 sequence	329
E.87.2.11 setCursorAtKey	330
E.87.2.12 sqliteError	330
E.87.2.13 createStructure	330
E.87.2.14 validateKeyValueTable	330
E.87.2.15 createKeyValueTable	331
E.87.2.16 validateSchema	331
E.87.2.17 readSegments	331
E.87.2.18 cleanup	332
E.88 BiometricEvaluation::Process::Statistics Class Reference	332
E.88.1 Detailed Description	333

E.88.2	Constructor & Destructor Documentation	333
E.88.2.1	Statistics	333
E.88.2.2	Statistics	333
E.88.3	Member Function Documentation	333
E.88.3.1	getCPUTimes	333
E.88.3.2	getMemorySizes	334
E.88.3.3	getNumThreads	334
E.88.3.4	logStats	335
E.88.3.5	startAutoLogging	335
E.88.3.6	stopAutoLogging	336
E.88.3.7	callStatistics_logStats	336
E.89	BiometricEvaluation::Error::StrategyError Class Reference	336
E.89.1	Detailed Description	336
E.89.2	Constructor & Destructor Documentation	336
E.89.2.1	StrategyError	336
E.89.2.2	StrategyError	337
E.90	BiometricEvaluation::Time::Timer Class Reference	337
E.90.1	Detailed Description	337
E.90.2	Constructor & Destructor Documentation	337
E.90.2.1	Timer	337
E.90.3	Member Function Documentation	337
E.90.3.1	start	337
E.90.3.2	stop	338
E.90.3.3	elapsed	338
E.91	BiometricEvaluation::View::View Class Reference	338
E.91.1	Detailed Description	339
E.91.2	Member Function Documentation	339
E.91.2.1	getImage	339
E.91.2.2	getImageSize	339
E.91.2.3	getImageResolution	339
E.91.2.4	getImageDepth	339
E.91.2.5	getCompressionAlgorithm	340
E.91.2.6	getScanResolution	340
E.92	BiometricEvaluation::Time::Watchdog Class Reference	340
E.92.1	Detailed Description	341
E.92.2	Constructor & Destructor Documentation	341
E.92.2.1	Watchdog	341
E.92.3	Member Function Documentation	342
E.92.3.1	setInterval	342
E.92.3.2	start	342
E.92.3.3	stop	342
E.92.3.4	expired	342
E.92.3.5	setCanSigJump	343
E.92.3.6	clearCanSigJump	343
E.92.3.7	setExpired	343
E.92.3.8	clearExpired	343
E.92.4	Member Data Documentation	343
E.92.4.1	PROCESSTIME	343
E.92.4.2	REALTIME	343
E.93	BiometricEvaluation::Process::Worker Class Reference	343
E.93.1	Detailed Description	344

E.93.2	Member Function Documentation	344
E.93.2.1	workerMain	344
E.93.2.2	getParameter	345
E.93.2.3	getParameterAsDouble	345
E.93.2.4	getParameterAsInteger	345
E.93.2.5	getParameterAsString	346
E.93.2.6	setParameter	346
E.93.2.7	stop	346
E.93.2.8	closeWorkerPipeEnds	346
E.93.2.9	closeManagerPipeEnds	347
E.93.2.10	getSendingPipe	347
E.93.2.11	getReceivingPipe	347
E.93.2.12	sendMessageToManager	348
E.93.2.13	receiveMessageFromManager	348
E.93.2.14	_initCommunication	348
E.93.2.15	stopRequested	349
E.93.2.16	waitForMessage	349
E.94	BiometricEvaluation::Process::WorkerController Class Reference	349
E.94.1	Detailed Description	350
E.94.2	Constructor & Destructor Documentation	350
E.94.2.1	WorkerController	350
E.94.3	Member Function Documentation	350
E.94.3.1	sendMessageToWorker	350
E.94.3.2	setParameter	351
E.94.3.3	setParameterFromDouble	351
E.94.3.4	setParameterFromInteger	351
E.94.3.5	setParameterFromString	352
E.94.3.6	reset	352
E.94.3.7	isWorking	352
E.94.3.8	getWorker	352
E.94.4	Member Data Documentation	352
E.94.4.1	_worker	353
E.95	BiometricEvaluation::Image::WSQ Class Reference	353
E.95.1	Detailed Description	353
E.95.2	Member Function Documentation	353
E.95.2.1	getRawData	353
E.95.2.2	getRawGrayscaleData	354
E.95.2.3	isWSQ	354
F	Example Documentation	357
F.1	/Users/wsalamon/Work/p4-nigos/projects/EVALUATION/Main/common/src/include/be_io_listrecstore.h	357

Chapter 1

Introduction

This document describes the Biometric Evaluation Framework (BECOMMON) and application programming interfaces (API) used to support the evaluation of biometric software within the NIST Image Group [13].

1.1 Rationale

When evaluating software in a “black box” fashion many aspects of program execution must be addressed, such as non-returning function calls, I/O errors, and other resource requirements. In addition, solutions to common problems should be portable across operating systems.

An evaluation consists of the testing of vendor-supplied software that implements certain biometric algorithms, such as fingerprint matching or face recognition. The NIST Image Group defines a test process and API for each evaluation. Vendors implement the API in their software, which is delivered to NIST as a software library, where common test driver is used to call the vendor library to perform the biometric operation. In order to support the common functionality used across all evaluations, such as logging, file input/output, etc., a common framework is used.

Even though the Biometric Evaluation Framework was written to support biometric software evaluations, much of the framework can be used for any general purpose programs where data storage and system interaction are needed. One goal of the BECOMMON is to reduce the low-level error processing (particularly with input and output) done directly by applications. The Biometric Evaluation Framework provides several abstractions that are useful to applications so they can focus on the task at hand.

This document describes the BECOMMON in two sections: Chapters containing descriptions of each package as well as code examples, and reference sections containing auto-generated API documentation.

The BECOMMON is a work-in-progress, and future development will occur in areas where the need arises for the testing programs of the NIST Image Group.

Chapter 2

Overview

The Biometric Evaluation Framework (BECCommon) is a set of C++[15] classes, error codes, and design patterns used to create a common environment to provide logging, data management, error handling, and other functionality that is needed for many applications used in the testing of biometric software. The goals of the framework include:

- Reduce the amount of I/O error handling implemented by applications.
- Provide standard interfaces for data management and logging;
- Remove the need for applications to handle low-level events from the operating system (signals, etc.);
- Provide services for timing the execution of code blocks;
- Allow applications to constrain the amount of processing time used by a block of code.

The experience of the NIST Image Group when running many software evaluations has led to the need of a common code for dealing with recurring software issues. One issue is the large amounts of data consumed, and created, by the software under test. Input data sets are typically biometric images, while output sets contain derived information. Both sets of data often contain millions of items, and storing each item as a file creates a tremendous burden on the file system. The *IO* package provides a solution to managing large amounts of records in a portable, efficient manner, as well as facilities for logging and maintaining runtime settings.

BECCommon is divided into several packages, each providing a set of related functionality, such as error handling and timing operations. The packages are an informal concept, mapped to formal C++ name spaces, e.g. *IO* and *Time*. A namespace contains classes, constants, and non-class functions that relate to concepts grouped in the namespace. All classes within BECCommon belong to the top-level *BiometricEvaluation* namespace.

Biometric image data is often supplied in a compressed format (e.g. WSQ, JPEG) and must be converted to a “raw” format. The *Image* package contains classes to represent compressed image data as an object, storing the image size and other attributes, in addition to the raw image.

Memory management issues are addressed by the *Memory* package. The use of classes and templates in this package can relieve applications of the need to directly manage memory for dynamically sized arrays, or call functions that are already provided to allocate and free C library objects.

While a program is running, it is often necessary to record certain statistics about the process, such as memory and processor usage. The *Process* package provides methods to obtain this information, as well as the capability to log to a file periodically, in an asynchronous manner.

In addition to its own statistics, a program may need to query some information about the environment under which it is running. The `System` package provides a count of CPUs, memory size, other system characteristics that an application can use to tailor its behavior.

Many aspects of software performance evaluation involve the use of timers. The `Time` package provides for the calculation of a time interval in a manner that is consistent across platforms, abstracting the underlying operating system's timing facility. Also, included is a "watchdog" facility, providing a solution to the problem of non-returning function calls. By using a watchdog timer, an application can abort a call to a function that doesn't return in the required interval.

The `Text` package provides a set of utility functions for operating on strings. The `digest` functions are of interest to those applications that must mask any information contained in a string before passing that information to another function. For example, often the biometric image file (or record) names contain information about the image, such as the finger position.

Error propagation and handling are addressed by the `Error` package. A set of exception objects are defined within this package, allowing for communication of error conditions out of the framework to the application, along with an explanatory string. Signal handling is related to error propagation in that when a process receives a signal, often it is due to software bug. Divide by zero, for example. The `Error` package provides for simple handling of the signal by the process.

Many packages in `BECommon` deal with biometric data record formats, including ANSI/NIST [3] records. In order to provide a general interface to several formats, `BECommon` represents the biometric data as derived from a source. For example, the `Finger` package contains classes that represent all information about a finger, including the source image and derived minutiae points. The `View` package combines the notions of a source image and derived information together into a single abstraction.

`BECommon` is designed to be used in a modular fashion, and it is possible to compile many packages independently. However, several packages do make use of other packages in the framework, and therefore, are less flexible in their reuse. However, `BECommon` is designed to reduce the intra-framework dependencies.

A set of test programs is included with the framework. These programs not only exercise the functions provided by the packages, but also can be used as example programs on how to use framework.

The chapters that follow this overview describe each package in detail, along with some code examples. The final set of chapters of this document contain the application programming interfaces for the types, methods, and classes that make up `BECommon`. However, the framework is under development, and other packages, classes, etc. will be added over time to address the needs of the NIST Image Group.

Chapter 3

Framework

The `Framework` package is used to retrieve information about the Biometric Evaluation Framework itself. Version numbers, the compiler used, and other information can be queried by applications. Versioning information is recorded in the `BECommon Makefile` and populated in the function implementation at compile-time.

Listing 3.1: Using the Framework API

```
1 #include <iostream>
2
3 #include <be_framework.h>
4
5 using namespace BiometricEvaluation;
6 using namespace std;
7
8 int
9 main(
10     int argc,
11     char* argv[])
12 {
13     cout << "Framework Version: ";
14     cout << Framework::getMajorVersion() << "." <<
15         Framework::getMinorVersion() << endl;
16     /* "Framework Version: 0.4" */
17
18     cout << "Compiler Used: ";
19     cout << Framework::getCompiler() << " v" <<
20         Framework::getCompilerVersion() << endl;
21     /* "Compiler Used: clang v3.0.0" */
22
23     cout << "Date/Time Compiled: ";
24     cout << Framework::getCompileDate() << " " <<
25         Framework::getCompileTime() << endl;
26     /* "Date/Time Compiled: Jan 24 2012 12:16:01" */
27
28     return (EXIT_SUCCESS);
29 }
```


Chapter 4

Memory

To assist applications with memory management, the `Memory` package provides classes to wrap C memory allocations, and other dynamically-sized objects.

4.1 AutoBuffer

The Biometric Evaluation Framework is designed to interoperate with existing C code that has its own memory management techniques, e.g. NIST Biometric Image Software [12]. In these cases, functions exist to allocate and free blocks of memory, and these calls must be made by the applications which use those libraries. To assist BECommon clients that use these existing libraries, the `AutoBuffer` class wraps the C memory management functions, guaranteeing the release of C objects when the `AutoBuffer` goes out of scope.

The `AutoBuffer` constructor takes three function pointers as parameters: one for C object construction, one for destruction, and a third, optional, function for copying the C object. If the latter is passed a `NULL`, the `AutoBuffer` and the underlying C object cannot be copied, and an exception will be thrown.

Listing 4.1 shows the use of `AutoBuffer` to wrap the memory allocation routines that are part of the NIST Biometric Image Software ANSI/NIST library.

Listing 4.1: Using the `AutoBuffer`

```
1 #include <be_memory_autobuffer.h>
2 #include <iostream>
3 extern "C" {
4     #include <an2k.h>
5 }
6
7 int
8 main(int argc, char* argv[]) {
9
10
11     /*
12      * alloc_ANSI_NIST(), free_ANSI_NIST(), and copy_ANSI_NIST()
13      * are functions in the NBIS AN2K library.
14      */
15     Memory::AutoBuffer<ANSI_NIST> an2k =
16         Memory::AutoBuffer<ANSI_NIST>(&alloc_ANSI_NIST,
17                                         &free_ANSI_NIST, &copy_ANSI_NIST);
```

```

18 |     if (read_ANSI_NIST(fp, an2k) != 0) {
19 |         cerr << "Could not read AN2K file." << endl;
20 |         return (EXIT_FAILURE);
21 |     }
22 |
23 |     for (int i = 1; i < an2k->num_records; i++) {
24 |         // process the ANSI/NIST record ...
25 |     }
26 | }

```

4.2 AutoArray

At its simplest level, `AutoArray` is a C-style array with numerous convenience methods, such as being able to query the number of elements. C++ iterators can be used over the contents of the array. The array can be resized without the need to create a new object. C++ operator overloading allows `AutoArray` objects to be passed to C-style functions that expect pointers to `AutoArray`'s template type.

`AutoArray` is used extensively in `BECommon` to help eliminate mistakes when manually allocating memory. The `AutoArray` constructor will allocate needed memory using `new` and the destructor will `delete` it. This ensures that any allocated memory will be appropriately freed when the `AutoArray` goes out of scope. Copy constructors and methods as well as the assignment operator all correctly manage memory so the client does not have to. Several objects in `BECommon` return `AutoArray` objects to assist clients in proper memory management.

A common use of `AutoArray` is to deal with records sequenced from a `RecordStore`. Listing 4.2 demonstrates this. Notice the omission of memory management statements – they are completely unnecessary.

Listing 4.2: Using `AutoArray`s with `RecordStore`s

```

1 | #include <be_io_dbrecstore.h>
2 | #include <be_memory_autoarray.h>
3 |
4 | #include <iostream>
5 |
6 | using namespace BiometricEvaluation;
7 |
8 | int
9 | main(
10 |     int argc,
11 |     char *argv[])
12 | {
13 |     IO::DBRecordStore rs("db_recstore", ".", IO::READONLY);
14 |
15 |     uint64_t value_size = 0;
16 |     string key("");
17 |     Memory::AutoArray<uint8_t> value;
18 |     for (bool stop = false; stop == false; ) {
19 |         try {
20 |             // Non-destructively resize the AutoArray to hold
21 |             // the next record.
22 |             value.resize(rs.sequence(key, NULL));
23 |
24 |             // Read the record into the AutoArray (treats the
25 |             // AutoArray as a pointer).

```



```

26         rs.read(key, value);
27
28         // Do something with value.
29         std::cout << "Key " << key << " has a value of " <<
30             value.size() << " bytes" << std::endl;
31     } catch (Error::ObjectDoesNotExist) {
32         stop = true;
33     }
34 }
35
36 return (0);
37 }

```

AutoArray is adapted from "c_array" [15, 496].

4.3 IndexedBuffer

Many applications have a need to read items from a data record and take action based on the value of the item read. For example, when reading a biometric data record, the number of finger minutiae points in the record is indicated by a value in the record header. Furthermore, the record format may be of a different endianness than the application's host platform.

The `IndexedBuffer` class is used to access data from a buffer in fixed-size amounts in sequence. Objects of this class maintain an index into the buffer as internal state and reads out of the buffer, when using certain methods, adjust the index. In addition, standard subscript access can be done on the buffer (reads and writes) without affecting the index. The basic element type is an unsigned eight-bit value. The `IndexedBuffer` object can be created to either manage the buffer memory directly, or to "wrap" an existing buffer.

Methods to retrieve elements from the buffer are defined in the class's interface. These functions are used to retrieve 8/16/32/64-bit values while moving the internal index. Several functions are also provided to take into account the endianness of the underlying data.

Listing 4.3 shows how an application can read a data record in big-endian format.

Listing 4.3: Using the `IndexedBuffer`

```

1 #include <be_memory_autoarray.h>
2 #include <be_memory_indexedbuffer.h>
3
4 int
5 main(int argc, char* argv[]) {
6
7     uint64_t size = IO::Utility::getFileSize("BiometricRecord");
8     FILE *fp = std::fopen("BiometricRecord", "rb");
9     Memory::IndexedBuffer iBuf(size);
10    fread(iBuf, 1, size, fp);
11    fclose(fp);
12    Memory::IndexedBuffer iBuf(recordData, recordData.size());
13
14    uint32_t lval;
15    uint16_t sval;
16
17    /*
18     * Record is big-endian:
19     * -----

```

```
20      * | NAME | LENGTH | ID |      ...      |
21      * -----
22      *      4      4      2
23      */
24
25      /* Read a 4-byte C string */
26      lval = iBuf.scanU32Val();          /* Format ID */
27      char *cptr = (char *)&lval;
28      string s(cptr);
29
30      /* Read a 4-byte length */
31      lval = iBuf.scanBeU32Val();
32
33      /* Read a 2-byte ID */
34      sval = iBuf.scanBeU16Val();
35 }
```

Chapter 5

Error Handling

Within the Biometric Evaluation Framework, Error handling has two aspects: One for communicating error conditions out of the framework and back to applications; the other for handling error signals from the environment and operating system. Classes and other code to implement error processing are described in this chapter.

5.1 Biometric Evaluation Exceptions

The Biometric Evaluation Framework contains a set of classes used to report errors to applications. Objects of these class types are thrown and contain descriptive information as to the nature of the error. Applications must handle the errors in a manner that makes sense for the application.

Applications should catch objects of the type specified in the API for the class being called. The type of object caught indicates the nature of the error that occurred, while the string stored within that object provides more information on the error.

Listing [6.2 on page 17](#) shows an example of exception handling when using the logging classes described in Section [6.3 on page 17](#).

5.2 Signal Handling

When the application process executes in a POSIX environment, signals to the process can be generated by the operating system. In many cases, if the signal is not handled by the process, execution terminates. Because the Biometric Evaluation Framework was designed to be used with software libraries for which no source code is available, changes to the code in these libraries cannot be made, and any faults in that code cannot be fixed. A common problem is that a function in the “black box” library dereferences a bad pointer, resulting in a segmentation violation signal being sent by the operating system.

To prevent termination of the application process, signal handling must be installed. The Biometric Evaluation Framework provides a class, `SignalManager`, to simplify the installation of a signal handler in order to allow the program to continue running. For example, when extracting a fingerprint minutia template from an image, often the library call will fault on a certain image. By using the `SignalManager`, the application can log that fault, and continue on to the next image.

Signal handling in a POSIX environment covers the bare essentials, and one of two actions is usually taken.

The signal can be handled and processing continues at the location the signal was generated. The second action is that, in addition to signal handling, the process continues from a different location. It is the second action that is implemented by the `SignalManager` class. The rationale for this type of signal handling is so the call to the faulting function can be aborted, but the caller can detect that the signal was handled and take action, usually by logging the fault.

By default, the `SignalManager` class installs a handler for the `SIGSEGV` and `SIGBUS` signals. However, other signals can be handled as desired.

One restriction on the use of `SignalManager` is that the POSIX calls for signal management (`signal(3)`, `sigaction(2)`, etc.) cannot be invoked inside of the signal handler block.

The example in Listing 5.1 shows application use of the `SignalManager` class.

Listing 5.1: Using the `SignalManager`

```

1 #include <be_error_signal_manager.h>
2 using namespace BiometricEvaluation;
3
4 int main(int argc, char *argv[])
5 {
6     Error::SignalManager *sigmgr = new Error::SignalManager();
7
8     BEGIN_SIGNAL_BLOCK(sigmgr, sigblock1);
9     // code that may result in signal generation
10    END_SIGNAL_BLOCK(sigmgr, sigblock1);
11    if (sigmgr->sigHandled()) {
12        // log the event, etc.
13    }
14 }
```

Within the `SignalManager` header file, two macros are defined: `BEGIN_SIGNAL_BLOCK()` and `END_SIGNAL_BLOCK()`, each taking the `SignalManager` object and label as parameters. The label must be unique for each signal block. These macros insert the jump buffer into the code, which is the location where the signal handler will jump to after handling the signal. The use of these macros greatly simplifies signal handling for the application, and it is recommended that applications use these macros instead of directly invoking the methods of the `SignalManager` class, except for changing the set of handled signals.

If a signal does occur, process control jumps to the end of the signal block, and the `sigHandled()` method of the signal manager can be called. The application may need to have the same statements inside the `sigHandled()` check as those outside of the signal handling block. For example, if a file needs to be closed before the end of the block, the same call to the close function must be made within the `sigHandled()` check. Careful application design can reduce the amount of code replication, however.

Listing 5.2 shows how an application can indicate what signals to handle. In this example, only the `SIGUSR1` signal would be handled.

Listing 5.2: Specifying Signals to the `SignalManager`

```

1 #include <be_error_signal_manager.h>
2 using namespace BiometricEvaluation;
3
4 int main(int argc, char *argv[])
5 {
6     Error::SignalManager *sigmgr = new Error::SignalManager();
7
8     sigset_t sigset;
```

```
9      sigemptyset(&sigset);
10     sigaddset(&sigset, SIGUSR1);
11     sigmgr->setSignalSet(sigset);
12
13     FILE *fp = fopen( ... );
14     BEGIN_SIGNAL_BLOCK(sigmgr, sigblock2);
15         // code that may result in signal generation
16         fclose(fp);
17     END_SIGNAL_BLOCK(asigmgr, sigblock2);
18     if (sigmgr->sigHandled()) {
19         cout << "SIGUSR1 occurred." << endl;
20         fclose(fp);
21     }
22 }
```


Chapter 6

Input/Output

The `IO` package is used by applications for the common types of input and output: managing stores of data, log files, and individual file management. The goal of using the `IO` API is to relieve applications of the need to manage low-level I/O operations such as file opening, writing, and error handling. Furthermore, by using the classes defined in `IO`, the actual storage mechanism used for data can be managed efficiently and placed in a consistent location for all applications.

Many classes manage persistent storage within the file system, taking care of file open and close operations, as well as error handling. When errors do occur, exceptions are thrown, which then must be handled by the application.

6.1 Utility

The `IO::Utility` namespace provides functions that are used to manipulate the file system and other low-level mechanisms. These functions can be used by applications in addition to being used by other classes within the Biometric Evaluation framework. The functions in this package are used to directly manipulate objects in the POSIX file system, or to check whether a file object exists.

6.2 Record Management

The `IO::RecordStore` class provides an abstraction for performing record-oriented input and output to an underlying storage system. Each implementation of the `RecordStore` provides a self-contained entity to manage data on behalf of the application in a reliable, efficient manner.

Many biometric evaluations generate thousands of files in the form of processed images and biometric templates, in addition to consuming large numbers of files as input. In many file systems, managing large numbers of files is not efficient, and leads to longer run times as well as difficulty in backing up and processing these files outside of the actual evaluation.

The `RecordStore` abstraction de-couples the application from the underlying storage, enabling the implementation of different strategies for data management. One simple strategy is to store each record into a separate file, reproducing what has typically been done in the evaluation software itself. Archive files and small databases are other implementation strategies that have been used.

Use of the `RecordStore` abstraction allows applications to switch storage strategy by changing a few lines

of code. Furthermore, error handling is consistent for all strategies by the use of common exceptions.

RecordStore s provide no semantic meaning to the nature of the data that passes through the store. Each record is an opaque object, given to the store as a pointer and data length, and is associated with a string the which is the key. Keys must be unique and are associated with a single record. Attempts to insert multiple records with the same key result in an exception being thrown.

Listing 6.1 illustrates the use of a database RecordStore within an application.

Listing 6.1: Using a RecordStore

```

1 #include <iostream>
2 #include <be_io_dbrecstore.h>
3 int
4 main(int argc, char* argv[]) {
5
6     IO::DBRecordStore *rs;
7     try {
8         rs = new IO::DBRecordStore("myRecords", "My Record Store", "");
9     } catch (Error::Exception& e) {
10         cout << "Caught " << e.getInfo() << endl;
11         return (EXIT_FAILURE);
12     }
13     auto_ptr<IO::DBRecordStore> ars(rs);
14
15     try {
16         uint8_t *theData;
17
18         theData = getSomeData();
19         ars->insert("key1", theData);
20
21         theData = getSomeData();
22         ars->insert("key2", theData);
23
24     } catch (Error::Exception& e) {
25         cout << "Caught " << e.getInfo() << endl;
26         return (EXIT_FAILURE);
27     }
28
29     // Some more processing where new data for a key comes in ...
30     theData = getSomeData();
31     ars->replace("key1", theData);
32
33     // Obtain the data for all keys ...
34     string theKey;
35     while (true) {
36         uint64_t len = rs->sequence(theKey, theData);
37         cout << "Read data for key " << theKey << " of length " << len << endl;
38     }
39     // The data for the key is no longer needed ...
40     ars->remove("key1");
41 }

```


6.3 Logging

Many applications are required to log information during their processing. In particular, the evaluation test drivers often create a log record for each call to the software under test. There is a need for the log entries to be consistent, yet any logging facility must be flexible in accepting the type of data that is to be written to the log file.

The logging classes in the `IO` package provide a straight-forward method for applications to record their progress without the need to manage the low-level output details. There are two classes, `IO::LogCabinet` and `IO::LogSheet` that are used to perform consistent logging of information by applications. A `LogCabinet` contains a set of `LogSheet`s.

A `LogSheet` is an output stream (subclass of `std::ostream`), and therefore can handle built-in types and any class that supports streaming. The example code in Listing 6.2 shows how an application can use a `LogSheet`, contained within a `LogCabinet`, to record operational information.

Log sheets are simple text files, with each entry numbered by the `LogSheet` class when written to the file. The description of the sheet is placed at the top of the file during construction of the `LogSheet` object. A call to the `newEntry()` method commits the current entry to the log file, and resets the write position to the beginning of the entry buffer.

In addition to streaming by using the `LogSheet::«` operator, applications can directly commit an entry to the log file by calling the `write()` method, thereby not disrupting the entry that is being formed. After an entry is committed, the entry number is automatically incremented.

The example in Listing 6.2 shows application use of the logging facility.

Listing 6.2: Using a `LogSheet` within a `LogCabinet`

```

1 #include <be_io_logcabinet.h>
2 using namespace BiometricEvaluation;
3 using namespace BiometricEvaluation::IO;
4
5 LogCabinet *lc;
6 try {
7     lc = new LogCabinet(lcname, "A Log Cabinet", "");
8 } catch (Error::ObjectExists &e) {
9     cout << "The Log Cabinet already exists." << endl;
10    return (-1);
11 } catch (Error::StrategyError& e) {
12    cout << "Caught " << e.getInfo() << endl;
13    return (-1);
14 }
15 auto_ptr<LogCabinet> alc(lc);
16 try {
17     ls = alc->newLogSheet(lsname, "Log Sheet in Cabinet");
18 } catch (Error::ObjectExists &e) {
19     cout << "The Log Sheet already exists." << endl;
20     return (-1);
21 } catch (Error::StrategyError& e) {
22     cout << "Caught " << e.getInfo() << endl;
23     return (-1);
24 }
25 ls->setAutoSync(true); // Force write of every entry when finished
26 int i = ...
27 *ls << "Adding an integer value " << i << " to the log." << endl;
28 ls->newEntry();        // Forces the write of the current entry

```

```

29| .....
30| delete ls;
31| return;                // The LogCabinet is destructed by the auto_ptr

```

6.4 Properties

The `Properties` class is used to store simple key-value string pairs, with the option to save to a file. Applications can use a `Properties` object to manage runtime settings that are persistent across invocations, or to simply store some settings in memory only.

Listing 6.3: Using a `Properties` Object

```

1| IO::Properties *props;
2| string fname = "test.prop";
3| try {
4|     props = new IO::Properties(fname);
5| } catch (Error::StrategyError &e) {
6|     cerr << "Caught " << e.getInfo() << endl;
7|     return;
8| } catch (Error::FileError& e) {
9|     cerr << "A file error occurred: " << e.getInfo() << endl;
10|    return;
11| }
12| props->setProperty("foo", "bar");
13| props->setProperty("theAnswer", "42");
14| :
15| :
16| :
17| try {
18|     int64_t theAnswer = props->getProperty("theAnswer");
19|     cout << "The answer is " << theAnswer << endl;
20| } catch (Error::ObjectDoesNotExist &e) {
21|     cerr << "The answer is elusive." << endl;
22|     return;
23| }
24| string fooProp = props->getProperty("foo");
25| cout << "Foo is set to " << fooProp << endl;
26| :
27| :
28| :
29| try {
30|     props->removeProperty("foo");
31| } catch (Error::ObjectDoesNotExist &e) {
32|     cerr << "Failed to remove property." << endl;
33| }

```

6.5 Compressor

Support for data compression and decompression can be found in the Biometric Evaluation Framework through the `Compressor` class hierarchy. `Compressor` is an abstract base class defining several pure-virtual methods for compression and decompression of buffers and files. Derived classes implement these methods and can

be instantiated through the factory method in the base class. As such, children should also be enumerated within `Compressor::Kind`. The Biometric Evaluation Framework comes with an example, GZIP, which compresses and decompresses the gzip format through interaction with `zlib` [4].

Listing 6.4: Using a Compressor Object

```
1 tr1::shared_ptr<IO::Compressor> compressor;
2 Memory::uint8Array compressedBuffer, largeBuffer = /* ... */;
3 try {
4     compressor = IO::Compressor::createCompressor(Compressor::Kind::GZIP);
5     /* Overloaded for all combination of buffer and file */
6     compressor->compress("largeInputFile", "compressedOutputFile");
7     compressedBuffer = compressor->compress(largeBuffer);
8 } catch (Error::Exception &e) {
9     cerr << "Could not compress (" << e.getInfo() << ')' << endl;
10 }
```

Different Compressor s may be able to respond to options that tune their operations. These options (and approved values) should be well-documented in the child class, however, a no-argument constructor of a child Compressor should automatically set any required options to default values. Setting and retrieving these options is very similar to interacting with a Properties object (see Section 6.4 on the facing page).

Listing 6.5: Setting Compressor Options

```
1 tr1::shared_ptr<IO::Compressor> compressor =
2     IO::Compressor::createCompressor(Compressor::Kind::GZIP);
3
4 /* A large GZIP chunk size can speed operations on systems with copious RAM */
5 compressor->setOption(IO::GZIP::CHUNK_SIZE, 32768);
```


Chapter 7

Time and Timing

The `Time` package within the Biometric Evaluation Framework provides a set of classes for performing timing-related operations, such as elapsed time and limiting execution time.

7.1 Elapsed Time

The `Timer` class provides applications a method to determine how long a block of code takes to execute. On many systems (e.g. Linux) the timer resolution is in microseconds.

Listing 7.1 shows how an application can use a `Timer` object to limit obtain the amount of time used for the execution of a block of code.

Listing 7.1: Using the `Timer`

```
1 #include <be_time_timer.h>
2
3 int main(int argc, char *argv[])
4 {
5     Time::Timer timer = new Time::Timer();
6
7     try {
8         atimer->start();
9         // do something useful, or not
10        atimer->stop();
11        cout << "Elapsed time: " << atimer->elapsed() << endl;
12    } catch (Error::StrategyError &e) {
13        cout << "Failed to create timer." << endl;
14    }
15 }
```

7.2 Limiting Execution Time

The `Watchdog` class allows applications to control the amount of time that a block of code has to execute. The time can be *real* (i.e. “wall”) time, or *process* time (not available on Windows). One typical usage for a

Watchdog timer is when a call is made to a function that may never return, due to problems processing an input biometric image.

Watchdog timers can be used in conjunction with `SignalManager` in order to both limit the processing time of a call, and handle all signals generated as a result of that call. See 5.2 for information on the `SignalManager` class.

One restriction on the use of Watchdog is that the POSIX calls for signal management (`signal(3)`, `sigaction(2)`, etc.) cannot be invoked inside of the WATCHDOG block. This restriction includes calls to `sleep(3)` because it is based on signal handling as well.

Listing 7.2 shows how an application can use a Watchdog object to limit the amount of process time for a block of code.

Listing 7.2: Using the Watchdog

```

1 #include <be_time_watchdog.h>
2 int main(int argc, char *argv[])
3
4     Time::Watchdog theDog = new Time::Watchdog(Time::Watchdog::PROCESSTIME);
5     theDog->setInterval(300);    // 300 microseconds
6
7     Time::Timer timer;
8
9     BEGIN_WATCHDOG_BLOCK(theDog, watchdogblock1);
10        timer.start();
11        // Do something that may take more than 300 usecs
12        timer.stop();
13        cout << "Total time was " << timer.elapsed() << endl;
14    END_WATCHDOG_BLOCK(theDog, watchdogblock1);
15    if (theDog->expired()) {
16        timer.stop();
17        cerr << "That took too long." << endl;
18    }
19 {
20 }
```

Within the Watchdog header file, two macros are defined: `BEGIN_WATCHDOG_BLOCK()` and `END_WATCHDOG_BLOCK()`, each taking the Watchdog object and label as parameters. The label must be unique for each WATCHDOG block. The use of these macros greatly simplifies Watchdog timers for the application, and it is recommended that applications use these macros instead of directly invoking the methods of the Watchdog class, except for setting the timeout value.

Any processing that is normally done at the end of the WATCHDOG block must also be done within the `expired()` check due to the fact that process control jumps to the end of the WATCHDOG block in the event of a timeout. A typical example is the use of the `Timer` object inside a WATCHDOG block, as the example in Listing 7.2 shows. In most cases, however, careful application design can remove the need for duplicate code. In the example, placing the `Timer start()/stop()` calls outside of the WATCHDOG block simplifies the coding, although the small amount of time for the WATCHDOG setup and tear down would be included in the time.

Chapter 8

Process Information

The `Process` package is a set of APIs used to gather information on a process, limit the capabilities of a process, and create manage processes.

8.1 Process Statistics

When a application is running, there is a need to obtain information of the process executing that application. The `Process` API can be used by the application itself to gather statistics related to the current amount of memory being used, the number of threads, and other items. Biometric evaluation test drivers are linked against a third party library, and therefore, the application writer does not control the thread count or memory usage for much of the processing. Listing 8.1 shows how an application can use the `Statistics` API.

Listing 8.1: Gathering Process Statistics

```
1 #include <be_error_exception.h>
2 #include <be_process_statistics.h>
3 using namespace BiometricEvaluation;
4
5 int main(int argc, char *argv[])
6 {
7     Process::Statistics stats;
8     uint64_t userstart, userend;
9     uint64_t systemstart, systemend;
10    uint64_t diff;
11    try {
12        stats.getCPUTimes(&userstart, &systemstart);
13
14        // Do some long processing....
15
16        stats.getCPUTimes(&userend, &systemend);
17        diff = userend - userstart;
18        cout << "User time elapsed is " << diff << endl;
19        diff = systemend - systemstart;
20        cout << "System time elapsed is " << diff << endl;
21    } catch (Error::Exception) {
22        cout << "Caught " << e.getInfo() << endl;
23    }
```

24 |
25 | }

In addition to using the `Process` API to gather statistics to be returned from the function call, the API provides a means to have a “standard” set of statistics logged either synchronously or asynchronously to a `LogSheet` (See Section 6.3 on page 17) contained within a `LogCabinet`. Applications can start and stop logging at will to this `LogSheet`. Post-mortem analysis can then be done on the entries in the `LogSheet`. Listing 8.2 shows the use of logging.

The `LogSheet` will have a file name constructed from the process name (i.e. the application executable) and the process ID. An example `LogSheet` contains this information at the start:

```
Description: Statistics for test_be_process_statistics (PID 28370)
# Entry Uptime Systeime RSS VMSize VMPeak VMData VMStack Threads
E0000000001 728889 6998 1788 57472 62612 31020 84 1
E0000000002 1300802 6998 1792 57472 62612 31020 84 1
```

The `Statistics` object creates the `LogSheet` with an appropriate description and comment entry with column headers. Each gathering of the statistics results in a single log entry.

Listing 8.2: Logging Process Statistics

```
1 #include <be_error_exception.h>
2 #include <be_io_logcabinet.h>
3 #include <be_process_statistics.h>
4 using namespace BiometricEvaluation;
5
6 int main(int argc, char *argv[])
7 {
8     IO::LogCabinet lc("statLogCabinet", "Cabinet for Statistics", "");
9
10    Process::Statistics *logstats;
11    try {
12        logstats = new Process::Statistics(&lc);
13    } catch (Error::Exception &e) {
14        cout << "Caught " << e.getInfo() << endl;
15        return (EXIT_FAILURE);
16    }
17    try {
18        while (some_processing_to_do) {
19            // Do the work
20            // Synchronously log after the work is done.
21            logstats->logStats();
22        }
23    } catch (Error::Exception &e) {
24        cout << "Caught " << e.getInfo() << endl;
25        delete logstats;
26        return (EXIT_FAILURE);
27    }
28
29    // Set up asynchronous logging, every second
30    try {
31        logstats->startAutoLogging(1);
32    } catch (Error::ObjectExists &e) {
33        cout << "Caught " << e.getInfo() << endl;
```



```

34         delete logstats;
35         return (EXIT_FAILURE);
36     }
37
38     // Do some other work
39
40     // Stop logging
41     logstats->stopAutoLogging();
42     delete logstats;
43 }

```

8.2 Process Management

During a biometric evaluation or other long-running CPU-bound task, it's beneficial to make efficient use of all the hardware available on the system. If your application is running on a multi-core machine, why not make use of more than one core? BECommon aims to simply this by abstracting the usage of `fork(2)` and `libpthread` to run multiple instances of the same function simultaneously.

8.2.1 Manager

There are three class hierarchies involved in the abstraction. The `BiometricEvaluation::Process::Manager` classes control the technique of process manipulation that will be used. BECommon provides two example abstractions: `ForkManager` and `POSIXThreadManager`. When using `ForkManager`, new processes will be created with `fork(2)`, with mediated access to these new processes through the `Manager`. Likewise, `POSIXThreadManager` creates new POSIX threads. Because both of these classes inherit from `Manager`, it is as trivial as changing the `Manager` object type to change how the workload is parallelized.

8.2.2 Worker

In the application using a `Manager`, a `Worker` subclass must be implemented. An example `Worker` is shown in Listing 8.3. The entry-point for a `Worker` is the `workerMain()` method, which must be implemented by the client application. Although `workerMain()` takes no arguments, data may be transmitted into the object through `WorkerController's` (8.2.3) `setParameter()` method. Within the `Worker` instance, the parameters are then retrieved with `getParameter()` when provided with the unique parameter name.

A responsible `Worker` performs its operations as fast as it can, however, at any given time, the `Manager` may ask the `Worker` to stop. It then becomes the *responsibility of the Worker* to stop as soon as possible. The `Worker` is notified of the stop request through its `stopRequested()` method. Note that the `Manager` does **not** force the `Worker` to stop, though prolonged work or cleanup in the `Worker` would likely produce undesired results in the client application. As such, a responsible `Worker` checkpoints itself to prepare for premature stops requested by the `Manager`. While it is important for `Worker's` to stop as soon as possible after the request is received, it is also important not to leave work in an unsynchronized state. In Listing 8.3, notice how the `Employee` must continue the interaction with the `Customer` before a stop request is handled, even if the `Employee's` shift has ended. Leaving the method before the `Customer's` order has been delivered would leave the `Customer` object in an unsafe state (hungry).

Listing 8.3: A Responsible Worker Implementation

```

1 #include <cstdlib>
2 #include <tr1/memory>

```

```

3 #include <queue>
4
5 #include <restaurant.h>
6
7 #include <be_process_forkmanager.h>
8
9 using namespace std;
10 using namespace BiometricEvaluation;
11 using namespace Restaurant;
12
13 class ResponsibleEmployeeTask : public Process::Worker
14 {
15 public:
16     int32_t
17     workerMain()
18     {
19         int32_t status = EXIT_FAILURE;
20
21         /* Retrieve objects assigned to this Task */
22         tr1::shared_ptr<Employee> employee =
23             tr1::static_pointer_cast<Employee>(
24                 this->getParameter("employee"));
25         tr1::shared_ptr< queue<Customer*> > customers =
26             tr1::static_pointer_cast< queue<Customer*> >(
27                 this->getParameter("customers"))
28
29         employee->clockIn();
30
31         Customer *customer;
32         /* Checkpoint after each customer */
33         while (this->stopRequested() == false ||
34             employee->isShiftOver() == false) {
35             customer = customers->front();
36
37             if (customer != NULL) {
38                 employee->takeOrder(customer);
39                 employee->cookFood(customer);
40                 employee->deliverOrder(customer);
41
42                 customers->pop();
43             }
44         }
45
46         employee->settleCashDrawer();
47         employee->clockOut();
48
49         status = EXIT_SUCCESS;
50         return (status);
51     }
52     ~ResponsibleEmployeeTask() {}
53 };

```

After a Manager starts its Workers, the Manager has the option of waiting until all Workers exit worker Main() before continuing code execution. If not waiting, there are several methods the Manager can perform to keep track of the status of the Workers. Even if not waiting for Workers to return, a responsible Manager will wait a reasonable amount of time for Workers to return before application termination. An example

of this reasonable waiting period can be seen in Listing 8.4.

8.2.3 WorkerController

The final piece of the process management puzzle is the WorkerController hierarchy. This class decorates and mediates communication between the Manager and the Worker. WorkerController objects may only be instantiated by a Manager object. All communications to the Worker (e.g. `isWorking()`) should be delegated through the WorkerController. If defining a new Manager, note that the WorkerController may seem unnecessary for the parallelization technique being employed. It's true that some parallelization techniques may not require this "middle-man" approach, but others do. Do not be concerned if a WorkerController implementation ends up being nothing more than a "pass-thru" to the Worker.

Listing 8.4 is a continuation of Listing 8.3 on page 25 demonstrating the use of Manager s and Worker Controllers.

Listing 8.4: Using Manager s and WorkerController s

```

1 int
2 main(
3     int argc,
4     char *argv[])
5 {
6     static const uint32_t numEmployees = 3;
7     int status = EXIT_FAILURE;
8
9     tr1::shared_ptr<Process::Manager> shiftLeader(new Process::ForkManager);
10    queue<Customer*> *customers = new queue<Customer*>();
11
12    /* Create Employees (Workers/WorkerControllers) */
13    tr1::shared_ptr<Process::WorkerController> employees[numEmployees];
14    for (uint32_t i = 0; i < numEmployees; i++) {
15        employees[i] = shiftLeader->addWorker(
16            tr1::shared_ptr<ResponsibleEmployeeTask>(
17                new ResponsibleEmployeeTask()));
18
19        /* Assign employees to each Task */
20        employees[i]->setParameter("employee",
21            tr1::shared_ptr<Employee>(new Employee()));
22        employees[i]->setParameter("customers",
23            tr1::shared_ptr<queue<Customer*>>(customers));
24    }
25
26    /* Employees start serving customers while shift leader manages */
27    shiftLeader->startWorkers(false);
28
29    /* Customers enter the queue... */
30    queue<Restaurant::AdministrativeTasks> adminTasks;
31    adminTasks.push("Inventory");
32    adminTasks.push("Customer Complaints");
33    adminTasks.push("Clean Dining Room");
34
35    while (shiftLeader->getNumActiveWorkers() != 0) {
36        shiftLeader->doTask(adminTasks.front());
37        adminTasks.pop();
38    }

```

```

39
40     /* ...end of the day */
41     for (uint32_t i = 0; i < numEmployees; i++)
42         if (employees[i]->isWorking())
43             shiftLeader->stopWorker(employees[i]);
44
45     /*
46      * Wait a reasonable amount of time before locking up for the night
47      * (in this case, indefinitely).
48     */
49     while (shiftLeader->getNumActiveWorkers() > 0)
50         sleep(1);
51
52     shiftLeader->armAlarmAndExit();
53
54     status = EXIT_SUCCESS;
55     return (status);
56 }

```

8.2.4 Communications

Manager s and Worker s might have good reason to communicate arbitrary messages directly. A communications mechanism is built-in to the [Process Management](#) model to facilitate such communications. The type and content of the message is completely up to the client implementation, since messages are sent as `AutoArray` s. A Manager does not directly send messages to a Worker. This service is provided by the `WorkerController` (via `sendMessageToWorker()`).

Manager s can keep an eye on incoming messages by calling the (optionally blocking) `waitForMessage()` method. This method will return a handle to the `Worker` that sent a message. Alternatively, the Manager can invoke `getNextMessage()` (again, blocking optional) to immediately receive the next message.

[Listing 8.5](#) and [Listing 8.6 on the next page](#) are continuations of [Listing 8.3 on page 25](#) and [Listing 8.4 on the previous page](#) respectively, showing an example of communication, using `std::string` messages.

Listing 8.5: Worker Communication

```

1     Memory::uint8Array msg;
2
3     /* Deal with next customer unless Manager interrupts in next second */
4     if (this->waitForMessage(1)) {
5         if (this->getMessageFromManager(msg)) {
6             Action action = Restaurant::messageToAction(msg);
7             switch (action) {
8                 case TAKE_BREAK:
9                     employee->goOnBreak();
10                    break;
11                /* ... */
12            }
13        }
14    }
15
16    /* ... */
17
18    if (customer->isComplaining()) {
19        sprintf((char *)&(*msg), "Customer Complant");

```

```
20 |         this->sendMessageToManager(msg);
21 |     }
```

Listing 8.6: Manager Communication

```
1 |     tr1::shared_ptr<Process::WorkerController> sender;
2 |     Memory::uint8Array msg;
3 |
4 |     /* Do routine tasks unless employee has concern in the next 2 seconds */
5 |     while (this->getNextMessage(sender, msg, 2)) {
6 |         Action action = Restaurant::messageToAction(msg);
7 |         switch (action) {
8 |             case CUSTOMER_COMPLAINT:
9 |                 sprintf((char *)&(*msg), "I'll take care of it.");
10 |                this->sendMessageToWorker(msg);
11 |                break;
12 |            /* ... */
13 |        }
14 |    }
15 |
16 |    /* ... */
17 |
18 |    /* Closing Time */
19 |    sprintf((char *)&(*msg), "Clock out and go home.");
20 |    this->broadcastMessage(msg);
```


Chapter 9

System

The `System` package provides a set of functions in the that return information about the hardware and operating system. This information can be used by applications to determine the amount of real memory, number of central processing units, or current load average. This information can be used to dynamically tailor the application behavior, or simply to provide additional information in a runtime log.

Listing 9.1 shows how an application can spawn several child processes based on the number of CPUs and memory available. Note that this information may not be available on all platforms, and therefore, the application must be prepared to handle that situation.

Listing 9.1: Using the `System` CPU Count Information

```
1 #include <iostream>
2 #include <be_system.h>
3
4 using namespace BiometricEvaluation;
5
6 int
7 main(int argc, char* argv[]) {
8
9     // perform some application setup ...
10
11     uint32_t cpuCount;
12     uint64_t memSize, vmSize;
13     try {
14         cpuCount = System::getCPUCount();
15         cpuCount--; // subtract one CPU for the parent process
16         memSize = System::getRealMemorySize();
17         Process::Statistics::getMemorySizes(NULL, &vmSize, NULL, NULL, NULL);
18         memSize -= vmSize; // subtract off memory used by parent
19
20         // Give each child a fraction of the memory
21         spawnChildren(cpuCount, memSize / cpuCount);
22     } catch (Error::NotImplemented) {
23         cout << "Running a single process only." << endl;
24     }
25
26     // processing done by parent ...
27 }
```


Chapter 10

Image

The `Image` package maintains the classes and other information related to images and image processing. Within the Biometric Evaluation Framework, many classes refer to images, such as when dealing with fingerprint data. Many biometric data standards supply the actual image encoded in one of several standard formats. Applications can retrieve the image as stored in the record, or decompressed by the `Image` class into a “raw” format. Therefore, within the `BECommon`, several of the common compression formats are supported, removing the need for applications to decompress the image directly, while maintaining access to the as-recorded image format.

10.1 The Image Namespace

The `Image` namespace contains several data types used to represent aspects of an image. The types defined are chiefly used to retrieve common information from images stored in an `Image` class (section 10.2). Data types in the `Image` namespace do not perform any translation of scale units or sizing, as each set of attributes is copied directly from the image data itself when possible.

The same applies to images encapsulated in biometric records. Although some biometric records have fields for image attributes like dimensions and resolution, the corresponding fields of an `Image` class are **not** populated with their contents. The `Image` namespace data types *are* used outside of the namespace, such as in finger views, to retrieve image attributes stored as part of the biometric record. Applications can compare those values against the values within the `Image` object, as in most cases those values are taken directly from the underlying image data. See Chapter 14 on page 45 for more information on image-based biometric records.

The `Image` namespace contains all of the `Image` classes that are used to represent an image. These classes are described in the following sections.

10.2 The Image Class

The `Image` class is an abstract base class that defines a set of minimum functionality for all supported image formats. Once an `Image` has been constructed, it may not be modified. For any supported image format, the following information is required to be accessible:

- Original binary data
- Compression algorithm

- Decompressed (“raw”) format binary data (grayscale, full color)
- Depth
- Dimensions (width, height)
- Resolution (horizontal, vertical)

A rudimentary implementation of generating a grayscale image is provided by the `Image` class in `getRawGrayscaleData()`. This implementation calculates the luminance value Y (of $YCbCr$) for each pixel of a color image. The resulting image always uses 8-bits to represent a pixel, but can return a raw image using 2 gray levels (1-bit) or 256 gray levels (8-bit). The 1-bit algorithm quantizes to black when the 8-bit color value is ≤ 127 . Image subclasses may override and implement their own grayscale conversion methods.

Also of interest in the `Image` class is `valueInColorspace()`, a static function to convert color values between bit depths.

10.3 Raw Image

The `RawImage` class represents a decompressed image, or an image where `getRawData()` would return the exact same data as `getData()`. `RawImage` has no special implementation or additional methods.

10.4 JPEG

The `JPEG` class represents an image encoded according to the JPEG image standard [8]. Decompression and grayscale conversion are accomplished via `libjpeg` [6].

As of version 8.0, `libjpeg` provided a way to handle JPEG images existing within in-memory buffers, as opposed to on-disk files. Because the `Image` class requires in-memory buffers, `JPEG` includes a JPEG memory source manager implementation, but it is built only if a version of `libjpeg` older than 8.0 is detected at compile-time.

`JPEG` provides a static function to determine whether or not a data buffer appears to be encoded in the JPEG image standard format. Errors within `libjpeg` will be caught and rethrown as `Exceptions`.

10.5 JPEGL

Similar to `JPEG`, the `JPEGL` class performs `Image` class services for lossless JPEG encoded images. `JPEGL` decompression is performed by NIST Biometric Image Software’s `libjpegl` [12].

10.6 JPEG2000

The `JPEG2000` class provides `Image` class functionality to JPEG 2000-encoded images [7]. The class makes an attempt to support the following JPEG 2000 codecs:

- JPEG 2000 codestream (.j2k)
- JPEG 2000 compressed image data (.jp2)

- JPEG 2000 interactive protocol (.jpt)

Decompression is provided by the OpenJPEG library (`libopenjpeg`) [11]. JPEG2000 also provides a static function to test whether or not an image appears to be JPEG 2000-encoded.

Not all information required by the `Image` class is present in a JPEG 2000-encoded image. In particular, some codecs and encoders omit the “Display Resolution Box.” It is generally accepted that the resolution will be 72 pixels-per-inch when the “Display Resolution Box” is not present.

Errors within `libopenjpeg` will be caught and rethrown as `Exceptions`.

10.7 NetPBM

The `NetPBM` class provides `Image` class functionality to all types of NetPBM formatted images, up to 48-bit depth. This includes the following formats:

- ASCII Portable Bitmap (P1, .pbm)
- ASCII Portable Graymap (P2, .pgm)
- ASCII Portable Pixmap (P3, .ppm)
- Binary Portable Bitmap (P4, .pbm)
- Binary Portable Graymap (P5, .pgm)
- Binary Portable Pixmap (P6, .ppm)

`NetPBM` provides some of its more general use parsing algorithms as static functions for use outside of the class. This includes ASCII to binary pixel conversion. A function to test for NetPBM formats is also provided.

10.8 PNG

The `PNG` class represents an image encoded according to the PNG image standard [5]. Decompression is provided by `libpng` [14].

`PNG` provides a static function to test whether or not an image appears to be encoded in the PNG image standard format. Errors within `libpng` are caught and rethrown as `Exceptions`.

10.9 WSQ

Images encoded in the WSQ-image standard [16] are represented by the `WSQ` class. The WSQ decompressor found in NIST Biometric Image Software [12], `libwsq`, is used by this class. The class provides a static function to determine whether or not an image appears to be encoded in the WSQ format.

Errors from the `libwsq` will be displayed through `stderr` and will **not** be rethrown as `Exceptions`.

Chapter 11

Text

The `Text` package consists of functions to perform common operations on `strings` and `char` arrays. Many of the operations may be considered “trivial,” but are used often enough within the Biometric Evaluation Framework and other applications that a common implementation in `BECommon` is more than warranted. A complete listing of functions is available in the documentation appendix for `BiometricEvaluation::Text2`.

Listing 11.1 shows how to use the `split()` function from the `Text` package. `split()` can separate a string into tokens delimited by a character, useful for processing comma- or space-separated text files (such files could be produced by a `LogSheet` (Section 6.3 on page 17), for instance). Here, a text file containing metadata for an image is being parsed, perhaps to be passed to the `RawImage` constructor (Section 10.3 on page 34).

Listing 11.1: Tokenizing a string

```
1  /* Definition of input strings */
2  static const vector<string>::size_type filenameToken = 0;
3  static const vector<string>::size_type widthToken = 1;
4  static const vector<string>::size_type heightToken = 2;
5  static const vector<string>::size_type depthToken = 3;
6
7  /* Split the string, presumably input from a file */
8  string input = "/mnt/raw\\ images/1.raw 500 500 8";
9  vector<string> tokens = Text::split(input, ' ', true);
10
11 /* Assign the retrieved tokens */
12 string filename;
13 uint32_t width, height, depth;
14 try {
15     filename = tokens.at(filenameToken);    /* "/mnt/raw images/1.raw" */
16     width = atoi(tokens.at(widthToken).c_str());    /* "500" */
17     height = atoi(tokens.at(heightToken).c_str());    /* "500" */
18     depth = atoi(tokens.at(depthToken).c_str());    /* "8" */
19 } catch (out_of_range) {
20     throw Error::FileError("Malformed input");
21 }
```

Notice the `true` parameter to `split()` in Listing 11.1. This instructs `split()` to not tokenize based on an escaped delimiter. If `false`, the first token would be split into two at the presence of the delimiter.

`Text` also contains functions to perform hashing via `OpenSSL`. A two-line program that emulates the command-

line md5sum program is shown in Listing 11.2. Changing the digest parameter to "sha1" would make the program emulate 'openssl sha1'.

Listing 11.2: md5sum via BECommon

```
1 #include <cstdlib>
2 #include <iostream>
3
4 #include <be_io_utility.h>
5 #include <be_text.h>
6 #include <be_memory_autoarray.h>
7
8 using namespace std;
9 using namespace BiometricEvaluation;
10
11 int
12 main(
13     int argc,
14     char *argv[])
15 {
16     if (argc == 0)
17         return (EXIT_FAILURE);
18
19     try {
20         Memory::uint8Array file = IO::Utility::readFile(argv[1]);
21         cout << Text::digest(file, file.size(), "md5") << " " <<
22             argv[1] << endl;
23     } catch (Error::Exception) {
24         return (EXIT_FAILURE);
25     }
26
27     return (EXIT_SUCCESS);
28 }
```

Chapter 12

Feature

The `Feature` package contains those items that relate to the representation of biometric features, such as fingerprint minutiae, facial features (eyes, etc.), and related information. Objects of these class types are typically associated with `View` (Chapter 14 on page 45) or `DataInterchange` (Chapter 15 on page 47) objects. For example, a minutiae object is usually obtained from a finger view, which may have been obtained from a data interchange object representing an entire biometric record for an individual.

The data contained within a `Feature` object is represented as the “native” format as it was extracted from the underlying data record. There is no translation to a common format and it is the application’s responsibility to interpret or translate the data as necessary.

Currently, fingerprint and palm print minutiae are the features supported within the `BECCommon`. As development continues, additional features contained within biometric data records will be supported.

12.1 ANSI/NIST Features

The ANSI/NIST [3] standard defines several features represented as data elements within a record. Fingerprint and palm minutiae is contained within Type-9 record. The `AN2K7Minutiae` class, contained in the `Feature` package, represents a single Type-9 record. An object of this class can be constructed directly from a complete ANSI/NIST record. However, it is more common for an application to retrieve these objects from the `AN2KView` object defined in the `Finger` package (Chapter 13 on page 41).

See Listing 13.1 on page 42 for a complete example of how to obtain the fingerprint minutiae data from an ANSI/NIST record.

12.2 ISO/INCITS Features

The ISO [2] and INCITS [1] fingerprint minutiae standards are represented within `BECCommon` with the same class, `INCITSMinutiae`, as the minutiae format is identical in both standards.

Listing 13.2 on page 43 shows how to create a view object for the fingerprint minutiae record contained in a file.

Chapter 13

Finger

One of the most commonly used biometric source is the fingerprint. Multiple types of information can be derived from a fingerprint, including minutiae and the pattern, such as whorl, etc. The `Finger` package contains the types, classes, and other items that are related to fingers and fingerprints. Objects of the `Finger` classes are typically not used in a stand-alone fashion, but are usually obtained from an object in the `DataInterchange` (Chapter [15 on page 47](#)) package.

Several enumerated types are defined in the `Finger` package. The types are used to represent those elements related to fingers and fingerprints that are common across all data formats. Types that represent finger position, impression type, and others are included in the package. Stream operators are defined for these types so they can be printed in human-readable format.

Most of the classes in the `Finger` package represent data taken directly from a record in a standard format (e.g. ANSI/NIST [\[3\]](#)). In addition to general information, such as finger position, other information may be represented: The source of the finger image; the quality of the image, etc. In addition to this descriptive information, the finger object will provide the set of derived minutiae or other data sets.

When representing the information about a finger (and fingerprint), the class in the `Finger` package implements the interface defined in the `View` package. A finger is a specific type of view in that it represents all the available information about the finger, including the source image, minutiae (often in several formats), as well as the capture data (date, location, etc.)

13.1 ANSI/NIST Minutiae Data Record

Finger views are objects that represent all the available information for a specific finger as contained in one or more biometric records. For example, an ANSI/NIST file may contain a Type-3 record (finger image) and an associated Type-9 record (finger minutiae). A finger view object based on the ANSI/NIST record can be instantiated and used by an application to retrieve all the desired information, including the source finger image. The internals of record processing and error handling are encapsulated within the class.

The `BCommon` provides several classes that are derived from a base `View` class, contained within the `Finger` package. See Chapter [13](#) for more information on the types associated with fingers and fingerprints. This section discusses finger views, the classes which are derived from the general `View` class. These subclasses represent specific biometric file types, such as ANSI/NIST or INCITS/M1. In the latter case, two files must be provided when constructing the object because INCITS finger image and finger minutiae records are defined in two separate standards.

13.1.1 ANSI/NIST Finger Views

An ANSI/NIST record may contain one or more finger views, each based on a type of finger image. These Type-3, Type-4, etc. records contain the image and Type-9 minutiae data, among other information. These record types are grouped into either the fixed- or variable-resolution categories, and are represented as specific classes within BECommon, AN2KViewFixedResolution and AN2KViewVariableResolution.

The AN2KMinutiaeDataRecord class represents all of the information taken from a ANSI/NIST Type-9 record. A Type-9 record may include minutiae data items in several formats (standard and proprietary) and the impression type code.

Listing 13.1 shows how an application can use the AN2KViewFixedResolution to retrieve image information, image data, and derived minutiae information from a file containing an ANSI/NIST record with Type-3 (fixed resolution image) and Type-9 (fingerprint minutiae) records.

Listing 13.1: Using an AN2K Finger View

```

1 #include <fstream>
2 #include <iostream>
3 #include <be_finger_an2kview_fixedres.h>
4 using namespace std;
5 using namespace BiometricEvaluation;
6
7 int
8 main(int argc, char* argv[]) {
9
10     Finger::AN2KViewFixedResolution *_an2kv
11     try {
12         _an2kv = new Finger::AN2KViewFixedResolution("type9-3.an2k",
13             TYPE_3_ID, 1);
14     } catch (Error::DataError &e) {
15         cerr << "Caught " << e.getInfo() << endl;
16         return (EXIT_FAILURE);
17     } catch (Error::FileError& e) {
18         cerr << "A file error occurred: " << e.getInfo() << endl;
19         return (EXIT_FAILURE);
20     }
21     std::auto_ptr<Finger::AN2KView> an2kv(_an2kv);
22
23     cout << "Image resolution is " << an2kv->getImageResolution() << endl;
24     cout << "Image size is " << an2kv->getImageSize() << endl;
25     cout << "Image depth is " << an2kv->getImageDepth() << endl;
26     cout << "Compression is " << an2kv->getCompressionAlgorithm() << endl;
27     cout << "Scan resolution is " << an2kv->getScanResolution() << endl;
28
29     // Save the finger image to a file.
30     tr1::shared_ptr<Image::Image> img = an2kv->getImage();
31     if (img.get() == NULL) {
32         cerr << "Image was not present." << endl;
33         return (EXIT_FAILURE);
34     }
35     string filename = "rawimg";
36     ofstream img_out(filename.c_str(), ofstream::binary);
37     img_out.write((char *)&(img->getRawData()[0]),
38         img->getRawData().size());
39     if (img_out.good())

```

```

40         cout << "\tFile: " << filename << endl;
41     else {
42         img_out.close();
43         cerr << "Error occurred when writing " << filename << endl;
44         return (EXIT_FAILURE);
45     }
46     img_out.close();
47
48     // Get the finger minutiae sets. AN2K records can have more than one
49     // set of minutiae for a finger.
50
51     vector<Finger::AN2KMinutiaeDataRecord> mindata = an2kv->getMinutiaeDataRecordSet();
52 }

```

13.1.2 ISO/INCITS Finger Views

The ISO [10] and INCITS [9] standards typically use separate files for the source biometric data and the derived data. For example, the ISO 19794-2 standard is for fingerprint minutiae data, while 19794-4 is for finger image data. The corresponding BECommon view objects are constructed with both files, although a view can be constructed with only one file. In the latter case, the view object will represent only that information contained in the single file.

Listing 13.1 on the preceding page shows how an application can create a view from a ANSI/INCTIS 378 finger minutiae format record [1].

Listing 13.2: Using an INCITS Finger View

```

1  #include <stdlib.h>
2  #include <fstream>
3  #include <iostream>
4  #include <be_finger_ansi2004view.h>
5  #include <be_feature_incitsminutiae.h>
6  using namespace std;
7  using namespace BiometricEvaluation;
8
9  int
10 main(int argc, char* argv[]) {
11
12     Finger::ANSI2004View fngv;
13     try {
14         fngv = Finger::ANSI2004View("test_data/fmr.ansi2004", "", 3);
15     } catch (Error::DataError &e) {
16         cerr << "Caught " << e.getInfo() << endl;
17         return (EXIT_FAILURE);
18     } catch (Error::FileError& e) {
19         cerr << "A file error occurred: " << e.getInfo() << endl;
20         return (EXIT_FAILURE);
21     }
22     cout << "Image resolution is " << fngv.getImageResolution() << endl;
23     cout << "Image size is " << fngv.getImageSize() << endl;
24     cout << "Image depth is " << fngv.getImageDepth() << endl;
25     cout << "Compression is " << fngv.getCompressionAlgorithm() << endl;
26     cout << "Scan resolution is " << fngv.getScanResolution() << endl;
27
28     Feature::INCITSMinutiae fmd = fngv.getMinutiaeData();

```

```
29 |     cout << "Minutiae format is " << fmd.getFormat() << endl;
30 |     Feature::MinutiaPointSet mps = fmd.getMinutiaPoints();
31 |     cout << "There are " << mps.size() << " minutiae points:" << endl;
32 |     for (size_t i = 0; i < mps.size(); i++)
33 |         cout << mps[i];
34 |
35 |         Feature::RidgeCountItemSet rcs = fmd.getRidgeCountItems();
36 |     cout << "There are " << rcs.size() << " ridge count items:" << endl;
37 |     for (int i = 0; i < rcs.size(); i++)
38 |         cout << "\t" << rcs[i];
39 |
40 |     Feature::CorePointSet cores = fmd.getCores();
41 |     cout << "There are " << cores.size() << " cores:" << endl;
42 |     for (int i = 0; i < cores.size(); i++)
43 |         cout << "\t" << cores[i];
44 |
45 |     Feature::DeltaPointSet deltas = fmd.getDeltas();
46 |     cout << "There are " << deltas.size() << " deltas:" << endl;
47 |     for (int i = 0; i < deltas.size(); i++)
48 |         cout << "\t" << deltas[i];
49 |
50 |     exit (EXIT_SUCCESS);
51 | }
```

Chapter 14

View

Within the Biometric Evaluation Framework a `View` represents all the information that was derived from an image of a biometric sample. For example, with a fingerprint image, any minutiae that were extracted from that image, as well as the image itself, are contained within a single `View` object. In many cases the image may not be present, however the image size and other information is contained within a biometric record, along with the derived information. A `View` is used to represent these records as well.

In the case where a raw image is part of the biometric record, the `View` object's related `Image` ([Chapter 10 on page 33](#)) object will have identical size, resolution, etc. values because the `View` class sets the `Image` attributes directly. For other image types (e.g. `JPEG`) the `Image` object will return attribute values taken from the image data.

`Views` are high-level abstractions of the biometric sample, and concrete implementations of a `View` include finger, face, iris, etc. views based on a specific type of biometric. Therefore, `View` objects are not created directly, Subclasses, such as finger views (see [Chapter 13 on page 41](#)), represent the specific type of biometric sample.

Objects are created with information taken from a biometric data record, an ANSI/NIST 2007 file, for example. Most record formats contain information about the image itself, such as the resolution and size. The `View` object can be used to retrieve this information. However, the data may differ from that contained in the image itself, and applications can compare the corresponding values taken from the `Image` object (when available) to those taken from the `View` object.

Chapter 15

Data Interchange

The `DataInterchange` package consists of classes and other elements used to process an entire biometric data record, or set of records. For example, a single ANSI/NIST record, consisting of many smaller records (fingerprint images, latent data, etc.) can be accessed by instantiating a single object. Classes in this package typically use has-a relationships to classes in the `Finger` and other packages that process individual biometric samples.

The design of classes in the `DataInterchange` package allows applications to create a single object from a biometric record, such as an ANSI/NIST file. After creating this object, the application can retrieve the needed information (such as `Finger Views` Chapter 13 on page 41) from this object. A typical example would be to retrieve all images from the record and pass them into a function that extracts a biometric template or some other image processing.

15.1 ANSI/NIST Data Records

The ANSI/NIST Data Interchange package contains the classes used to represent ANSI/NIST [3] records. One class, `AN2KRecord`, is used to represent the entire ANSI/NIST record. An object of this class will contain objects of the `Finger` classes, as well as other packages. By instantiating the `AN2KRecord` object, the application can retrieve all the information and images contained in the ANSI/NIST record.

The `AN2KMinutiaeDataRecord` class represents an entire Type-9 record from an ANSI/NIST file. However, some components of this class are represented by classes in other packages. For example, the `AN2K7Minutiae` class in the `Feature` package represents the “standard” format minutiae in the Type-9 record.

Listing 15.1 shows how an application can retrieve all finger captures (Type-4 records) from an ANSI/NIST record. Once the Views are retrieved, the application obtains the set of minutiae records associated with that View.

Listing 15.1: Retrieving ANSI/NIST Finger Captures

```
1 #include <iostream>
2 #include <be_error_exception.h>
3 #include <be_finger_an2kview_capture.h>
4
5 int
6 main(int argc, char* argv[])
7 {
8     /*
```

```

9      * Call the constructor that will open an existing AN2K file and
10     * retrieve the first finger capture (Type-14) record.
11     */
12     std::auto_ptr<Finger::AN2KViewCapture> an2kv;
13     try {
14         an2kv.reset(new Finger::AN2KViewCapture("type9-14.an2k", 1));
15     } catch (Error::DataError &e) {
16         cout << "Caught " << e.getInfo() << endl;
17         return (EXIT_FAILURE);
18     } catch (Error::FileError& e) {
19         cout << "A file error occurred: " << e.getInfo() << endl;
20         return (EXIT_FAILURE);
21     }
22
23     cout << "Get the set of minutiae data records: ";
24     vector<Finger::AN2KMinutiaeDataRecord> records =
25         an2kv->getMinutiaeDataRecordSet();
26     cout << "There are " << records.size() << " minutiae records." << endl;
27
28     /*
29      * Get the info from the first minutiae record in the View.
30      */
31     DataInterchange::AN2KMinutiaeDataRecord type9 = records[0];
32
33     /*
34      * Get the "standard" set of minutiae.
35      */
36     Feature::AN2K7Minutiae an2k7m = type9.getAN2K7Minutiae();
37
38     /*
39      * Obtain the minutiae points, ridge counts, cores, and deltas.
40      */
41     Feature::MinutiaPointSet mps;
42     Feature::RidgeCountItemSet rcs;
43     Feature::CorePointSet cps;
44     Feature::DeltaPointSet dps;
45     try {
46         mps = an2k7m->getMinutiaPoints();
47         rcs = an2k7m->getRidgeCountItems();
48         cps = an2k7m->getCores();
49         dps = an2k7m->getDeltas();
50
51     } catch (Error::DataError &e) {
52         cout << "Caught " << e.getInfo() << endl;
53         return (EXIT_FAILURE);
54     }
55
56     cout << "There are " << mps.size() << " minutiae points:" << endl;
57     /*
58      * Print out the minutiae points.
59      */
60     for (int i = 0; i < mps.size(); i++) {
61         printf("(%u,%u,%u)\n", mps[i].coordinate.x, mps[i].coordinate.y,
62             mps[i].theta);
63     }
64     cout << "There are " << rcs.size() << " ridge counts:" << endl;

```



```

65     for (int i = 0; i < rcs.size(); i++) {
66         printf("(%u,%u,%u)\n", rcs[i].index_one, rcs[i].index_two,
67             rcs[i].count);
68     }
69     cout << "There are " << cps.size() << " cores." << endl;
70     cout << "There are " << dps.size() << " deltas." << endl;
71
72     cout << "Fingerprint Reader: " << endl;
73     try { cout << an2k7m->getOriginatingFingerprintReadingSystem() << endl; }
74     catch (Error::ObjectDoesNotExist) { cout << "<Omitted>" << endl; }
75
76     cout << "Pattern (primary): " <<
77     Feature::AN2K7Minutiae::convertPatternClassification(
78     an2k7m->getPatternClassificationSet().at(0)) << endl;
79
80     return(EXIT_SUCCESS);
81 }

```

Listing 15.2 shows how an application can retrieve all latent finger images from a set of ANSI/NIST record retrieved from a RecordStore. Using the Image object, the image's "raw" data can be retrieved and passed to another function for processing. Note that the image data may be stored in a compressed format inside the ANSI/NIST record, but is converted to raw format by the Image object.

Listing 15.2: Retrieving ANSI/NIST Latent Records

```

1 #include <be_io_recordstore.h>
2 #include <be_data_interchange_an2k.h>
3 using namespace BiometricEvaluation;
4
5 void
6 processImageData(uint8_t *buf, uint32_t size)
7 {
8     :
9     :
10    :
11    :
12 }
13
14 int
15 main(int argc, char* argv[]) {
16
17     std::tr1::shared_ptr<IO::RecordStore> rs;
18     try {
19         rs = IO::RecordStore::openRecordStore(rsname, datadir, IO::READONLY);
20     } catch (Error::Exception &e) {
21         cerr << "Could not open record store: " << e.getInfo() << endl;
22         return (EXIT_FAILURE);
23     }
24
25     /*
26      * Read some AN2K records and construct the View objects.
27      */
28     Utility::uint8Array data;
29     string key;
30     while (true) { // Loop through all records in store
31         uint64_t rlen;

```

```

32     try {
33         rlen = rs->sequence(key, NULL);
34     } catch (Error::ObjectDoesNotExist &e) {
35         break;
36     } catch (Error::Exception &e) {
37         cout << "Failed sequence: " << e.getInfo() << endl;
38         return (EXIT_FAILURE);
39     }
40     data.resize(rlen);
41     try {
42         rs->read(key, data);
43         DataInterchange::AN2KRecord an2k(data);
44         std::vector<Finger::AN2KViewLatent> latents = an2k.getFingerLatents();
45         for (int i = 0; i < latents.size(); i++) {
46             trl::shared_ptr<Image::Image> img = latents[i].getImage();
47             if (img != NULL) {
48                 cout << "\tCompression: " << img->getCompressionAlgorithm() << endl;
49                 cout << "\tDimensions: " << img->getDimensions() << endl;
50                 cout << "\tResolution: " << img->getResolution() << endl;
51                 cout << "\tDepth: " << img->getDepth() << endl;
52                 processImageData(img->getRawData(), img->getRawData().size());
53             }
54         }
55     } catch (Error::Exception &e) {
56         return (EXIT_FAILURE);
57     }
58 }
59 return (EXIT_SUCCESS);
60 }

```

15.2 INCITS Data Records

This INCITS class of data records covers all those record formats that are derived from the standards defined by the InterNational Committee for Information Technology Standards [9]. These formats include the ANSI-2004 Finger Minutiae Record Format [1], the ISO equivalent [2], and other data formats, including finger images.

15.2.1 Finger Views

Within the BECommon, finger view objects (Section 14) can be created from a combination of finger minutiae and image records. However, it is not necessary to have both records in order to create the view because each record contains enough information to represent the finger (image size, for example). However, if a view is constructed using only the minutiae record, then the image itself will not be present. Alternatively, if a view is made from an image record, no minutiae data would be available. It is possible to construct a view without any information.

Listing 13.2 on page 43 shows an example of accessing the information in an ANSI 378-2004 Finger Minutiae Record by creating an ANSI2004View object from the record file.

References

- [1] *ANSI INCITS 378-2004: Finger Minutiae Format for Data Interchange*. ANSI/INCITS, 2004. 39, 43, 50
- [2] *ISO/IEC 19794-2: Information technology - Biometric data interchange formats - Part 2: Finger minutiae data*. ISO/IEC, first edition, 2005. 39, 50
- [3] *American National Standard for Information Systems - Data Format for the Interchange of Fingerprint, Facial, & Other Biometric Information*. ANSI/NIST-ITL, 1-2007 edition, 2007. 4, 39, 41, 47
- [4] Mark Adler. zlib, 2012. <http://www.zlib.net/>. 19
- [5] World Wide Web Consortium. Portable Network Graphics Standard, 2003. <http://www.w3.org/TR/PNG/>. 35
- [6] Independent JPEG Group. libjpeg, 2011. <http://www.ijg.org/>. 34
- [7] Joint Photographic Experts Group. JPEG2000 Image Standard, 1992. <http://www.jpeg.org/jpeg2000/index.html>. 34
- [8] Joint Photographic Experts Group. JPEG Image Standard, 2011. <http://www.jpeg.org/jpeg/index.html>. 34
- [9] International Committee for Information Technology Standards. <http://www.incits.org>. 43, 50
- [10] ISO/IEC Joint Technical Committee 1/SC 37 Biometrics. 43
- [11] Communications and Remote Sensing Lab, Université catholique de Louvain. OpenJPEG Library, 2011. <http://www.openjpeg.org/>. 35
- [12] NIST Biometric Image Software, 2011. <http://www.nist.gov/itl/iad/ig/nbis.cfm>. 7, 34, 35
- [13] NIST Image Group. <http://www.nist.gov/itl/iad/ig>. 1
- [14] Greg Roelofs. libpng, 2011. <http://www.libpng.org/pub/png/libpng.html>. 35
- [15] Bjarne Stroustrup. *The C++ Programming Language*. Addison Wesley, special edition, 2000. 3, 9
- [16] Wavelet Scalar Quantization Gray-Scale Fingerprint Image Compression Standard, 2010. https://www.fbibiospecs.org/docs/WSQ_Gray-scale_Specification_Version_3_1_Final.pdf. 35

Appendix A

Namespace Index

A.1 Namespace List

Here is a list of all documented namespaces with brief descriptions:

BiometricEvaluation::Error	65
Exceptions, and other error handling	
BiometricEvaluation::Finger	66
Biometric information relating to finger images and derived information	
BiometricEvaluation::Framework	68
Information about the framework	
BiometricEvaluation::Image	69
Basic information relating to images	
BiometricEvaluation::IO	71
Input/Output functionality	
BiometricEvaluation::IO::Utility	73
BiometricEvaluation::Memory	80
Support for memory-related operations	
BiometricEvaluation::Process	81
Process information and controls	
BiometricEvaluation::System	81
Operating system, hardware, etc	
BiometricEvaluation::Text	83
Text processing for string objects	
BiometricEvaluation::Time	85
Support for time and timers	
BiometricEvaluation::View	86
View information	

Appendix B

Hierarchical Index

B.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

BiometricEvaluation::Finger::AN2KViewCapture::AmputatedBandaged	89
BiometricEvaluation::Finger::AN2KMinutiaeDataRecord	94
BiometricEvaluation::View::AN2KViewVariableResolution::AN2KQualityMetric	96
BiometricEvaluation::DataInterchange::AN2KRecord	96
BiometricEvaluation::Memory::AutoArray< T >	139
BiometricEvaluation::Memory::AutoArray< uint8_t >	139
BiometricEvaluation::Memory::AutoBuffer< T >	147
BiometricEvaluation::Memory::AutoBuffer< ANSI_NIST >	147
BiometricEvaluation::DataInterchange::AN2KRecord::CharacterSet	148
BiometricEvaluation::Image::CompressionAlgorithm	156
BiometricEvaluation::IO::Compressor	156
BiometricEvaluation::IO::GZip	197
BiometricEvaluation::Image::Coordinate	167
BiometricEvaluation::Feature::CorePoint	168
BiometricEvaluation::Feature::DeltaPoint	176
BiometricEvaluation::View::AN2KView::DeviceMonitoringMode	176
BiometricEvaluation::DataInterchange::AN2KRecord::DomainName	177
BiometricEvaluation::Feature::AN2K7Minutiae::EncodingMethod	178
BiometricEvaluation::Feature::AN2K7Minutiae::PatternClassification::Entry	178
BiometricEvaluation::Error::Exception	179
BiometricEvaluation::Error::ConversionError	166
BiometricEvaluation::Error::DataError	169
BiometricEvaluation::Error::FileError	181
BiometricEvaluation::Error::MemoryError	262
BiometricEvaluation::Error::NotImplemented	270
BiometricEvaluation::Error::ObjectDoesNotExist	271
BiometricEvaluation::Error::ObjectExists	271
BiometricEvaluation::Error::ObjectIsClosed	272
BiometricEvaluation::Error::ObjectIsOpen	273
BiometricEvaluation::Error::ParameterError	284
BiometricEvaluation::Error::StrategyError	336

BiometricEvaluation::Finger::FingerImageCode	188
BiometricEvaluation::Feature::AN2K7Minutiae::FingerprintReadingSystem	188
BiometricEvaluation::Finger::AN2KViewCapture::FingerSegmentPosition	189
BiometricEvaluation::Image::Image	205
BiometricEvaluation::Image::JPEG	235
BiometricEvaluation::Image::JPEG2000	237
BiometricEvaluation::Image::JPEGL	239
BiometricEvaluation::Image::NetPBM	265
BiometricEvaluation::Image::PNG	285
BiometricEvaluation::Image::Raw	300
BiometricEvaluation::Image::WSQ	353
BiometricEvaluation::Finger::Impression	213
BiometricEvaluation::Memory::IndexedBuffer	228
iterator	
BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >	278
BiometricEvaluation::Memory::OrderedMapIterator< Key, T >	281
BiometricEvaluation::IO::LogCabinet	247
BiometricEvaluation::Process::Manager	256
BiometricEvaluation::Process::ForkManager	190
BiometricEvaluation::Process::POSIXThreadManager	288
BiometricEvaluation::IO::ManifestEntry	262
BiometricEvaluation::Feature::Minutiae	263
BiometricEvaluation::Feature::AN2K7Minutiae	89
BiometricEvaluation::Feature::INCITSMinutiae	213
BiometricEvaluation::Feature::MinutiaeFormat	264
BiometricEvaluation::Feature::MinutiaeType	264
BiometricEvaluation::Feature::MinutiaPoint	265
BiometricEvaluation::Memory::OrderedMap< Key, T >	274
BiometricEvaluation::Memory::OrderedMap< string, ManifestEntry >	274
ostream	
BiometricEvaluation::IO::LogSheet	249
BiometricEvaluation::Finger::PatternClassification	284
BiometricEvaluation::Feature::AN2K7Minutiae::PatternClassification	285
BiometricEvaluation::Finger::Position	287
BiometricEvaluation::Finger::AN2KViewVariableResolution::PrintPositionCoordinate	291
BiometricEvaluation::IO::Properties	293
BiometricEvaluation::IO::PropertiesFile	298
BiometricEvaluation::IO::RecordStore	302
BiometricEvaluation::IO::ArchiveRecordStore	131
BiometricEvaluation::IO::CompressedRecordStore	149
BiometricEvaluation::IO::DBRecordStore	170
BiometricEvaluation::IO::FileRecordStore	182
BiometricEvaluation::IO::ListRecordStore	241
BiometricEvaluation::IO::SQLiteRecordStore	324
BiometricEvaluation::View::AN2KView::RecordType	317
BiometricEvaluation::Image::Resolution	318
BiometricEvaluation::Feature::RidgeCountExtractionMethod	319
BiometricEvaluation::Feature::RidgeCountItem	320
BiometricEvaluation::Error::SignalManager	320
BiometricEvaluation::Image::Size	323

BiometricEvaluation::Process::Statistics	332
BiometricEvaluation::Time::Timer	337
BiometricEvaluation::View::View	338
BiometricEvaluation::Finger::INCITSView	217
BiometricEvaluation::Finger::ANSI2004View	127
BiometricEvaluation::Finger::ANSI2007View	129
BiometricEvaluation::Finger::ISO2005View	232
BiometricEvaluation::View::AN2KView	106
BiometricEvaluation::Finger::AN2KView	102
BiometricEvaluation::Finger::AN2KViewFixedResolution	116
BiometricEvaluation::View::AN2KViewVariableResolution	123
BiometricEvaluation::Finger::AN2KViewVariableResolution	119
BiometricEvaluation::Finger::AN2KViewCapture	111
BiometricEvaluation::Finger::AN2KViewLatent	118
BiometricEvaluation::Time::Watchdog	340
BiometricEvaluation::Process::Worker	343
BiometricEvaluation::Process::WorkerController	349
BiometricEvaluation::Process::ForkWorkerController	194
BiometricEvaluation::Process::POSIXThreadWorkerController	290

Appendix C

Class Index

C.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

BiometricEvaluation::Finger::AN2KViewCapture::AmputatedBandaged	
Enumeration of the finger amputated or bandaged code, a reason that a capture could not be made	89
BiometricEvaluation::Feature::AN2K7Minutiae	
A class to represent a set of minutiae in an ANSI/NIST record	89
BiometricEvaluation::Finger::AN2KMinutiaeDataRecord	
Representation of a Type-9 Record from an AN2K file	94
BiometricEvaluation::View::AN2KViewVariableResolution::AN2KQualityMetric	
A structure to represent an AN2K quality metric	96
BiometricEvaluation::DataInterchange::AN2KRecord	
A class to represent an entire ANSI/NIST record	96
BiometricEvaluation::Finger::AN2KView	
A class to represent single finger view and derived information	102
BiometricEvaluation::View::AN2KView	
A class to represent single biometric view and derived information	106
BiometricEvaluation::Finger::AN2KViewCapture	
Represents an ANSI/NIST variable-resolution finger image	111
BiometricEvaluation::Finger::AN2KViewFixedResolution	
A class to represent single finger view and derived information	116
BiometricEvaluation::Finger::AN2KViewLatent	
.	118
BiometricEvaluation::Finger::AN2KViewVariableResolution	
A class to represent single finger view based on an ANSI/NIST record	119
BiometricEvaluation::View::AN2KViewVariableResolution	
A class to represent single view based on an ANSI/NIST record	123
BiometricEvaluation::Finger::ANSI2004View	
A class to represent single finger view and derived information	127
BiometricEvaluation::Finger::ANSI2007View	
A class to represent single finger view and derived information	129
BiometricEvaluation::IO::ArchiveRecordStore	
This class implements the IO::RecordStore interface by storing data items in single file, with an associated manifest file	131

BiometricEvaluation::Memory::AutoArray< T >	
A C-style array wrapped in the facade of a C++ STL container	139
BiometricEvaluation::Memory::AutoBuffer< T >	147
BiometricEvaluation::DataInterchange::AN2KRecord::CharacterSet	148
BiometricEvaluation::IO::CompressedRecordStore	
Sibling-implemented RecordStore with Compression	149
BiometricEvaluation::Image::CompressionAlgorithm	
Image compression algorithms	156
BiometricEvaluation::IO::Compressor	156
BiometricEvaluation::Error::ConversionError	
Error when converting one object into another, a property value from string to int, for example	166
BiometricEvaluation::Image::Coordinate	
A structure to contain a two-dimensional coordinate without a specified origin	167
BiometricEvaluation::Feature::CorePoint	
Representation of the core	168
BiometricEvaluation::Error::DataError	
Error when reading data from an external source	169
BiometricEvaluation::IO::DBRecordStore	
A class that implements IO::RecordStore using a Berkeley DB database as the underlying record storage system	170
BiometricEvaluation::Feature::DeltaPoint	
Representation of the delta	176
BiometricEvaluation::View::AN2KView::DeviceMonitoringMode	
The level of human monitoring for the image capture device	176
BiometricEvaluation::DataInterchange::AN2KRecord::DomainName	
Representation of a domain name for the user-defined Type-2 logical record implementation	177
BiometricEvaluation::Feature::AN2K7Minutiae::EncodingMethod	
Methods for encoding minutiae data in an AN2K record	178
BiometricEvaluation::Feature::AN2K7Minutiae::PatternClassification::Entry	178
BiometricEvaluation::Error::Exception	
The parent class of all BiometricEvaluation exceptions	179
BiometricEvaluation::Error::FileError	
File error when opening, reading, writing, etc	181
BiometricEvaluation::IO::FileRecordStore	182
BiometricEvaluation::Finger::FingerImageCode	188
BiometricEvaluation::Feature::AN2K7Minutiae::FingerprintReadingSystem	
Representation of information about a fingerprint reader system	188
BiometricEvaluation::Finger::AN2KViewCapture::FingerSegmentPosition	
Locations of an individual finger segment in a slap	189
BiometricEvaluation::Process::ForkManager	
Manager implementation that starts Workers by calling <code>fork(2)</code>	190
BiometricEvaluation::Process::ForkWorkerController	
Wrapper of a Worker returned from a Process::ForkManager	194
BiometricEvaluation::IO::GZip	
Compressor for gzip compression from zlib	197
BiometricEvaluation::Image::Image	
Represent attributes common to all images	205
BiometricEvaluation::Finger::Impression	
Finger and palm impression types	213

BiometricEvaluation::Feature::INCITSMinutiae	
A class to represent a set of minutiae in an ANSI/INCITS record	213
BiometricEvaluation::Finger::INCITSView	
A class to represent single finger view and derived information	217
BiometricEvaluation::Memory::IndexedBuffer	
Manage a memory buffer with an index	228
BiometricEvaluation::Finger::ISO2005View	
A class to represent single finger view and derived information	232
BiometricEvaluation::Image::JPEG	
A JPEG-encoded image	235
BiometricEvaluation::Image::JPEG2000	
A JPEG-2000-encoded image	237
BiometricEvaluation::Image::JPEGL	
A Lossless JPEG-encoded image	239
BiometricEvaluation::IO::ListRecordStore	241
BiometricEvaluation::IO::LogCabinet	247
BiometricEvaluation::IO::LogSheet	
A class to represent a single logging mechanism	249
BiometricEvaluation::Process::Manager	
An interface for intranode process management classes	256
BiometricEvaluation::IO::ManifestEntry	262
BiometricEvaluation::Error::MemoryError	
An error occurred when allocating an object	262
BiometricEvaluation::Feature::Minutiae	
A class to represent a set of minutiae data points	263
BiometricEvaluation::Feature::MinutiaeFormat	
Enumerate the minutiae format standards	264
BiometricEvaluation::Feature::MinutiaeType	
Enumerate the types of minutiae: Ridge Ending, Bifurcation, Compound, or other	264
BiometricEvaluation::Feature::MinutiaPoint	
Representation of a finger minutiae data point	265
BiometricEvaluation::Image::NetPBM	
A NetPBM-encoded image	265
BiometricEvaluation::Error::NotImplemented	
A NotImplemented object is thrown when the underlying implementation of this interface has not or could not be created	270
BiometricEvaluation::Error::ObjectDoesNotExist	
The named object does not exist	271
BiometricEvaluation::Error::ObjectExists	
The named object exists and will not be replaced	271
BiometricEvaluation::Error::ObjectIsClosed	
The object is closed	272
BiometricEvaluation::Error::ObjectIsOpen	
The object is already opened	273
BiometricEvaluation::Memory::OrderedMap< Key, T >	274
BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >	278
BiometricEvaluation::Memory::OrderedMapIterator< Key, T >	281
BiometricEvaluation::Error::ParameterError	
An invalid parameter was passed to a constructor or method	284
BiometricEvaluation::Finger::PatternClassification	
Pattern classification codes	284

BiometricEvaluation::Feature::AN2K7Minutiae::PatternClassification	
Pattern classification codes	285
BiometricEvaluation::Image::PNG	
A PNG-encoded image	285
BiometricEvaluation::Finger::Position	
Finger position codes	287
BiometricEvaluation::Process::POSIXThreadManager	
Manager implementation that starts Workers in POSIX threads	288
BiometricEvaluation::Process::POSIXThreadWorkerController	
Decorated Worker returned from a Process::POSIXThreadManager	290
BiometricEvaluation::Finger::AN2KViewVariableResolution::PrintPositionCoordinate	
Offsets to the bounding boxes for the EJI, full finger views, or EJI segments	291
BiometricEvaluation::IO::Properties	
Maintain key/value pairs of strings, with each property matched to one value	293
BiometricEvaluation::IO::PropertiesFile	
A Properties object persisted in an file on disk	298
BiometricEvaluation::Image::Raw	
An image with no encoding or compression	300
BiometricEvaluation::IO::RecordStore	
A class to represent a data storage mechanism	302
BiometricEvaluation::View::AN2KView::RecordType	
The type of AN2K record	317
BiometricEvaluation::Image::Resolution	
A structure to represent the resolution of an image	318
BiometricEvaluation::Feature::RidgeCountExtractionMethod	
Enumerate the types of extraction methods for ridge counts	319
BiometricEvaluation::Feature::RidgeCountItem	
Representation of ridge count data, which is the number of ridges between any two minutia data points, each represented by its index number	320
BiometricEvaluation::Error::SignalManager	
A SignalManager object is used to handle signals that come from the operating system	320
BiometricEvaluation::Image::Size	
A structure to represent the size of an image, in pixels	323
BiometricEvaluation::IO::SQLiteRecordStore	
A RecordStore implementation using a SQLite database as the underlying record storage system	324
BiometricEvaluation::Process::Statistics	
Interface for gathering process statistics, such as memory usage, system time, etc	332
BiometricEvaluation::Error::StrategyError	
A StrategyError object is thrown when the underlying implementation of this interface encounters an error	336
BiometricEvaluation::Time::Timer	
This class can be used by applications to report the amount of time a block of code takes to execute	337
BiometricEvaluation::View::View	
A class to represent single biometric element view	338
BiometricEvaluation::Time::Watchdog	
A Watchdog object can be used by applications to limit the amount of processing time taken by a block of code	340
BiometricEvaluation::Process::Worker	
An abstraction of an instance that performs work on given data	343

BiometricEvaluation::Process::WorkerController	
Wrapper of a Worker returned from a Process::Manager	349
BiometricEvaluation::Image::WSQ	
A WSQ-encoded image	353

Appendix D

Namespace Documentation

D.1 BiometricEvaluation::Error Namespace Reference

Exceptions, and other error handling.

Classes

- class [Exception](#)
The parent class of all BiometricEvaluation exceptions.
- class [FileError](#)
File error when opening, reading, writing, etc.
- class [ParameterError](#)
An invalid parameter was passed to a constructor or method.
- class [ConversionError](#)
Error when converting one object into another, a property value from string to int, for example.
- class [DataError](#)
Error when reading data from an external source.
- class [MemoryError](#)
An error occurred when allocating an object.
- class [ObjectExists](#)
The named object exists and will not be replaced.
- class [ObjectDoesNotExist](#)
The named object does not exist.
- class [ObjectIsOpen](#)
The object is already opened.
- class [ObjectIsClosed](#)
The object is closed.
- class [StrategyError](#)
A [StrategyError](#) object is thrown when the underlying implementation of this interface encounters an error.
- class [NotImplemented](#)
A [NotImplemented](#) object is thrown when the underlying implementation of this interface has not or could not be created.

- class [SignalManager](#)

A [SignalManager](#) object is used to handle signals that come from the operating system.

Functions

- string [errorStr](#) ()
- void [SignalManagerSigHandler](#) (int signo, siginfo_t *info, void *uap)

D.1.1 Detailed Description

Exceptions, and other error handling. The [Error](#) package contains classes for exceptions, and functions used for error handling, including signals generated by a process.

D.1.2 Function Documentation

D.1.2.1 string BiometricEvaluation::Error::errorStr ()

Convert the value of errno to a human-readable error message.

Returns

The current error message specified by errno.

D.2 BiometricEvaluation::Finger Namespace Reference

Biometric information relating to finger images and derived information.

Classes

- class [PatternClassification](#)

Pattern classification codes.

- class [Position](#)

Finger position codes.

- class [Impression](#)

Finger and palm impression types.

- class [FingerImageCode](#)

- class [AN2KMinutiaeDataRecord](#)

Representation of a Type-9 Record from an AN2K file.

- class [AN2KView](#)

A class to represent single finger view and derived information.

- class [AN2KViewCapture](#)

Represents an ANSI/NIST variable-resolution finger image.

- class [AN2KViewFixedResolution](#)

A class to represent single finger view and derived information.

- class [AN2KViewLatent](#)
- class [AN2KViewVariableResolution](#)
A class to represent single finger view based on an ANSI/NIST record.
- class [ANSI2004View](#)
A class to represent single finger view and derived information.
- class [ANSI2007View](#)
A class to represent single finger view and derived information.
- class [INCITSView](#)
A class to represent single finger view and derived information.
- class [ISO2005View](#)
A class to represent single finger view and derived information.

Typedefs

- typedef std::vector
 < Position::Kind > **PositionSet**
- typedef std::map
 < Position::Kind,
 FingerImageCode::Kind > **PositionDescriptors**

Functions

- std::ostream & [operator<<](#) (std::ostream &, const Finger::PatternClassification::Kind &)
Output stream overload for PatternClassification::Kind.
- std::ostream & **operator<<** (std::ostream &, const Position::Kind &)
- std::ostream & **operator<<** (std::ostream &, const Impression::Kind &)
- std::ostream & **operator<<** (std::ostream &, const FingerImageCode::Kind &)
- std::ostream & [operator<<](#) (std::ostream &stream, const [AN2KViewCapture::AmputatedBandaged::Kind](#) &ab)
Output stream overload for AmputatedBandaged::Kind.
- std::ostream & [operator<<](#) (std::ostream &stream, const [AN2KViewCapture::FingerSegmentPosition](#) &fsp)
Output stream overload for FingerSegmentPosition.
- std::ostream & [operator<<](#) (std::ostream &stream, const [AN2KViewVariableResolution::PrintPositionCoordinate](#) &ppc)
Output stream overload for PrintPositionCoordinate.

D.2.1 Detailed Description

Biometric information relating to finger images and derived information. The [Finger](#) package gathers all finger related matters, including classes to represent finger minutiae and helper functions for conversion between biometric representations. Contained within this namespace are classes to represent specific record formats, such as ANSI/NIST finger image records.

D.2.2 Function Documentation

D.2.2.1 `std::ostream& BiometricEvaluation::Finger::operator<< (std::ostream & stream, const AN2KViewVariableResolution::PrintPositionCoordinate & ppc)`

Output stream overload for PrintPositionCoordinate.

Parameters

<code>in</code>	<code><i>stream</i></code>	Stream on which to append formatted PrintPositionCoordinate information.
<code>in</code>	<code><i>ppc</i></code>	PrintPositionCoordinate information to append to stream.

Returns

Stream with a ppc textual representation appended.

D.3 BiometricEvaluation::Framework Namespace Reference

Information about the framework.

Functions

- unsigned int [getMajorVersion \(\)](#)
Framework major version.
- unsigned int [getMinorVersion \(\)](#)
Framework minor version.
- std::string [getCompiler \(\)](#)
Compiler used to compile this framework.
- std::string [getCompileDate \(\)](#)
Date when this framework was compiled.
- std::string [getCompileTime \(\)](#)
Time when this framework was compiled.
- std::string [getCompilerVersion \(\)](#)
Version string of compiler used to compile this framework.

D.3.1 Detailed Description

Information about the framework.

D.3.2 Function Documentation

D.3.2.1 `unsigned int BiometricEvaluation::Framework::getMajorVersion ()`

[Framework](#) major version.

Returns

The major version number of the BiometricFramework

D.3.2.2 unsigned int BiometricEvaluation::Framework::getMinorVersion ()

Framework minor version.

Returns

The minor version of the BiometricEvaluation framework.

D.3.2.3 std::string BiometricEvaluation::Framework::getCompiler ()

Compiler used to compile this framework.

Returns

The name of the compiler used to compile this framework.

D.3.2.4 std::string BiometricEvaluation::Framework::getCompileDate ()

Date when this framework was compiled.

Returns

Date when this framework was compiled, in the form "MMM DD YYYY"

D.3.2.5 std::string BiometricEvaluation::Framework::getCompileTime ()

Time when this framework was compiled.

Returns

Time when this framework was compiled, in the form "HH:MM:SS"

D.3.2.6 std::string BiometricEvaluation::Framework::getCompilerVersion ()

Version string of compiler used to compile this framework.

Returns

Major, minor, and patch level of the compiler used.

D.4 BiometricEvaluation::Image Namespace Reference

Basic information relating to images.

Classes

- class [CompressionAlgorithm](#)
Image compression algorithms.
- struct [Coordinate](#)
A structure to contain a two-dimensional coordinate without a specified origin.
- struct [Size](#)
A structure to represent the size of an image, in pixels.
- struct [Resolution](#)
A structure to represent the resolution of an image.
- class [Image](#)
Represent attributes common to all images.
- class [JPEG](#)
A JPEG-encoded image.
- class [JPEG2000](#)
A JPEG-2000-encoded image.
- class [JPEGL](#)
A Lossless JPEG-encoded image.
- class [NetPBM](#)
A NetPBM-encoded image.
- class [PNG](#)
A PNG-encoded image.
- class [Raw](#)
An image with no encoding or compression.
- class [WSQ](#)
A WSQ-encoded image.

Typedefs

- typedef struct [Coordinate](#) **Coordinate**
- typedef std::vector
 < [Image::Coordinate](#) > **CoordinateSet**
- typedef struct [Size](#) **Size**
- typedef struct [Resolution](#) **Resolution**

Functions

- std::ostream & **operator**<< (std::ostream &, const CompressionAlgorithm::Kind &)
- std::ostream & **operator**<< (std::ostream &, const [Coordinate](#) &)
- std::ostream & **operator**<< (std::ostream &stream, const CoordinateSet &coordinates)
Output stream overload for CoordinateSet.
- std::ostream & **operator**<< (std::ostream &, const [Size](#) &)
- std::ostream & **operator**<< (std::ostream &, const [Resolution](#) &)
- std::ostream & **operator**<< (std::ostream &stream, const [Resolution::Kind](#) &kind)
- float [distance](#) (const [Coordinate](#) &p1, const [Coordinate](#) &p2)
Calculate the distance between two points.

D.4.1 Detailed Description

Basic information relating to images. Classes and methods for manipulating images.

The [Image](#) package gathers all image related matters, including classes to represent an image, coordinates, and functions for conversion between biometric representations.

D.4.2 Function Documentation

D.4.2.1 `std::ostream& BiometricEvaluation::Image::operator<< (std::ostream & stream, const CoordinateSet & coordinates)`

Output stream overload for CoordinateSet.

Parameters

<code>in</code>	<code><i>stream</i></code>	Stream on which to append formatted CoordinateSet information.
<code>in</code>	<code><i>coordinates</i></code>	CoordinateSet information to append to stream.

Returns

stream with a coordinates textual representation appended.

D.4.2.2 `float BiometricEvaluation::Image::distance (const Coordinate & p1, const Coordinate & p2)`

Calculate the distance between two points.

Parameters

<code>in</code>	<code><i>p1</i></code>	First point.
<code>in</code>	<code><i>p2</i></code>	Second point.

Returns

Distance between p1 and p2.

D.5 BiometricEvaluation::IO Namespace Reference

Input/Output functionality.

Namespaces

- namespace [Utility](#)

Classes

- struct [ManifestEntry](#)

- class [ArchiveRecordStore](#)
This class implements the [IO::RecordStore](#) interface by storing data items in single file, with an associated manifest file.
- class [CompressedRecordStore](#)
Sibling-implemented [RecordStore](#) with Compression.
- class [Compressor](#)
- class [DBRecordStore](#)
A class that implements [IO::RecordStore](#) using a Berkeley DB database as the underlying record storage system.
- class [FileRecordStore](#)
- class [GZip](#)
Compressor for gzip compression from zlib.
- class [ListRecordStore](#)
- class [LogCabinet](#)
- class [LogSheet](#)
A class to represent a single logging mechanism.
- class [Properties](#)
Maintain key/value pairs of strings, with each property matched to one value.
- class [PropertiesFile](#)
A [Properties](#) object persisted in an file on disk.
- class [RecordStore](#)
A class to represent a data storage mechanism.
- class [SQLiteRecordStore](#)
A [RecordStore](#) implementation using a SQLite database as the underlying record storage system.

Typedefs

- typedef [Memory::OrderedMap](#)
 < string, [ManifestEntry](#) > [ManifestMap](#)
- typedef map< string, string > [PropertiesMap](#)

D.5.1 Detailed Description

Input/Output functionality. The [IO](#) package contains classes and functions used to abstract input and output operations and provide for robust error handling on behalf of the application.

D.5.2 Typedef Documentation

D.5.2.1 typedef [Memory::OrderedMap](#)<string, [ManifestEntry](#)> [BiometricEvaluation::IO::ManifestMap](#)

Convenience typedef for storing the manifest

D.5.2.2 typedef map<string, string> [BiometricEvaluation::IO::PropertiesMap](#)

Internal structure used for storing property keys/values

D.6 BiometricEvaluation::IO::Utility Namespace Reference

Functions

- void [removeDirectory](#) (const string &directory, const string &prefix) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Remove a directory using directory name and parent pathname.
- void [removeDirectory](#) (const string &pathname) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Remove a directory using a complete pathname.
- void [copyDirectoryContents](#) (const string &sourcepath, const string &targetpath, const bool removesource=false) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Copy the contents of a directory, optionally deleting the source directory contents when done.
- void [setAsideName](#) (const string &name) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Set aside a file or directory name.
- uint64_t [getFileSize](#) (const string &pathname) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- bool [fileExists](#) (const string &pathname) throw (Error::StrategyError)
- bool [pathIsDirectory](#) (const string &pathname) throw (Error::StrategyError)
- bool [validateRootName](#) (const string &name)
- bool [constructAndCheckPath](#) (const string &name, const string &parentDir, string &fullPath)
- int [makePath](#) (const string &path, const mode_t mode)
Create an entire directory tree.
- [Memory::uint8Array](#) [readFile](#) (const string &path, ios_base::openmode mode=ios_base::binary) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Read the contents of a file into a buffer.
- void [writeFile](#) (const uint8_t *data, const size_t size, const string &path, ios_base::openmode mode=ios_base::binary) throw (Error::ObjectExists, Error::StrategyError)
Write the contents of a buffer to a file.
- void [writeFile](#) (const [Memory::uint8Array](#) data, const string &path, ios_base::openmode mode=ios_base::binary) throw (Error::ObjectExists, Error::StrategyError)
Write the contents of a buffer to a file.
- bool [isReadable](#) (const string &pathname)
Determine if a file can be opened with read permission.
- bool [isWritable](#) (const string &pathname)
Determine if a file can be opened with read/write permission.
- string [createTemporaryFile](#) (const string &prefix="", const string &parentDir="/tmp") throw (Error::FileError, Error::MemoryError)
Create a temporary file.
- FILE * [createTemporaryFile](#) (string &path, const string &prefix="", const string &parentDir="/tmp") throw (Error::FileError, Error::MemoryError)
Create a temporary file.

D.6.1 Detailed Description

A class containing utility functions used for [IO](#) operations. These functions are class methods.

D.6.2 Function Documentation

D.6.2.1 `void BiometricEvaluation::IO::Utility::removeDirectory (const string & directory, const string & prefix) throw (Error::ObjectDoesNotExist, Error::StrategyError)`

Remove a directory using directory name and parent pathname.

Parameters

in	<i>directory</i>	The name of the directory to be removed, without a preceding path.
in	<i>prefix</i>	The path leading to the directory.

Exceptions

<i>Error::ObjectDoesNotExist</i>	The named directory does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system, or the directory name or prefix is malformed.

D.6.2.2 `void BiometricEvaluation::IO::Utility::removeDirectory (const string & pathname) throw (Error::ObjectDoesNotExist, Error::StrategyError)`

Remove a directory using a complete pathname.

Parameters

in	<i>pathname</i>	The complete path name of the directory to be removed,
----	-----------------	--

Exceptions

<i>Error::ObjectDoesNotExist</i>	The named directory does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system, or the path name is malformed.

D.6.2.3 `void BiometricEvaluation::IO::Utility::copyDirectoryContents (const string & sourcepath, const string & targetpath, const bool removesource = false) throw (Error::ObjectDoesNotExist, Error::StrategyError)`

Copy the contents of a directory, optionally deleting the source directory contents when done.

Parameters

in	<i>sourcepath</i>	The name of the directory whose contents are to be moved.
in	<i>targetpath</i>	The name of the directory where the contents of the sourcepath are to be moved.
in	<i>removesource</i>	Flag indicating whether to remove the source directory after the copy is complete.

Exceptions

<i>Error::ObjectDoesNotExist</i>	The source named directory does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system, or the directory name or prefix is malformed.

D.6.2.4 void BiometricEvaluation::IO::Utility::setAsideName (const string & *name*) throw (Error::ObjectDoesNotExist, Error::StrategyError)

Set aside a file or directory name.

A file or directory is renamed in a sequential manner. For example, if directory foo is set aside, it will be renamed foo.1. If foo is recreated by the application, and again set aside, it will be renamed foo.2. There is a limit of uint16_t max attempts at creating a set aside name.

Parameters

in	<i>name</i>	The path name of the file or directory to be set aside.
----	-------------	---

Exceptions

<i>Error::ObjectDoesNotExist</i>	The named object does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system, the name or prefix is malformed, or the maximum number of attempts was reached.

D.6.2.5 uint64_t BiometricEvaluation::IO::Utility::getFileSize (const string & *pathname*) throw (Error::ObjectDoesNotExist, Error::StrategyError)

Get the size of a file.

Parameters

in	<i>pathname</i>	The name of the file to be sized; can be a complete path.
----	-----------------	---

Returns

The file size.

Exceptions

<i>Error::ObjectDoesNotExist</i>	The named directory does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system, or pathname is malformed.

D.6.2.6 `bool BiometricEvaluation::IO::Utility::fileExists (const string & pathname) throw (Error::StrategyError)`

Indicate whether a file exists.

Parameters

in	<i>pathname</i>	The name of the file to be checked; can be a complete path.
----	-----------------	---

Returns

true if the file exists, false otherwise.

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying storage system, or <i>pathname</i> is malformed.
---	--

D.6.2.7 `bool BiometricEvaluation::IO::Utility::validateRootName (const string & name)`

Check whether or not a string is valid as a name for a rooted entity, such as a [RecordStore](#) or other type of container that is persistent within the file system. Notably, name cannot contain path name separators ('/' and '\') or begin with whitespace.

Parameters

in	<i>name</i>	The proposed name for the entity.
----	-------------	-----------------------------------

Returns

true if the name is acceptable, false otherwise.

D.6.2.8 `bool BiometricEvaluation::IO::Utility::constructAndCheckPath (const string & name, const string & parentDir, string & fullPath)`

Construct a full path for a rooted entity, and return true if that path exists; false otherwise.

Parameters

in	<i>name</i>	The proposed name for the entity; cannot be a pathname.
in	<i>parentDir</i>	The name of the directory to contain the entity.
out	<i>fullPath</i>	The complete path to the new entity, when true is returned; ambiguous when false is returned.

Returns

true if the named entity is present in the file system, false otherwise.

D.6.2.9 `int BiometricEvaluation::IO::Utility::makePath (const string & path, const mode_t mode)`

Create an entire directory tree.

All intermediate nodes are created if they don't exist.

Parameters

<i>in</i>	<i>path</i>	The path to create.
<i>in</i>	<i>mode</i>	The permission mode of each element in the path. See chmod(2).

Returns

0 on success, non-zero otherwise, and errno can be checked.

D.6.2.10 `Memory::uint8Array BiometricEvaluation::IO::Utility::readFile (const string & path, ios_base::openmode mode = ios_base::binary) throw (Error::ObjectDoesNotExist, Error::StrategyError)`

Read the contents of a file into a buffer.

Parameters

<i>path</i>	Path to a file to be read.
<i>mode</i>	Bitwise OR'd arguments to send to the file stream constructor.

Returns

Contents of path in a buffer.

Exceptions

<i>Error::ObjectDoesNotExist</i>	path does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

D.6.2.11 `void BiometricEvaluation::IO::Utility::writeFile (const uint8_t * data, const size_t size, const string & path, ios_base::openmode mode = ios_base::binary) throw (Error::ObjectExists, Error::StrategyError)`

Write the contents of a buffer to a file.

Parameters

<i>data</i>	Data buffer to write.
<i>size</i>	Size of data.
<i>path</i>	Path to file to create with contents of data.
<i>mode</i>	Bitwise OR'd arguments to send to the file stream constructor.

Exceptions

<i>ObjectExists</i>	path exists but truncate not set, or path exists and is a directory.
<i>StrategyError</i>	An error occurred when using the underlying storage system.

D.6.2.12 `void BiometricEvaluation::IO::Utility::writeFile (const Memory::uint8Array data, const string & path, ios_base::openmode mode = ios_base::binary) throw (Error::ObjectExists, Error::StrategyError)`

Write the contents of a buffer to a file.

Parameters

<i>data</i>	Data buffer to write.
<i>path</i>	Path to file to create with contents of data.
<i>mode</i>	Bitwise OR'd arguments to send to the file stream constructor.

Exceptions

<i>ObjectExists</i>	path exists but truncate not set, or path exists and is a directory.
<i>StrategyError</i>	An error occurred when using the underlying storage system.

D.6.2.13 `bool BiometricEvaluation::IO::Utility::isReadable (const string & pathname)`

Determine if a file can be opened with read permission.

Parameters

<i>in</i>	<i>pathname</i>	Path to the file to check.
-----------	-----------------	----------------------------

Returns

true if the file can be opened with read permission, false otherwise.

Note

Could return true if the file does not exist, though [fileExists\(\)](#) will return false if you do not have read permission.

See Also

[BiometricEvaluation::IO::Utility::fileExists\(\)](#)

D.6.2.14 `bool BiometricEvaluation::IO::Utility::isWritable (const string & pathname)`

Determine if a file can be opened with read/write permission.

Parameters

in	<i>pathname</i>	Path to the file to check.
----	-----------------	----------------------------

Returns

true if the file can be opened with write permission, false otherwise.

Note

Could return true if the file does not exist, though [fileExists\(\)](#) will return false if you do not have read permission.

See Also

[BiometricEvaluation::IO::Utility::fileExists\(\)](#)

D.6.2.15 `string BiometricEvaluation::IO::Utility::createTemporaryFile (const string & prefix = "", const string & parentDir = "/tmp") throw (Error::FileError, Error::MemoryError)`

Create a temporary file.

Parameters

in	<i>prefix</i>	String to be prefixed to the random temporary name.
in	<i>parentDir</i>	Where to place the temporary file.

Exceptions

Error::FileError	Could not create or close temporary file.
Error::MemoryError	Error allocating memory for file name.

Returns

Path to temporary file.

Note

Exclusivity is not guaranteed for the path returned, since the exclusive descriptor is closed before returning.

D.6.2.16 `FILE* BiometricEvaluation::IO::Utility::createTemporaryFile (string & path, const string & prefix = "", const string & parentDir = "/tmp") throw (Error::FileError, Error::MemoryError)`

Create a temporary file.

Exclusivity to the file stream is guaranteed.

Parameters

out	<i>path</i>	Reference to a string that will hold the path to the opened temporary file.
in	<i>prefix</i>	String to be prefixed to the random temporary name.
in	<i>parentDir</i>	Where to place the temporary file.

Exceptions

<i>Error::FileError</i>	Could not create or close temporary file.
<i>Error::MemoryError</i>	Error allocating memory for file name.

Returns

Open file stream to path.

Note

Caller must `fclose(3)` the returned stream.

D.7 BiometricEvaluation::Memory Namespace Reference

Support for memory-related operations.

Classes

- class [AutoArray](#)
A C-style array wrapped in the facade of a C++ STL container.
- class [AutoBuffer](#)
- class [IndexedBuffer](#)
Manage a memory buffer with an index.
- class [OrderedMap](#)
- class [OrderedMapIterator](#)
- class [OrderedMapConstIterator](#)

Typedefs

- typedef [AutoArray](#)< uint8_t > **uint8Array**
- typedef [AutoArray](#)< uint16_t > **uint16Array**
- typedef [AutoArray](#)< uint32_t > **uint32Array**

D.7.1 Detailed Description

Support for memory-related operations. The [Memory](#) package contains templates and classes that are used to manage memory, auto-sizing arrays, for example.

D.8 BiometricEvaluation::Process Namespace Reference

[Process](#) information and controls.

Classes

- class [ForkManager](#)
Manager implementation that starts Workers by calling fork(2).
- class [ForkWorkerController](#)
Wrapper of a [Worker](#) returned from a [Process::ForkManager](#).
- class [Manager](#)
An interface for intranode process management classes.
- class [POSIXThreadManager](#)
Manager implementation that starts Workers in POSIX threads.
- class [POSIXThreadWorkerController](#)
Decorated [Worker](#) returned from a [Process::POSIXThreadManager](#).
- class [Statistics](#)
The [Statistics](#) class provides an interface for gathering process statistics, such as memory usage, system time, etc.
- class [Worker](#)
An abstraction of an instance that performs work on given data.
- class [WorkerController](#)
Wrapper of a [Worker](#) returned from a [Process::Manager](#).

Typedefs

- typedef map< string,
tr1::shared_ptr< void > > [ParameterList](#)

D.8.1 Detailed Description

[Process](#) information and controls. The [Process](#) package gathers all process related matters, including a class to obtain resource usage statistics.

D.8.2 Typedef Documentation

D.8.2.1 typedef map< string, tr1::shared_ptr<void> > BiometricEvaluation::Process::ParameterList

Convenience typedef for parameter lists to child routines

D.9 BiometricEvaluation::System Namespace Reference

Operating system, hardware, etc.

Functions

- `uint32_t getCPUCount ()` throw (`Error::NotImplemented`)
Obtain the number of central processing units that are online. Typically, this is the total CPU core count for the system.
- `uint64_t getRealMemorySize ()` throw (`Error::NotImplemented`)
Obtain the amount of real memory in the system.
- `double getLoadAverage ()` throw (`Error::NotImplemented`)
Obtain the system load average for the last minute.

D.9.1 Detailed Description

Operating system, hardware, etc. The `System` package gathers all system related matters, such as the operating system name, number of CPUs, etc.

D.9.2 Function Documentation

D.9.2.1 `uint32_t BiometricEvaluation::System::getCPUCount ()` throw (`Error::NotImplemented`)

Obtain the number of central processing units that are online. Typically, this is the total CPU core count for the system.

Returns

The number of processing units.

Exceptions

<i><code>Error::NotImplemented</code></i>	Not implemented for this operating system, or the underlying OS feature is not installed.
---	---

D.9.2.2 `uint64_t BiometricEvaluation::System::getRealMemorySize ()` throw (`Error::NotImplemented`)

Obtain the amount of real memory in the system.

Returns

The real memory size, in kilobytes.

Exceptions

<i><code>Error::NotImplemented</code></i>	Not implemented for this operating system, or the underlying OS feature is not installed.
---	---

D.9.2.3 double BiometricEvaluation::System::getLoadAverage () throw (Error::NotImplemented)

Obtain the system load average for the last minute.

Returns

The system load average.

Exceptions

<i>Error::NotImplemented</i>	Not implemented for this operating system, or the underlying OS feature is not installed.
------------------------------	---

D.10 BiometricEvaluation::Text Namespace Reference

[Text](#) processing for string objects.

Functions

- void [removeLeadingTrailingWhitespace](#) (string &s)
Remove lead and trailing white space from a string object.
- string [digest](#) (const string &s, const string &digest="md5") throw (Error::MemoryError, Error::NotImplemented, Error::StrategyError)
Compute the digest of a string.
- string [digest](#) (const void *buffer, const size_t buffer_size, const string &digest="md5") throw (Error::MemoryError, Error::NotImplemented, Error::StrategyError)
Compute the digest of a memory buffer.
- vector< string > [split](#) (const string &str, const char delimiter, bool escape=true) throw (Error::ParameterError)
Return tokens bound by delimiters and the beginning and end of a string.
- string [filename](#) (const string &path)
Extract the filename portion of a pathname.
- string [dirname](#) (const string &path)
Extract the directory part of a pathname.

D.10.1 Detailed Description

[Text](#) processing for string objects. The [Text](#) package contains a set of functions for the processing of strings: removing leading and trailing whitespace, computing a digest, and other utility functions.

D.10.2 Function Documentation

D.10.2.1 string BiometricEvaluation::Text::digest (const string & s, const string & digest = "md5") throw (Error::MemoryError, Error::NotImplemented, Error::StrategyError)

Compute the digest of a string.

Parameters

in	<i>s</i>	The string of which a digest should be computed.
in	<i>digest</i>	The digest to use. Any digest supported by OpenSSL is valid, and the default is MD5.

Exceptions

<i>Error::MemoryError</i>	Could not allocate memory to store digest.
<i>Error::NotImplemented</i>	The value of digest is not a supported digest.
<i>Error::StrategyError</i>	An error occurred while obtaining the digest.

Returns

An ASCII representation of the hex digits composing the digest.

D.10.2.2 `string BiometricEvaluation::Text::digest (const void * buffer, const size_t buffer_size, const string & digest = "md5") throw (Error::MemoryError, Error::NotImplemented, Error::StrategyError)`

Compute the digest of a memory buffer.

Parameters

in	<i>buffer</i>	The buffer of which a digest should be computed.
in	<i>buffer_size</i>	The size of buffer.
in	<i>digest</i>	The digest to use. Any digest supported by OpenSSL is valid, and the default is MD5.

Exceptions

<i>Error::MemoryError</i>	Could not allocate memory to store digest.
<i>Error::NotImplemented</i>	The value of digest is not a supported digest.
<i>Error::StrategyError</i>	An error occurred while obtaining the digest.

Returns

An ASCII representation of the hex digits composing the digest.

D.10.2.3 `vector<string> BiometricEvaluation::Text::split (const string & str, const char delimiter, bool escape = true) throw (Error::ParameterError)`

Return tokens bound by delimiters and the beginning and end of a string.

Parameters

in	<i>str</i>	String to tokenize.
in	<i>delimiter</i>	Character that defines the end of a token. Any are valid, except '\'.
in	<i>escape</i>	If the delimiter is prefixed with '\' in the string, do not split at that point and remove the '\'.

Returns

Vector of string tokens, in order of appearance.

Note

If delimiter does not appear in string, the returned vector vector will still contain one item, str.

D.10.2.4 string BiometricEvaluation::Text::filename (const string & path)

Extract the filename portion of a pathname.

Parameters

in	path	Path from which to extract the filename portion.
----	------	--

Returns

Filename portion of path.

D.10.2.5 string BiometricEvaluation::Text::dirname (const string & path)

Extract the directory part of a pathname.

Parameters

in	path	Path from which to extract the directory portion.
----	------	---

Returns

Directory portion of path.

D.11 BiometricEvaluation::Time Namespace Reference

Support for time and timers.

Classes

- class [Timer](#)

This class can be used by applications to report the amount of time a block of code takes to execute.

- class [Watchdog](#)

A [Watchdog](#) object can be used by applications to limit the amount of processing time taken by a block of code.

Functions

- string [getCurrentTime](#) ()

Return the current time as a string.

- void **WatchdogSignalHandler** (int signo, siginfo_t *info, void *uap)

Variables

- const uint64_t **OneSecond** = 1000000
- const uint64_t **OneHalfSecond** = 500000
- const uint64_t **OneQuarterSecond** = 250000
- const uint64_t **OneEighthSecond** = 125000
- const int **NanosecondsPerMicrosecond** = 1000
- const int **MicrosecondsPerSecond** = 1000000
- const int **MicrosecondsPerMillisecond** = 1000
- const int **MillisecondsPerSecond** = 1000

D.11.1 Detailed Description

Support for time and timers. The [Time](#) package gathers all timing relating matters, such as Timers, [Watchdog](#) timers, etc. [Time](#) values are in microsecond units.

D.12 BiometricEvaluation::View Namespace Reference

[View](#) information.

Classes

- class [AN2KView](#)
A class to represent single biometric view and derived information.
- class [AN2KViewVariableResolution](#)
A class to represent single view based on an ANSI/NIST record.
- class [View](#)
A class to represent single biometric element view.

Functions

- std::ostream & [operator<<](#) (std::ostream &stream, const [AN2KView::DeviceMonitoringMode::Kind](#) &kind)
Output stream overload for DeviceMonitoringMode.
- std::ostream & [operator<<](#) (std::ostream &stream, const [AN2KViewVariableResolution::AN2KQualityMetric](#) &qm)
Output stream overload for AN2KQualityMetric.

D.12.1 Detailed Description

[View](#) information. The [View](#) package gathers all classes and other items that are related to a biometric view, which represents an image and all information derived from that image, such as fingerprint minutiae.

D.12.2 Function Documentation

D.12.2.1 `std::ostream& BiometricEvaluation::View::operator<< (std::ostream & stream, const AN2KViewVariableResolution::AN2KQualityMetric & qm)`

Output stream overload for AN2KQualityMetric.

Parameters

<code>in</code>	<code><i>stream</i></code>	Stream on which to append formatted AN2KQualityMetric information.
<code>in</code>	<code><i>qm</i></code>	AN2KQualityMetric information to append to stream.

Returns

`stream` with a `qm` textual representation appended.

Appendix E

Class Documentation

E.1 BiometricEvaluation::Finger::AN2KViewCapture::AmputatedBandaged Class Reference

Enumeration of the finger amputated or bandaged code, a reason that a capture could not be made.

```
#include <be_finger_an2kview_capture.h>
```

Public Types

- enum [Kind](#) { [Amputated](#), [Bandaged](#), [NA](#) }

E.1.1 Detailed Description

Enumeration of the finger amputated or bandaged code, a reason that a capture could not be made.

E.1.2 Member Enumeration Documentation

E.1.2.1 enum BiometricEvaluation::Finger::AN2KViewCapture::AmputatedBandaged::Kind

Enumerator

Amputated Amputation

Bandaged Unable to print (e.g., bandaged)


NA Optional field – not specified

E.2 BiometricEvaluation::Feature::AN2K7Minutiae Class Reference

A class to represent a set of minutiae in an ANSI/NIST record.

```
#include <be_feature_an2k7minutiae.h>
```

Inheritance diagram for BiometricEvaluation::Feature::AN2K7Minutiae:



Classes

- class [EncodingMethod](#)
Methods for encoding minutiae data in an AN2K record.
- struct [FingerprintReadingSystem](#)
Representation of information about a fingerprint reader system.
- class [PatternClassification](#)
Pattern classification codes.

Public Types

- typedef std::vector
< [PatternClassification::Entry](#) > **PatternClassificationSet**
- typedef struct
[FingerprintReadingSystem](#) **FingerprintReadingSystem**

Public Member Functions

- [AN2K7Minutiae](#) (const std::string &filename, int recordNumber) throw (Error::DataError, Error::File-Error)
Construct an AN2K7 [Minutiae](#) object from file data.
- [AN2K7Minutiae](#) (Memory::uint8Array &buf, int recordNumber) throw (Error::DataError)
Construct an AN2K7 [Minutiae](#) object from data contained in a memory buffer.
- PatternClassificationSet [getPatternClassificationSet](#) () const
Obtain the set fingerprint pattern classifications.
- [FingerprintReadingSystem](#) [getOriginatingFingerprintReadingSystem](#) () const throw (Error::ObjectDoes-NotExist)
- MinutiaeFormat::Kind [getFormat](#) () const
Obtain the minutiae format kind.
- MinutiaPointSet [getMinutiaPoints](#) () const
Obtain the set of finger minutiae data points. The set may be empty.
- RidgeCountItemSet [getRidgeCountItems](#) () const
Obtain the set of ridge count data items. The set may be empty.
- CorePointSet [getCores](#) () const
Obtains the set of core positions. The set may be empty.
- DeltaPointSet [getDeltas](#) () const
Obtains the set of delta positions. The set may be empty.

Static Public Member Functions

- static
Finger::PatternClassification::Kind [convertPatternClassification](#) (const char *fpc) throw (Error::DataError)
Convert string read from AN2K record into a [PatternClassification](#).
- static
Finger::PatternClassification::Kind [convertPatternClassification](#) (const [PatternClassification::Entry](#) &entry) throw (Error::DataError)
Convert a standard [PatternClassification::Entry](#) to a [PatternClassification::Kind](#).
- static EncodingMethod::Kind [convertEncodingMethod](#) (const char *mem) throw (Error::DataError)
Convert string read from AN2K record into a [EncodingMethod](#).
- static [Image::Coordinate](#) [convertCoordinate](#) (const char *str, bool calculateDistance=true) throw (Error::DataError)
Obtain a [Coordinate](#) given an AN2K entry.

E.2.1 Detailed Description

A class to represent a set of minutiae in an ANSI/NIST record.

Each minutiae point, ridge count item, core, and delta is represented in the native ANSI/NIST format.

E.2.2 Constructor & Destructor Documentation

E.2.2.1 BiometricEvaluation::Feature::AN2K7Minutiae::AN2K7Minutiae (const std::string & filename, int recordNumber) throw (Error::DataError, Error::FileError)

Construct an AN2K7 [Minutiae](#) object from file data.

The file contains a complete ANSI/NIST record, and an object of this class represents a single fingerprint minutiae record.

Parameters

in	<i>filename</i>	The name of the file containing the complete ANSI/NIST record.
in	<i>recordNumber</i>	Which fingerprint minutiae record to read from the complete AN2K record.

Exceptions

Error::FileError	An error occurred when opening or reading from the file.
Error::DataError	An error occurred reading the AN2K record, or there is no fingerprint minutiae record for the requested number.

E.2.2.2 BiometricEvaluation::Feature::AN2K7Minutiae::AN2K7Minutiae (Memory::uint8Array & buf, int recordNumber) throw (Error::DataError)

Construct an AN2K7 [Minutiae](#) object from data contained in a memory buffer.

The buffer contains a complete ANSI/NIST record, and an object of this class represents a single fingerprint

minutiae record.

Parameters

in	<i>buf</i>	The memory buffer containing the complete ANSI/NIST record.
in	<i>recordNumber</i>	Which fingerprint minutiae record to read from the complete AN2K record.

Exceptions

<i>Error::DataError</i>	An error occurred reading the AN2K record, or there is no fingerprint minutiae record for the requested number.
---	---

E.2.3 Member Function Documentation

E.2.3.1 static `Finger::PatternClassification::Kind BiometricEvaluation::Feature::AN2K7Minutiae::convertPatternClassification (const char * fpc) throw (Error::DataError)`
[static]

Convert string read from AN2K record into a [PatternClassification](#).

Parameters

in	<i>fpc</i>	Value for pattern classification read from AN2K record.
----	------------	---

Exceptions

<i>Error::DataError</i>	Invalid value for <i>fpc</i> .
---	--------------------------------

E.2.3.2 static `Finger::PatternClassification::Kind BiometricEvaluation::Feature::AN2K7Minutiae::convertPatternClassification (const PatternClassification::Entry & entry) throw (Error::DataError)`
[static]

Convert a standard [PatternClassification::Entry](#) to a `PatternClassification::Kind`.

Parameters

in	<i>entry</i>	A standard pattern classification entry
----	--------------	---

Exceptions

<i>Error::DataError</i>	Non-standard pattern classification entry.
---	--

E.2.3.3 static `EncodingMethod::Kind BiometricEvaluation::Feature::AN2K7Minutiae::convertEncodingMethod (const char * mem) throw (Error::DataError)` [static]

Convert string read from AN2K record into a [EncodingMethod](#).

Parameters

<i>in</i>	<i>mem</i>	Value for minutiae encoding method read from AN2K record.
-----------	------------	---

Exceptions

<i>Error::DataError</i>	Invalid value for mem.
---	------------------------

E.2.3.4 PatternClassificationSet BiometricEvaluation::Feature::AN2K7Minutiae::getPatternClassificationSet () const

Obtain the set fingerprint pattern classifications.

The code returned may be a standard code or user-defined. Applications should call isPatternClassificationStandard() to check.

E.2.3.5 FingerprintReadingSystem BiometricEvaluation::Feature::AN2K7Minutiae::getOriginatingFingerprintReadingSystem () const throw (Error::ObjectDoesNotExist)

Obtain the originating fingerprint reading system.

Exceptions

<i>Error::ObjectDoesNotExist</i>	The optional OFR field has been excluded.
--	---

E.2.3.6 static Image::Coordinate BiometricEvaluation::Feature::AN2K7Minutiae::convertCoordinate (const char * *str*, bool *calculateDistance* = true) throw (Error::DataError) [static]

Obtain a Coordinate given an AN2K entry.

This AN2K entry is formatted as "XXXXYYYYY".

Parameters

<i>in</i>	<i>str</i>	Coordinate string from an AN2K record.
<i>in</i>	<i>calculateDistance</i>	Whether or not to calculate the [xy]Distance portion of the Coordinate.

Returns

[*Image::Coordinate*](#) representation of *str*.

Exceptions

<i>Error::DataError</i>	Invalid format of <i>str</i> .
---	--------------------------------

E.3 BiometricEvaluation::Finger::AN2KMinutiaeDataRecord Class Reference

Representation of a Type-9 Record from an AN2K file.

```
#include <be_finger_an2kminutiae_data_record.h>
```

Public Member Functions

- [AN2KMinutiaeDataRecord](#) (const string &filename, int recordNumber) throw (Error::DataError, Error::FileError)
Construct an [AN2KMinutiaeDataRecord](#) object from data contained in a file on disk.
- [AN2KMinutiaeDataRecord](#) (Memory::uint8Array &buf, int recordNumber) throw (Error::DataError)
Construct an [AN2KMinutiaeDataRecord](#) object from data contained in a memory buffer.
- `tr1::shared_ptr`
< [Feature::AN2K7Minutiae](#) > [getAN2K7Minutiae](#) () const
Obtain the "standard" minutiae data from this Type-9 Record (fields 9.005 - 9.012).
- `Impression::Kind` [getImpressionType](#) () const
Return impression type field from Type-9 Record.
- `map< uint16_t, Memory::uint8Array >` [getRegisteredVendorBlock](#) (Feature::MinutiaeFormat::Kind vendor) const throw (Error::NotImplemented)
Obtain data recorded in a registered vendor minutiae block found in this Type-9 Record.

E.3.1 Detailed Description

Representation of a Type-9 Record from an AN2K file.

Type-9 Records may contain only "standard" minutiae data (fields 9.005 - 9.012) or any combination of "standard" minutiae data and registered vendor minutiae data (several vendors from fields 9.013 - 9.175).

E.3.2 Constructor & Destructor Documentation

E.3.2.1 BiometricEvaluation::Finger::AN2KMinutiaeDataRecord::AN2KMinutiaeDataRecord (const string & filename, int recordNumber) throw (Error::DataError, Error::FileError)

Construct an [AN2KMinutiaeDataRecord](#) object from data contained in a file on disk.

The file contains a complete ANSI/NIST record, and an object of this class represents a single fingerprint minutiae record.

Parameters

in	<i>filename</i>	The name of the file containing the complete ANSI/NIST record.
in	<i>recordNumber</i>	Which fingerprint minutiae record to read from the complete AN2K record.

Exceptions

Error::FileError	An error occurred when opening or reading from the file.
Error::DataError	An error occurred reading the AN2K record, or there is no fingerprint minutiae record for the requested number.

E.3.2.2 BiometricEvaluation::Finger::AN2KMinutiaeDataRecord::AN2KMinutiaeDataRecord (Memory::uint8Array & *buf*, int *recordNumber*) throw (Error::DataError)

Construct an [AN2KMinutiaeDataRecord](#) object from data contained in a memory buffer.

The buffer contains a complete ANSI/NIST record, and an object of this class represents a single fingerprint minutiae record.

Parameters

in	<i>buf</i>	The memory buffer containing the complete ANSI/NIST record.
in	<i>recordNumber</i>	Which fingerprint minutiae record to read from the complete AN2K record.

Exceptions

Error::DataError	An error occurred reading the AN2K record, or there is no fingerprint minutiae record for the requested number.
----------------------------------	---

E.3.3 Member Function Documentation

E.3.3.1 tr1::shared_ptr<Feature::AN2K7Minutiae> BiometricEvaluation::Finger::AN2KMinutiaeDataRecord::getAN2K7Minutiae () const

Obtain the "standard" minutiae data from this Type-9 Record (fields 9.005 - 9.012).

Returns

Shared pointer to an AN2KMinutiae object containing the standard format minutiae data found in this Type-9 Record.

E.3.3.2 Impression::Kind BiometricEvaluation::Finger::AN2KMinutiaeDataRecord::getImpressionType () const

Return impression type field from Type-9 Record.

Returns

[Impression](#) type of the image from which minutiae points were generated.

E.3.3.3 map<uint16_t, Memory::uint8Array> BiometricEvaluation::Finger::AN2KMinutiaeDataRecord::getRegisteredVendorBlock (Feature::MinutiaeFormat::Kind *vendor*) const throw (Error::NotImplemented)

Obtain data recorded in a registered vendor minutiae block found in this Type-9 Record.

Parameters

in	<i>vendor</i>	The vendor whose registered minutiae blocks are being requested.
----	---------------	--

Returns

A map of the registered vendor minutiae block fields. The map key is the AN2K Field number. The value is a uint8Array of the ASCII data found at that field. All Fields will be present as keys even if there was no data recorded in that Field.

Exceptions

<i>Error::NotImplemented</i>	Cannot return a map of fields for vendor, likely because there exists a better, native implementation of accessing minutiae data in AN2KMinutiaeDataRecord .
------------------------------	--

E.4 BiometricEvaluation::View::AN2KViewVariableResolution::AN2KQualityMetric Struct Reference

A structure to represent an AN2K quality metric.

```
#include <be_view_an2kview_varres.h>
```

Public Attributes

- Finger::Position::Kind **position**
- uint8_t **score**
- uint16_t **vendorID**
- uint16_t **productCode**

E.4.1 Detailed Description

A structure to represent an AN2K quality metric.

The quality metric is an optional field in the Type-13 (Latent), Type-14 (Fingerprint and Segmentation) and Type-15 (Palmpoint). The NIST Quality Metric is also returned via this structure.

E.5 BiometricEvaluation::DataInterchange::AN2KRecord Class Reference

A class to represent an entire ANSI/NIST record.

```
#include <be_data_interchange_an2k.h>
```

Classes

- struct [CharacterSet](#)
- struct [DomainName](#)

Representation of a domain name for the user-defined Type-2 logical record implementation.

Public Types

- typedef struct [DomainName](#) [DomainName](#)
- typedef struct [CharacterSet](#) [CharacterSet](#)

Public Member Functions

- [AN2KRecord](#) (const std::string filename) throw ([Error::FileError](#), [Error::DataError](#))
Constructor taking an AN2K record from a file.
- [AN2KRecord](#) ([Memory::uint8Array](#) &buf) throw ([Error::DataError](#))
Constructor taking an AN2K record from a buffer.
- string [getVersionNumber](#) () const
- string [getDate](#) () const
- string [getDestinationAgency](#) () const
- string [getOriginatingAgency](#) () const
- string [getTransactionControlNumber](#) () const
- string [getNativeScanningResolution](#) () const
- string [getNominalTransmittingResolution](#) () const
- uint32_t [getFingerLatentCount](#) () const
Obtain the count of latent (Type-13) finger views.
- std::vector
 < [Finger::AN2KViewLatent](#) > [getFingerLatents](#) () const
Obtain all latent (Type-13) finger views.
- uint32_t [getFingerCaptureCount](#) () const
Obtain the count of capture (Type-14) finger views.
- std::vector
 < [Finger::AN2KViewCapture](#) > [getFingerCaptures](#) () const
Obtain all capture (Type-14) finger views.
- std::vector
 < [Finger::AN2KMinutiaeDataRecord](#) > [getMinutiaeDataRecordSet](#) () const
Obtain all minutiae (Type-9) data.
- uint8_t [getPriority](#) () const
Obtain the urgency with which a response is required.
- [DomainName](#) [getDomainName](#) () const
Obtain the identifier of the domain name for the user-defined Type-2 logical record implementation.
- struct tm [getGreenwichMeanTime](#) () const
Obtain the date and time of encoding in terms of GMT units.
- std::vector< [CharacterSet](#) > [getDirectoryOfCharacterSets](#) () const
Obtain the list of character sets other than 7-bit ASCII that may appear in the transaction.

Static Public Member Functions

- static set< int > [recordLocations](#) ([Memory::uint8Array](#) &buf, const [View::AN2KView::RecordType::Kind](#) recordType) throw ([Error::DataError](#))
Find the position within a buffer of all Records of a particular type.
- static set< int > [recordLocations](#) (const ANSI_NIST *an2k, const [View::AN2KView::RecordType::Kind](#) recordType)
Find the position within an ANSI_NIST struct of all Records of a particular type.

E.5.1 Detailed Description

A class to represent an entire ANSI/NIST record.

An object of this class can be used to retrieve all the general record information, finger views, and other components of the ANSI/NIST record.

E.5.2 Member Typedef Documentation

E.5.2.1 `typedef struct DomainName BiometricEvaluation::DataInterchange::AN2KRecord::DomainName`

Convenience typedef for struct [DomainName](#)

E.5.2.2 `typedef struct CharacterSet BiometricEvaluation::DataInterchange::AN2KRecord::CharacterSet`

Convenience typedef for struct [CharacterSet](#)

E.5.3 Constructor & Destructor Documentation

E.5.3.1 `BiometricEvaluation::DataInterchange::AN2KRecord::AN2KRecord (const std::string filename) throw (Error::FileError, Error::DataError)`

Constructor taking an AN2K record from a file.

Parameters

<code>in</code>	<code><i>filename</i></code>	The name of the file containing the complete ANSI/NIST record.
-----------------	------------------------------	--

Exceptions

<code>Error::FileError</code>	An error occurred when opening or reading the file.
<code>Error::DataError</code>	An error occurred when processing the AN2K record.

E.5.3.2 `BiometricEvaluation::DataInterchange::AN2KRecord::AN2KRecord (Memory::uint8Array & buf) throw (Error::DataError)`

Constructor taking an AN2K record from a buffer.

Parameters

<code>in</code>	<code><i>buf</i></code>	The memory buffer containing the complete ANSI/NIST record.
-----------------	-------------------------	---

Exceptions

<code>Error::DataError</code>	An error occurred when processing the AN2K record.
---	--

E.5.4 Member Function Documentation

E.5.4.1 static set<int> BiometricEvaluation::DataInterchange::AN2KRecord::recordLocations (Memory::uint8Array & *buf*, const View::AN2KView::RecordType::Kind *recordType*) throw (Error::DataError) [static]

Find the position within a buffer of all Records of a particular type.

Parameters

in	<i>buf</i>	AN2K Buffer to search.
in	<i>recordType</i>	The ID of the Record to search for.

Returns

Set of integer positions within *buf* where a *recordType* Record is located.

Exceptions

<i>Error::DataError</i>	An error occurred when processing the AN2K record.
---	--

E.5.4.2 static set<int> BiometricEvaluation::DataInterchange::AN2KRecord::recordLocations (const ANSI_NIST * *an2k*, const View::AN2KView::RecordType::Kind *recordType*) [static]

Find the position within an ANSI_NIST struct of all Records of a particular type.

Parameters

in	<i>an2k</i>	ANSI_NIST struct to search.
in	<i>recordType</i>	The ID of the Record to search for.

Returns

Set of integer positions within the ANSI_NIST struct where a *recordType* Record is located.

E.5.4.3 string BiometricEvaluation::DataInterchange::AN2KRecord::getVersionNumber () const

Returns

The record version field in the Type-1 record.

E.5.4.4 string BiometricEvaluation::DataInterchange::AN2KRecord::getDate () const

Returns

The date field in the Type-1 record.

E.5.4.5 `string BiometricEvaluation::DataInterchange::AN2KRecord::getDestinationAgency () const`

Returns

The destination agency ID.

E.5.4.6 `string BiometricEvaluation::DataInterchange::AN2KRecord::getOriginatingAgency () const`

Returns

The originating agency ID.

E.5.4.7 `string BiometricEvaluation::DataInterchange::AN2KRecord::getTransactionControlNumber () const`

Returns

The transaction control number.

E.5.4.8 `string BiometricEvaluation::DataInterchange::AN2KRecord::getNativeScanningResolution () const`

Returns

The native scanning resolution.

E.5.4.9 `string BiometricEvaluation::DataInterchange::AN2KRecord::getNominalTransmittingResolution () const`

Returns

The nominal transmitting resolution.

E.5.4.10 `uint32_t BiometricEvaluation::DataInterchange::AN2KRecord::getFingerLatentCount () const`

Obtain the count of latent (Type-13) finger views.

Returns

The number of latents in the AN2K record.

E.5.4.11 `std::vector<Finger::AN2KViewLatent> BiometricEvaluation::DataInterchange::AN2KRecord::getFingerLatents () const`

Obtain all latent (Type-13) finger views.

The returned vector will be empty when no latent views are present in the [AN2KRecord](#).

Returns

A vector of AN2KViewLatent objects, each representing a single latent finger view.

E.5.4.12 `uint32_t BiometricEvaluation::DataInterchange::AN2KRecord::getFingerCaptureCount () const`

Obtain the count of capture (Type-14) finger views.

Returns

The number of captures in the AN2K record.

E.5.4.13 `std::vector<Finger::AN2KViewCapture> BiometricEvaluation::DataInterchange::AN2KRecord::getFingerCaptures () const`

Obtain all capture (Type-14) finger views.

The returned vector will be empty when no capture views are present in the [AN2KRecord](#).

Returns

A vector of AN2KViewCapture objects, each representing a single capture finger view.

E.5.4.14 `std::vector<Finger::AN2KMinutiaeDataRecord> BiometricEvaluation::DataInterchange::AN2KRecord::getMinutiaeDataRecordSet () const`

Obtain all minutiae (Type-9) data.

Returns

A vector of AN2KMinutiaeDataRecord objects, each representing a single Type-9 Record.

E.5.4.15 `uint8_t BiometricEvaluation::DataInterchange::AN2KRecord::getPriority () const`

Obtain the urgency with which a response is required.

Returns

Priority (1:High - 9:Low)

E.5.4.16 `DomainName BiometricEvaluation::DataInterchange::AN2KRecord::getDomainName () const`

Obtain the identifier of the domain name for the user-defined Type-2 logical record implementation.

Returns

[DomainName](#) struct with identifier and version information (if defined).

E.5.4.17 `struct tm BiometricEvaluation::DataInterchange::AN2KRecord::getGreenwichMeanTime () const`
`[read]`

Obtain the date and time of encoding in terms of GMT units.

Returns

struct tm encoding of the GMT field.

E.5.4.18 `std::vector<CharacterSet> BiometricEvaluation::DataInterchange::AN2KRecord::getDirectoryOf-
CharacterSets () const`

Obtain the list of character sets other than 7-bit ASCII that may appear in the transaction.

Returns


Vector of [CharacterSet](#) structs representing other character sets that may appear in the transaction.

E.6 BiometricEvaluation::Finger::AN2KView Class Reference

A class to represent single finger view and derived information.

```
#include <be_finger_an2kview.h>
```

Inheritance diagram for BiometricEvaluation::Finger::AN2KView:



Public Member Functions

- `vector< AN2KMinutiaeDataRecord > getMinutiaeDataRecordSet () const` throw (Error::DataError)
Obtain the set of minutiae records.
- `Finger::PositionSet getPosition () const`
Obtain the set of finger positions.
- `Finger::Impression::Kind getImpressionType () const`
Obtain the finger impression code.

Static Public Member Functions

- static Finger::Position::Kind [convertPosition](#) (int an2kFGP) throw (Error::DataError)
Convert a compression algorithm indicator from an AN2K finger image record.
- static Finger::PositionSet [populateFGP](#) (FIELD *field) throw (Error::DataError)
Read the finger positions from an AN2K record.
- static Finger::Impression::Kind [convertImpression](#) (const unsigned char *str) throw (Error::DataError)
Convert an impression code from a string.
- static
Finger::FingerImageCode::Kind [convertFingerImageCode](#) (const char *str) throw (Error::DataError)
Convert an finger image code from a string.

Protected Member Functions

- [AN2KView](#) (const std::string filename, const RecordType::Kind typeID, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError, Error::FileError)
Construct an AN2K finger view from a file.
- [AN2KView](#) (Memory::uint8Array &buf, const RecordType::Kind typeID, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError)
Construct an AN2K finger view from a buffer.
- void [addMinutiaeDataRecord](#) (Finger::AN2KMinutiaeDataRecord &mdr)
Add a minutiae data record to the [AN2KMinutiaeDataRecord](#) set.
- void [setPositions](#) (Finger::PositionSet &ps)
Add a position set to the collection of position sets.
- void [setImpressionType](#) (Finger::Impression::Kind &imp)
Mutator for the impression type.

Additional Inherited Members

E.6.1 Detailed Description

A class to represent single finger view and derived information.

A base [Finger::AN2KView](#) object represents an ANSI/NIST Type-3/4/5/6 record, and can return the image as well as the other information associated with that image, such as the minutiae from the corresponding Type-9 record.

For these types of records, the image resolution and scan resolution are identical. For compressed images, applications can compare the image resolution and size taken from the Type-3/4/5/6 record to that returned by the [Image](#) object directly.

E.6.2 Constructor & Destructor Documentation

- E.6.2.1 [BiometricEvaluation::Finger::AN2KView::AN2KView](#) (const std::string *filename*, const RecordType::Kind *typeID*, const uint32_t *recordNumber*) throw (Error::ParameterError, Error::DataError, Error::FileError) [protected]

Construct an AN2K finger view from a file.

The file must contain the entire AN2K record, not just the finger image and/or minutiae records.

Parameters

in	<i>filename</i>	The name of the file containing the AN2K record.
in	<i>typeID</i>	The type of AN2K finger view: Type-3/Type-4/etc.
in	<i>recordNumber</i>	Which finger record to read as there may be multiple finger views of the same type within a single AN2K record.

Exceptions

<i>Error::ParameterError</i>	An invalid parameter was passed in.
<i>Error::DataError</i>	An error occurred when parsing the AN2K record.
<i>Error::FileError</i>	An error occurred when reading the file.

E.6.2.2 BiometricEvaluation::Finger::AN2KView::AN2KView (Memory::uint8Array & buf, const RecordType::Kind typeID, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError) [protected]

Construct an AN2K finger view from a buffer.

The buffer must contain the entire AN2K record, not just the finger image and/or minutiae records.

Parameters

in	<i>buf</i>	The buffer containing the AN2K record.
in	<i>typeID</i>	The type of AN2K finger view: Type-3/Type-4/etc.
in	<i>recordNumber</i>	Which finger record to read as there may be multiple finger views of the same type within a single AN2K record.

Exceptions

<i>Error::ParameterError</i>	An invalid parameter was passed in.
<i>Error::DataError</i>	An error occurred when parsing the AN2K record.

E.6.3 Member Function Documentation

E.6.3.1 static Finger::Position::Kind BiometricEvaluation::Finger::AN2KView::convertPosition (int an2kFGP) throw (Error::DataError) [static]

Convert a compression algorithm indicator from an AN2K finger image record.

Parameters

in	<i>an2kFGP</i>	A finger position code as defined by the AN2K standard.
----	----------------	---

Exceptions

<i>Error::DataError</i>	The position code is invalid.
---	-------------------------------

E.6.3.2 static Finger::PositionSet BiometricEvaluation::Finger::AN2KView::populateFGP (FIELD * *field*) throw (Error::DataError) [static]

Read the finger positions from an AN2K record.

An AN2K finger image record can have multiple values * for the finger position. Pull them out of the position field and return them as a set.

Exceptions

Error::DataError	The data contains an invalid value.
----------------------------------	-------------------------------------

E.6.3.3 static Finger::FingerImageCode::Kind BiometricEvaluation::Finger::AN2KView::convertFingerImageCode (const char * *str*) throw (Error::DataError) [static]

Convert an finger image code from a string.

Parameters

in	<i>str</i>	The character string containing the image code.
----	------------	---

Returns

A [FingerImageCode](#) value.

Exceptions

Error::DataError	The string contains an invalid image code.
----------------------------------	--

E.6.3.4 vector<AN2KMinutiaeDataRecord> BiometricEvaluation::Finger::AN2KView::getMinutiaeDataRecordSet () const throw (Error::DataError)

Obtain the set of minutiae records.

Because it is possible to have more than one Type-9 record associated with a finger view, this method returns a set of objects, each one representing a single Type-9 record.

Returns

The vector of minutiae data records.

E.6.3.5 Finger::PositionSet BiometricEvaluation::Finger::AN2KView::getPositions () const

Obtain the set of finger positions.

An AN2K finger image record contains a set of possible finger positions. This method returns that set as read from the image record. Any minutiae record (Type-9) associated with this image will have its own set of positions.

E.6.3.6 `Finger::Impression::Kind BiometricEvaluation::Finger::AN2KView::getImpressionType () const`

Obtain the finger impression code.

Returns

The finger impression code.

E.6.3.7 `void BiometricEvaluation::Finger::AN2KView::addMinutiaeDataRecord (Finger::AN2KMinutiaeDataRecord & mdr) [protected]`

Add a minutiae data record to the [AN2KMinutiaeDataRecord](#) set.

Parameters

<code>in</code>	<code><i>mdr</i></code>	The minutiae data record to be added.
-----------------	-------------------------	---------------------------------------

E.6.3.8 `void BiometricEvaluation::Finger::AN2KView::setPositions (Finger::PositionSet & ps) [protected]`

Add a position set to the collection of position sets.

Parameters

<code>in</code>	<code><i>ps</i></code>	The position set to be added.
-----------------	------------------------	-------------------------------

E.6.3.9 `void BiometricEvaluation::Finger::AN2KView::setImpressionType (Finger::Impression::Kind & imp) [protected]`

Mutator for the impression type.

Parameters


<code>in</code>	<code><i>imp</i></code>	The impression type for this finger view.
-----------------	-------------------------	---

E.7 BiometricEvaluation::View::AN2KView Class Reference

A class to represent single biometric view and derived information.

```
#include <be_view_an2kview.h>
```

Inheritance diagram for BiometricEvaluation::View::AN2KView:



Classes

- class [DeviceMonitoringMode](#)
The level of human monitoring for the image capture device.
- class [RecordType](#)
The type of AN2K record.

Public Member Functions

- [AN2KView](#) (const std::string filename, const RecordType::Kind typeID, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError, Error::FileError)
Construct an AN2K view from a file.
- [AN2KView](#) (Memory::uint8Array &buf, const RecordType::Kind typeID, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError)
Construct an AN2K view from a buffer.
- tr1::shared_ptr< [Image::Image](#) > [getImage](#) () const
Obtain the image used for the finger view.
- [Image::Size](#) [getImageSize](#) () const
Obtain the image size.
- [Image::Resolution](#) [getImageResolution](#) () const
Obtain the image resolution.
- uint32_t [getImageDepth](#) () const
Obtain the image depth.
- Image::CompressionAlgorithm::Kind [getCompressionAlgorithm](#) () const
Obtain the compression algorithm used on the image.
- [Image::Resolution](#) [getScanResolution](#) () const
Obtain the image scan resolution.
- vector
< [Finger::AN2KMinutiaeDataRecord](#) > [getMinutiaeDataRecordSet](#) () const throw (Error::DataError)
Obtain the set of minutiae records.
- RecordType::Kind [getRecordType](#) () const
Obtain the ANSI-NIST record type.

Static Public Member Functions

- static [DeviceMonitoringMode::Kind](#) [convertDeviceMonitoringMode](#) (const char *dmm) throw (Error::DataError)
Convert a device monitoring mode indicator from an AN2K record.
- static [Image::CompressionAlgorithm::Kind](#) [convertCompressionAlgorithm](#) (const uint16_t recordType, const unsigned char *an2kValue) throw (Error::ParameterError, Error::DataError)
Convert a compression algorithm indicator from an AN2K finger image record.

Static Public Attributes

- static const double [MinimumScanResolutionPPMM](#)
Constants to define the minimum resolution used for fingerprint images in an AN2k record.
- static const double **HalfMinimumScanResolutionPPMM**
- static const int [FixedResolutionBitDepth](#) = 8
The defined bit-depth for fixed-resolution images.

Protected Member Functions

- [Memory::AutoBuffer](#)< ANSI_NIST > [getAN2K](#) () const
Obtain the complete ANSI/NIST record set.
- RECORD * [getAN2KRecord](#) () const
Obtain a pointer to the single ANSI/NIST record.
- void [setImageData](#) (const [Memory::AutoArray](#)< uint8_t > &imageData)
Mutator for the image data.
- void [setImageResolution](#) (const [Image::Resolution](#) &ir)
Mutator for the image resolution.
- void [setImageDepth](#) (const uint32_t depth)
Mutator for the image depth.
- void [setScanResolution](#) (const [Image::Resolution](#) &ir)
Mutator for the scan resolution.
- void [setCompressionAlgorithm](#) (const [Image::CompressionAlgorithm::Kind](#) &ca)
Mutator for the compression algorithm.

E.7.1 Detailed Description

A class to represent single biometric view and derived information.

This abstraction represents the image and derived information taken from an ANSI/NIST record.

For these types of records, the image resolution and scan resolution are identical. For compressed images, applications can compare the image resolution and size taken from the Type-3/4/5/6 record to that returned by the [Image](#) object directly.

E.7.2 Constructor & Destructor Documentation

E.7.2.1 `BiometricEvaluation::View::AN2KView::AN2KView (const std::string filename, const RecordType::Kind typeID, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError, Error::FileError)`

Construct an AN2K view from a file.

The file must contain the entire AN2K record, not just the image and other view-related records.

E.7.2.2 `BiometricEvaluation::View::AN2KView::AN2KView (Memory::uint8Array & buf, const RecordType::Kind typeID, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError)`

Construct an AN2K view from a buffer.

The buffer must contain the entire AN2K record, not just the image and other view-related records.

E.7.3 Member Function Documentation

E.7.3.1 `static DeviceMonitoringMode::Kind BiometricEvaluation::View::AN2KView::convertDeviceMonitoringMode (const char * dmm) throw (Error::DataError)`
[static]

Convert a device monitoring mode indicator from an AN2K record.

Parameters

<i>dmm</i>	Item value for device monitoring mode from an AN2K record.
------------	--

Returns

[DeviceMonitoringMode](#) representation of dmm.

Exceptions

Error::DataError	Invalid format of dmm.
----------------------------------	------------------------

E.7.3.2 `static Image::CompressionAlgorithm::Kind BiometricEvaluation::View::AN2KView::convertCompressionAlgorithm (const uint16_t recordType, const unsigned char * an2kValue) throw (Error::ParameterError, Error::DataError)` [static]

Convert a compression algorithm indicator from an AN2K finger image record.

Parameters

<i>recordType</i>	The AN2K record type as an integer, allowing the value taken directly from the AN2K record or a RecordType::Kind to be passed in.
<i>an2kValue</i>	Compression type data as read from an AN2K record.

Returns

The compression algorithm.

Exceptions

<i>Error::DataError</i>	Invalid compression algorithm for record type.
<i>Error::ParameterError</i>	Invalid record type.

E.7.3.3 `tr1::shared_ptr<Image::Image> BiometricEvaluation::View::AN2KView::getImage () const` `[virtual]`

Obtain the image used for the finger view.

Not all finger views will have an image, however the derived information, such as minutiae, may be present.

Implements [BiometricEvaluation::View::View](#).

E.7.3.4 `Image::Size BiometricEvaluation::View::AN2KView::getImageSize () const` `[virtual]`

Obtain the image size.

This value is as present in the biometric record, and not in the image data itself. Normally, this value and the actual image size must be equal, but applications can check for inconsistencies. In the case of raw images, however, the value obtained with this method must be accepted as correct.

Implements [BiometricEvaluation::View::View](#).

E.7.3.5 `Image::Resolution BiometricEvaluation::View::AN2KView::getImageResolution () const` `[virtual]`

Obtain the image resolution.

[Image](#) resolution is taken from the biometric record, and not from the image data. In some cases, the resolution may be the components of the pixel ratio, and applications must check the [Image::Resolution::units](#) field for value NA.

Implements [BiometricEvaluation::View::View](#).

E.7.3.6 `uint32_t BiometricEvaluation::View::AN2KView::getImageDepth () const` `[virtual]`

Obtain the image depth.

This value is as present in the biometric record, and not in the image data itself. Normally, this value and the actual image depth must be equal, but applications can check for inconsistencies. In the case of raw images, however, the value obtained with this method must be accepted as correct.

Implements [BiometricEvaluation::View::View](#).

E.7.3.7 Image::CompressionAlgorithm::Kind BiometricEvaluation::View::AN2KView::getCompressionAlgorithm () const [virtual]

Obtain the compression algorithm used on the image.

This value is as present in the biometric record, and not obtained from the image data itself.

Implements [BiometricEvaluation::View::View](#).

E.7.3.8 Image::Resolution BiometricEvaluation::View::AN2KView::getScanResolution () const [virtual]

Obtain the image scan resolution.

This value is as present in the biometric record, and not in the image data itself. Normally, this value and the actual image resolution must be equal, but applications can check for inconsistencies.

Implements [BiometricEvaluation::View::View](#).

E.7.3.9 vector<Finger::AN2KMinutiaeDataRecord> BiometricEvaluation::View::AN2KView::getMinutiaeDataRecordSet () const throw (Error::DataError)

Obtain the set of minutiae records.

Each [AN2KViewVariableResolution](#) may have more than one associated Type-9 record and each Type-9 record may have more than one minutiae format.

Returns

A vector of minutiae data records.

E.7.3.10 RecordType::Kind BiometricEvaluation::View::AN2KView::getRecordType () const

Obtain the ANSI-NIST record type.

Returns

The type of record used to construct this object.

E.7.3.11 RECORD* BiometricEvaluation::View::AN2KView::getAN2KRecord () const [protected]

Obtain a pointer to the single ANSI/NIST record.


Child classes use this method to obtain a pointer to the specific ANSI/NIST record that was searched for by this class object.

E.8 BiometricEvaluation::Finger::AN2KViewCapture Class Reference

Represents an ANSI/NIST variable-resolution finger image.

```
#include <be_finger_an2kview_capture.h>
```

Inheritance diagram for BiometricEvaluation::Finger::AN2KViewCapture:



Classes

- class [AmputatedBandaged](#)
Enumeration of the finger amputated or bandaged code, a reason that a capture could not be made.
- struct [FingerSegmentPosition](#)
Locations of an individual finger segment in a slap.

Public Types

- typedef struct [FingerSegmentPosition](#) **FingerSegmentPosition**
- typedef std::vector [FingerSegmentPosition](#) > **FingerSegmentPositionSet**

Public Member Functions

- [AN2KViewCapture](#) (const std::string &filename, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError, Error::FileError)
Construct an AN2K finger view from a file.
- [AN2KViewCapture](#) (Memory::uint8Array &buf, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError)
Construct an AN2K finger view using from a memory buffer.
- QualityMetricSet [extractNISTQuality](#) (const FIELD *field) throw (Error::DataError)
Extract the NQM information from an AN2K FIELD.
- PositionDescriptors [getPrintPositionDescriptors](#) () const
Return search position descriptors.
- QualityMetricSet [getNISTQualityMetric](#) () const
Obtain the NIST quality metric for all segmented finger images.
- QualityMetricSet [getSegmentationQualityMetric](#) () const
Obtain the segmentation quality metric for all segmented finger images.

- [AmputatedBandaged::Kind](#) [getAmputatedBandaged](#) () const
- [FingerSegmentPositionSet](#) [getFingerSegmentPositionSet](#) () const
- [FingerSegmentPositionSet](#) [getAlternateFingerSegmentPositionSet](#) () const
- [QualityMetricSet](#) [getFingerprintQualityMetric](#) () const

Obtain metrics for fingerprint image quality score data for the image stored in this record.

Static Public Member Functions

- static [AmputatedBandaged::Kind](#) [convertAmputatedBandaged](#) (const char *ampcd) throw (Error::DataError)
- static [FingerSegmentPosition](#) [convertFingerSegmentPosition](#) (const SUBFIELD *sf) throw (Error::DataError)
- static [FingerSegmentPosition](#) [convertAlternateFingerSegmentPosition](#) (const SUBFIELD *sf) throw (Error::DataError)

Convert string read from AN2K record into a [AmputatedBandaged](#) code.

Convert SUBFIELD read from AN2K record into a [FingerSegmentPosition](#) struct.

Convert SUBFIELD read from AN2K record into an [AlternateFingerSegmentPosition](#) struct.

Additional Inherited Members

E.8.1 Detailed Description

Represents an ANSI/NIST variable-resolution finger image.

If the complete ANSI/NIST record contains a corresponding Type-9 (finger minutiae) record, an object of this class can be used to retrieve the minutiae set(s).

E.8.2 Constructor & Destructor Documentation

E.8.2.1 [BiometricEvaluation::Finger::AN2KViewCapture::AN2KViewCapture](#) (const std::string & *filename*, const uint32_t *recordNumber*) throw (Error::ParameterError, Error::DataError, Error::FileError)

Construct an AN2K finger view from a file.

The file must contain the entire AN2K record, not just the finger image and/or minutiae records. The object is constructed based on the nth variable resolution record found.

Parameters

in	<i>filename</i>	The name of the file containing the complete ANSI/NIST record.
in	<i>recordNumber</i>	The number of variable resolution record to read from the complete AN2K record.

Exceptions

Error::ParameterError	
Error::DataError	
Error::FileError	An error occurred when opening or reading the file.

E.8.2.2 `BiometricEvaluation::Finger::AN2KViewCapture::AN2KViewCapture (Memory::uint8Array & buf, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError)`

Construct an AN2K finger view using from a memory buffer.

The buffer must contain the entire AN2K record, not just the finger image and/or minutiae records.

E.8.3 Member Function Documentation

E.8.3.1 `static AmputatedBandaged::Kind BiometricEvaluation::Finger::AN2KViewCapture::convertAmputatedBandaged (const char * ampcd) throw (Error::DataError)`
[static]

Convert string read from AN2K record into a [AmputatedBandaged](#) code.

Parameters

in	<i>ampcd</i>	Value for amputated bandaged code read from an AN2K record.
----	--------------	---

Exceptions

Error::DataError	Invalid value for ampcd.
----------------------------------	--------------------------

E.8.3.2 `static FingerSegmentPosition BiometricEvaluation::Finger::AN2KViewCapture::convertFingerSegmentPosition (const SUBFIELD * sf) throw (Error::DataError)`
[static]

Convert SUBFIELD read from AN2K record into a [FingerSegmentPosition](#) struct.

Parameters

in	<i>sf</i>	Subfield value for a single finger segment position read from an AN2K record.
----	-----------	---

Exceptions

Error::DataError	Invalid value within sf.
----------------------------------	--------------------------

E.8.3.3 `static FingerSegmentPosition BiometricEvaluation::Finger::AN2KViewCapture::convertAlternateFingerSegmentPosition (const SUBFIELD * sf) throw (Error::DataError)`
[static]

Convert SUBFIELD read from AN2K record into an AlternateFingerSegmentPosition struct.

Parameters

in	<i>sf</i>	Subfield value for a single alternate finger segment position read from an AN2K record.
----	-----------	---

Exceptions

<i>Error::DataError</i>	Invalid value with sf.
---	------------------------

E.8.3.4 QualityMetricSet BiometricEvaluation::Finger::AN2KViewCapture::extractNISTQuality (const FIELD * field) throw (Error::DataError)

Extract the NQM information from an AN2K FIELD.

Parameters

<i>field</i>	FIELD containing properly formatted NQM data
--------------	--

Returns

QualityMetricSet representation of field.

Exceptions

<i>Error::DataError</i>	Invalid format of field for NQM.
---	----------------------------------

E.8.3.5 QualityMetricSet BiometricEvaluation::Finger::AN2KViewCapture::getNISTQualityMetric () const

Obtain the NIST quality metric for all segmented finger images.

Returns

QualityMetricSet containing the NIST quality metric for all segmented finger images.

Vendor ID and Product Code are undefined, as they are unused by NQM.

E.8.3.6 QualityMetricSet BiometricEvaluation::Finger::AN2KViewCapture::getSegmentationQualityMetric () const

Obtain the segmentation quality metric for all segmented finger images.

Returns

QualityMetricSet containing the segmentation quality metric for all segmented finger images.

E.8.3.7 AmputatedBandaged::Kind BiometricEvaluation::Finger::AN2KViewCapture::getAmputated-Bandaged () const**Returns**

Optional amputated or bandaged code.

E.8.3.8 FingerSegmentPositionSet BiometricEvaluation::Finger::AN2KViewCapture::getFingerSegmentPositionSet () const

Returns

Optional set of rectangular finger segment positions for all finger segments.

E.8.3.9 FingerSegmentPositionSet BiometricEvaluation::Finger::AN2KViewCapture::getAlternateFingerSegmentPositionSet () const

Returns

Optional set of polygonal finger segment positions for all finger segments.

E.8.3.10 QualityMetricSet BiometricEvaluation::Finger::AN2KViewCapture::getFingerprintQualityMetric () const

Obtain metrics for fingerprint image quality score data for the image stored in this record.

Returns


Fingerprint quality metrics

E.9 BiometricEvaluation::Finger::AN2KViewFixedResolution Class Reference

A class to represent single finger view and derived information.

```
#include <be_finger_an2kview_fixedres.h>
```

Inheritance diagram for BiometricEvaluation::Finger::AN2KViewFixedResolution:



Public Member Functions

- [AN2KViewFixedResolution](#) (const std::string filename, const RecordType::Kind typeID, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError, Error::FileError)

Construct an AN2K finger view from a file.

- [AN2KViewFixedResolution](#) ([Memory::uint8Array](#) &buf, const [RecordType::Kind](#) typeId, const [uint32_t](#) recordNumber) throw ([Error::ParameterError](#), [Error::DataError](#))

Construct an AN2K finger view from a buffer.

Additional Inherited Members

E.9.1 Detailed Description

A class to represent single finger view and derived information.

A base [Finger::AN2KView](#) object represents an ANSI/NIST Type-3/4/5/6 record, and can return the image as well as the other information associated with that image, such as the minutiae from the corresponding Type-9 record.

For these types of records, the image resolution and scan resolution are identical. For compressed images, applications can compare the image resolution and size taken from the Type-3/4/5/6 record to that returned by the [Image](#) object directly.

E.9.2 Constructor & Destructor Documentation

- E.9.2.1** [BiometricEvaluation::Finger::AN2KViewFixedResolution::AN2KViewFixedResolution](#) (const [std::string](#) filename, const [RecordType::Kind](#) typeId, const [uint32_t](#) recordNumber) throw ([Error::ParameterError](#), [Error::DataError](#), [Error::FileError](#))

Construct an AN2K finger view from a file.

The file must contain the entire AN2K record, not just the finger image and/or minutiae records.

Parameters

in	filename	The name of the file containing the AN2K record.
in	typeID	The type of AN2K finger view: Type-3/Type-4/etc.
in	recordNumber	Which finger record to read as there may be multiple finger views of the same type within a single AN2K record.

Exceptions

Error::ParameterError	An invalid parameter was passed in.
Error::DataError	An error occurred when parsing the AN2K record.
Error::FileError	An error occurred when reading the file.

- E.9.2.2** [BiometricEvaluation::Finger::AN2KViewFixedResolution::AN2KViewFixedResolution](#) ([Memory::uint8Array](#) & buf, const [RecordType::Kind](#) typeId, const [uint32_t](#) recordNumber) throw ([Error::ParameterError](#), [Error::DataError](#))

Construct an AN2K finger view from a buffer.

The buffer must contain the entire AN2K record, not just the finger image and/or minutiae records.

Parameters


in	<i>buf</i>	The buffer containing the AN2K record.
in	<i>typeID</i>	The type of AN2K finger view: Type-3/Type-4/etc.
in	<i>recordNumber</i>	Which finger record to read as there may be multiple finger views of the same type within a single AN2K record.

Exceptions

<i>Error::ParameterError</i>	An invalid parameter was passed in.
<i>Error::DataError</i>	An error occurred when parsing the AN2K record.

E.10 BiometricEvaluation::Finger::AN2KViewLatent Class Reference

Inheritance diagram for BiometricEvaluation::Finger::AN2KViewLatent:

**Public Member Functions**

- [AN2KViewLatent](#) (const std::string &filename, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError, Error::FileError)
Construct an AN2K finger view from a file.
- [AN2KViewLatent](#) (Memory::uint8Array &buf, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError)
Construct an AN2K finger view using from a memory buffer.
- QualityMetricSet [getLatentQualityMetric](#) () const
Obtain metrics for latent image quality score data for the image stored in this record.
- PositionDescriptors [getSearchPositionDescriptors](#) () const
Return search position descriptors.

Additional Inherited Members

E.10.1 Constructor & Destructor Documentation

E.10.1.1 `BiometricEvaluation::Finger::AN2KViewLatent::AN2KViewLatent (const std::string & filename, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError, Error::FileError)`

Construct an AN2K finger view from a file.

The file must contain the entire AN2K record, not just the finger image and/or minutiae records.

E.10.1.2 `BiometricEvaluation::Finger::AN2KViewLatent::AN2KViewLatent (Memory::uint8Array & buf, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError)`

Construct an AN2K finger view using from a memory buffer.

The buffer must contain the entire AN2K record, not just the finger image and/or minutiae records.

E.10.2 Member Function Documentation

E.10.2.1 `QualityMetricSet BiometricEvaluation::Finger::AN2KViewLatent::getLatentQualityMetric () const`

Obtain metrics for latent image quality score data for the image stored in this record.

Returns


Latent quality metrics

E.11 BiometricEvaluation::Finger::AN2KViewVariableResolution Class Reference

A class to represent single finger view based on an ANSI/NIST record.

```
#include <be_finger_an2kview_varres.h>
```

Inheritance diagram for BiometricEvaluation::Finger::AN2KViewVariableResolution:



Classes

- struct [PrintPositionCoordinate](#)

Offsets to the bounding boxes for the EJI, full finger views, or EJI segments.

Public Types

- typedef struct
[PrintPositionCoordinate](#) **PrintPositionCoordinate**
- typedef std::vector
< [PrintPositionCoordinate](#) > **PrintPositionCoordinateSet**

Public Member Functions

- Finger::PositionSet [getPositions](#) () const
Obtain the set of finger positions.
- Finger::Impression::Kind [getImpressionType](#) () const
- PrintPositionCoordinateSet [getPrintPositionCoordinates](#) () const
Obtain print position coordinates.

Protected Member Functions

- [AN2KViewVariableResolution](#) (const std::string &filename, const RecordType::Kind typeID, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError, Error::FileError)
Construct an AN2K finger view from a file.
- [AN2KViewVariableResolution](#) (Memory::uint8Array &buf, const RecordType::Kind typeID, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError)
Construct an AN2K finger view from a buffer.
- PositionDescriptors [getPositionDescriptors](#) () const

Static Protected Member Functions

- static [PrintPositionCoordinate](#) [convertPrintPositionCoordinate](#) (SUBFIELD *subfield) throw (Error::DataError)
Convert a print position coordinate AN2K subfield to a [PrintPositionCoordinate](#) object.
- static PositionDescriptors [parsePositionDescriptors](#) (const RecordType::Kind typeID, const RECORD *record) throw (Error::DataError)
Parse position descriptors from a record.

Additional Inherited Members

E.11.1 Detailed Description

A class to represent single finger view based on an ANSI/NIST record.

The view represents a variable resolution (Type-13, 14) ANSI_NIST record.

E.11.2 Constructor & Destructor Documentation

E.11.2.1 BiometricEvaluation::Finger::AN2KViewVariableResolution::AN2KViewVariableResolution (const std::string & *filename*, const RecordType::Kind *typeID*, const uint32_t *recordNumber*) throw (Error::ParameterError, Error::DataError, Error::FileError) [protected]

Construct an AN2K finger view from a file.

The file must contain the entire AN2K record, not just the finger image and/or minutiae records.

Parameters

in	<i>filename</i>	The name of the file containing the AN2K record.
in	<i>typeID</i>	The type of AN2K finger view: Type-3/Type-4/etc.
in	<i>recordNumber</i>	Which finger record to read as there may be multiple finger views of the same type within a single AN2K record.

Exceptions

<i>Error::ParameterError</i>	An invalid parameter was passed in.
<i>Error::DataError</i>	An error occurred when parsing the AN2K record.
<i>Error::FileError</i>	An error occurred when reading the file.

E.11.2.2 BiometricEvaluation::Finger::AN2KViewVariableResolution::AN2KViewVariableResolution (Memory::uint8Array & *buf*, const RecordType::Kind *typeID*, const uint32_t *recordNumber*) throw (Error::ParameterError, Error::DataError) [protected]

Construct an AN2K finger view from a buffer.

The buffer must contain the entire AN2K record, not just the finger image and/or minutiae records.

Parameters

in	<i>buf</i>	The buffer containing the AN2K record.
in	<i>typeID</i>	The type of AN2K finger view: Type-3/Type-4/etc.
in	<i>recordNumber</i>	Which finger record to read as there may be multiple finger views of the same type within a single AN2K record.

Exceptions

<i>Error::ParameterError</i>	An invalid parameter was passed in.
<i>Error::DataError</i>	An error occurred when parsing the AN2K record.

E.11.3 Member Function Documentation

E.11.3.1 Finger::PositionSet BiometricEvaluation::Finger::AN2KViewVariableResolution::getPositions () const

Obtain the set of finger positions.

An AN2K finger image record contains a set of possible finger positions. This method returns that set as read from the image record. Any minutiae record (Type-9) associated with this image will have its own set of positions.

E.11.3.2 `Finger::Impression::Kind BiometricEvaluation::Finger::AN2KViewVariableResolution::getImpression-Type () const`

Returns

The finger impression code.

E.11.3.3 `PrintPositionCoordinateSet BiometricEvaluation::Finger::AN2KViewVariableResolution::getPrint-PositionCoordinates () const`

Obtain print position coordinates.

Returns

Set of all PrintPositionCoordinates

E.11.3.4 `static PrintPositionCoordinate BiometricEvaluation::Finger::AN2KViewVariableResolution::convert-PrintPositionCoordinate (SUBFIELD * subfield) throw (Error::DataError) [static], [protected]`

Convert a print position coordinate AN2K subfield to a [PrintPositionCoordinate](#) object.

Parameters

in	<i>subfield</i>	A print position coordinate AN2K subfield
----	-----------------	---

Returns

Object representation of field.

Exceptions

Error::DataError	Invalid data for a print position coordinate AN2K field.
----------------------------------	--

E.11.3.5 `PositionDescriptors BiometricEvaluation::Finger::AN2KViewVariableResolution::getPosition-Descriptors () const [protected]`

Returns

The set of position descriptors.

E.11.3.6 static PositionDescriptors BiometricEvaluation::Finger::AN2KViewVariableResolution::parsePositionDescriptors (const RecordType::Kind *typeID*, const RECORD * *record*) throw (Error::DataError) [static], [protected]

Parse position descriptors from a record.

Parameters

in	<i>typeID</i>	The logical record type.
in	<i>record</i>	The opened AN2K record.

Returns


Mapping of finger position codes to finger image code.

E.12 BiometricEvaluation::View::AN2KViewVariableResolution Class Reference

A class to represent single view based on an ANSI/NIST record.

```
#include <be_view_an2kview_varres.h>
```

Inheritance diagram for BiometricEvaluation::View::AN2KViewVariableResolution:



Classes

- struct [AN2KQualityMetric](#)
A structure to represent an AN2K quality metric.

Public Types

- typedef struct [AN2KQualityMetric](#) AN2KQualityMetric
- typedef std::vector
< [AN2KQualityMetric](#) > QualityMetricSet

Public Member Functions

- string [getSourceAgency](#) () const

- string `getCaptureDate ()` const
- string `getComment ()` const
Obtain the comment field.
- `Memory::uint8Array` `getUserDefinedField` (const uint16_t field) const throw (Error::ParameterError)
Obtain a user-defined field.

Static Public Member Functions

- static QualityMetricSet `extractQuality` (FIELD *field) throw (Error::DataError)
Read a Quality Metric Set from a variable resolution AN2K record.
- static `Memory::uint8Array` `parseUserDefinedField` (const RECORD *const record, int fieldID) throw (Error::ParameterError)
Read raw bytes from a user-defined AN2K field.

Protected Member Functions

- `AN2KViewVariableResolution` (const std::string &filename, const RecordType::Kind typeID, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError, Error::FileError)
Construct an AN2K finger view from a file.
- `AN2KViewVariableResolution` (`Memory::uint8Array` &buf, const RecordType::Kind typeID, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError)
Construct an AN2K finger view using from a memory buffer.
- QualityMetricSet `getQualityMetric ()` const
Obtain quality metrics for associated image record.

Additional Inherited Members

E.12.1 Detailed Description

A class to represent single view based on an ANSI/NIST record.

The view represents a variable resolution (Type-13/14/15) AN2K record.

E.12.2 Constructor & Destructor Documentation

- E.12.2.1** `BiometricEvaluation::View::AN2KViewVariableResolution::AN2KViewVariableResolution (const std::string & filename, const RecordType::Kind typeID, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError, Error::FileError) [protected]`

Construct an AN2K finger view from a file.

The file must contain the entire AN2K record, not just the finger image and/or minutiae records.

E.12.2.2 `BiometricEvaluation::View::AN2KViewVariableResolution::AN2KViewVariableResolution (Memory::uint8Array & buf, const RecordType::Kind typeId, const uint32_t recordNumber) throw (Error::ParameterError, Error::DataError) [protected]`

Construct an AN2K finger view using from a memory buffer.

The buffer must contain the entire AN2K record, not just the finger image and/or minutiae records.

E.12.3 Member Function Documentation

E.12.3.1 `static QualityMetricSet BiometricEvaluation::View::AN2KViewVariableResolution::extractQuality (FIELD * field) throw (Error::DataError) [static]`

Read a Quality Metric Set from a variable resolution AN2K record.

Parameters

<i>in</i>	<i>field</i>	A pointer to the field within the AN2K record.
-----------	--------------	--

Exceptions

<i>Error::DataError</i>	The data contains an invalid value.
---	-------------------------------------

E.12.3.2 `string BiometricEvaluation::View::AN2KViewVariableResolution::getSourceAgency () const`

Returns

The source agency.

E.12.3.3 `string BiometricEvaluation::View::AN2KViewVariableResolution::getCaptureDate () const`

Returns

The capture date.

E.12.3.4 `string BiometricEvaluation::View::AN2KViewVariableResolution::getComment () const`

Obtain the comment field.

The comment field is optional in an AN2K record.

Returns

The comment field, empty string if not present.

E.12.3.5 `Memory::uint8Array BiometricEvaluation::View::AN2KViewVariableResolution::getUserDefinedField (const uint16_t field) const` throw (`Error::ParameterError`)

Obtain a user-defined field.

Fields are retrieved on-demand and then cached.

Parameters

in	<i>field</i>	The field number to retrieve.
----	--------------	-------------------------------

Returns

Raw bytes read from the field.

Exceptions

<i>Error::ParameterError</i>	Invalid value for field.
--	--------------------------

E.12.3.6 `static Memory::uint8Array BiometricEvaluation::View::AN2KViewVariableResolution::parseUserDefinedField (const RECORD *const record, int fieldID)` throw (`Error::ParameterError`) [static]

Read raw bytes from a user-defined AN2K field.

Parameters

in	<i>record</i>	Pointer to a RECORD containing the user-defined field.
in	<i>fieldID</i>	The user-defined field number.

Returns

Raw bytes from field.

Exceptions

<i>Error::ParameterError</i>	Invalid value for fieldID.
--	----------------------------

E.12.3.7 `QualityMetricSet BiometricEvaluation::View::AN2KViewVariableResolution::getQualityMetric ()` `const` [protected]

Obtain quality metrics for associated image record.

Returns


Quality metrics

E.13 BiometricEvaluation::Finger::ANSI2004View Class Reference

A class to represent single finger view and derived information.

```
#include <be_finger_ansi2004view.h>
```

Inheritance diagram for BiometricEvaluation::Finger::ANSI2004View:



Public Member Functions

- [ANSI2004View](#) ()
Construct an empty ANSI finger view.
- [ANSI2004View](#) (const std::string &fmrFilename, const std::string &firFilename, const uint32_t view-Number) throw (Error::DataError, Error::FileError)
Construct an ANSI-2004 finger view from records contained in files.
- [ANSI2004View](#) (Memory::uint8Array &fmrBuffer, Memory::uint8Array &firBuffer, const uint32_t view-Number) throw (Error::DataError)
Construct an ANSI-2004 finger view from records contained in buffers.

Static Public Attributes

- static const uint16_t **CORE_TYPE_MASK** = 0xC0
- static const uint16_t **CORE_TYPE_SHIFT** = 6
- static const uint16_t **CORE_NUM_CORES_MASK** = 0x0F
- static const uint16_t **CORE_X_COORD_MASK** = 0x3FFF
- static const uint16_t **CORE_Y_COORD_MASK** = 0x3FFF
- static const uint16_t **DELTA_TYPE_MASK** = 0xC0
- static const uint16_t **DELTA_TYPE_SHIFT** = 6
- static const uint16_t **DELTA_NUM_DELTAS_MASK** = 0x3F
- static const uint16_t **DELTA_X_COORD_MASK** = 0x3FFF
- static const uint16_t **DELTA_Y_COORD_MASK** = 0x3FFF

Protected Member Functions

- virtual void [readCoreDeltaData](#) (Memory::IndexedBuffer &buf, uint32_t dataLength, Feature::Core-PointSet &cores, Feature::DeltaPointSet &deltas) throw (Error::DataError)
Read the core points data.

Additional Inherited Members

E.13.1 Detailed Description

A class to represent single finger view and derived information.

A [Finger::ANSI2004View](#) object represents a finger view from a INCITS/ANSI-2004 [Finger](#) Minutiae Record.

E.13.2 Constructor & Destructor Documentation

E.13.2.1 `BiometricEvaluation::Finger::ANSI2004View::ANSI2004View (const std::string & fmrFilename, const std::string & firFilename, const uint32_t viewNumber) throw (Error::DataError, Error::FileError)`

Construct an ANSI-2004 finger view from records contained in files.

A view can be constructed from a single record, with information missing as appropriate. For example, if a view is constructed with just the minutiae record, no image would be part of the view. However, the image size etc. would be present because that information is also present in the minutiae record.

Parameters

in	<i>fmrFilename</i>	The name of the file containing the complete finger minutiae record.
in	<i>firFilename</i>	The name of the file containing the complete finger image record.
in	<i>viewNumber</i>	The finger view number to use.

E.13.2.2 `BiometricEvaluation::Finger::ANSI2004View::ANSI2004View (Memory::uint8Array & fmrBuffer, Memory::uint8Array & firBuffer, const uint32_t viewNumber) throw (Error::DataError)`

Construct an ANSI-2004 finger view from records contained in buffers.

A view can be constructed from a single record, with information missing as appropriate. For example, if a view is constructed with just the minutiae record, no image would be part of the view. However, the image size etc. would be present because that information is also present in the minutiae record.

Parameters

in	<i>fmrBuffer</i>	The buffer containing the complete finger minutiae record.
in	<i>firBuffer</i>	The buffer containing the complete finger image record.
in	<i>viewNumber</i>	The finger view number to use.

E.13.3 Member Function Documentation

E.13.3.1 `virtual void BiometricEvaluation::Finger::ANSI2004View::readCoreDeltaData (Memory::IndexedBuffer & buf, uint32_t dataLength, Feature::CorePointSet & cores, Feature::DeltaPointSet & deltas) throw (Error::DataError) [protected], [virtual]`

Read the core points data.

This method must be overridden by derived classes to read data in a specific record format.

Parameters

in, out	<i>buf</i>	The indexed buffer containing the record data. On function exit, the buffer index will be set to the location after the last core point data item.
out	<i>cores</i>	The set of core data items.
out	<i>deltas</i>	The set of delta data items.
in	<i>dataLength</i>	The length of the entire ridge count data block.


Implements [BiometricEvaluation::Finger::INCITSView](#).

E.14 BiometricEvaluation::Finger::ANSI2007View Class Reference

A class to represent single finger view and derived information.

```
#include <be_finger_ansi2007view.h>
```

Inheritance diagram for BiometricEvaluation::Finger::ANSI2007View:



Public Member Functions

- [ANSI2007View](#) (const std::string &fmrFilename, const std::string &firFilename, const uint32_t view-Number) throw (Error::DataError, Error::FileError)
Construct an ANSI-2007 finger view from records contained in files.
- [ANSI2007View](#) ([Memory::uint8Array](#) &fmrBuffer, [Memory::uint8Array](#) &firBuffer, const uint32_t view-Number) throw (Error::DataError)
Construct an ANSI-2007 finger view from records contained in buffers.

Static Public Attributes

- static const string **FMR_SPEC_VERSION**
- static const uint16_t **CORE_TYPE_MASK** = 0xC0
- static const uint16_t **CORE_TYPE_SHIFT** = 6
- static const uint16_t **CORE_NUM_CORES_MASK** = 0x0F
- static const uint16_t **CORE_X_COORD_MASK** = 0x3FFF
- static const uint16_t **CORE_Y_COORD_MASK** = 0x3FFF
- static const uint16_t **DELTA_TYPE_MASK** = 0xC0
- static const uint16_t **DELTA_TYPE_SHIFT** = 6
- static const uint16_t **DELTA_NUM_DELTAS_MASK** = 0x0F
- static const uint16_t **DELTA_X_COORD_MASK** = 0x3FFF
- static const uint16_t **DELTA_Y_COORD_MASK** = 0x3FFF

Protected Member Functions

- void **readFMRHeader** ([Memory::IndexedBuffer](#) &buf, const uint32_t formatStandard) throw (Error::ParameterError, Error::DataError)
- void **readFVMR** ([Memory::IndexedBuffer](#) &buf) throw (Error::DataError)
- virtual void **readCoreDeltaData** ([Memory::IndexedBuffer](#) &buf, uint32_t dataLength, Feature::CorePointSet &cores, Feature::DeltaPointSet &deltas) throw (Error::DataError)

Read the core points data.

Additional Inherited Members

E.14.1 Detailed Description

A class to represent single finger view and derived information.

A [Finger::ANSI2007View](#) object represents a finger view from a INCITS/ANSI-2007 [Finger](#) Minutiae Record.

E.14.2 Constructor & Destructor Documentation

E.14.2.1 BiometricEvaluation::Finger::ANSI2007View::ANSI2007View (const std::string & fmrFilename, const std::string & firFilename, const uint32_t viewNumber) throw (Error::DataError, Error::FileError)

Construct an ANSI-2007 finger view from records contained in files.

A view can be constructed from a single record, with information missing as appropriate. For example, if a view is constructed with just the minutiae record, no image would be part of the view. However, the image size etc. would be present because that information is also present in the minutiae record.

Parameters

in	<i>fmrFilename</i>	The name of the file containing the complete finger minutiae record.
in	<i>firFilename</i>	The name of the file containing the complete finger image record.
in	<i>viewNumber</i>	The finger view number to use.

Exceptions

Error::DataError	Invalid record format.
----------------------------------	------------------------

E.14.2.2 BiometricEvaluation::Finger::ANSI2007View::ANSI2007View (Memory::uint8Array & fmrBuffer, Memory::uint8Array & firBuffer, const uint32_t viewNumber) throw (Error::DataError)

Construct an ANSI-2007 finger view from records contained in buffers.

A view can be constructed from a single record, with information missing as appropriate. For example, if a view is constructed with just the minutiae record, no image would be part of the view. However, the image size etc. would be present because that information is also present in the minutiae record.

Parameters

in	<i>fmrBuffer</i>	The buffer containing the complete finger minutiae record.
in	<i>firBuffer</i>	The buffer containing the complete finger image record.
in	<i>viewNumber</i>	The finger view number to use.

Exceptions

Error::DataError	Invalid record format.
----------------------------------	------------------------

E.14.3 Member Function Documentation

E.14.3.1 virtual void BiometricEvaluation::Finger::ANSI2007View::readCoreDeltaData (Memory::IndexedBuffer & *buf*, uint32_t *dataLength*, Feature::CorePointSet & *cores*, Feature::DeltaPointSet & *deltas*) throw (Error::DataError) [protected], [virtual]

Read the core points data.

This method must be overridden by derived classes to read data in a specific record format.

Parameters

in, out	<i>buf</i>	The indexed buffer containing the record data. On function exit, the buffer index will be set to the location after the last core point data item.
out	<i>cores</i>	The set of core data items.
out	<i>deltas</i>	The set of delta data items.
in	<i>dataLength</i>	The length of the entire ridge count data block.


Implements [BiometricEvaluation::Finger::INCITSView](#).

E.15 BiometricEvaluation::IO::ArchiveRecordStore Class Reference

This class implements the [IO::RecordStore](#) interface by storing data items in single file, with an associated manifest file.

```
#include <be_io_archiverecstore.h>
```

Inheritance diagram for BiometricEvaluation::IO::ArchiveRecordStore:

**Public Member Functions**

- [ArchiveRecordStore](#) (const string &name, const string &description, const string &parentDir) throw (-Error::ObjectExists, Error::StrategyError)

- [ArchiveRecordStore](#) (const string &name, const string &parentDir, uint8_t mode=IO::READWRITE) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- [~ArchiveRecordStore](#) ()
- uint64_t [getSpaceUsed](#) () const throw (Error::StrategyError)
Obtain real storage utilization.
- void [sync](#) () const throw (Error::StrategyError)
- void [insert](#) (const string &key, const void *const data, const uint64_t size) throw (Error::ObjectExists, Error::StrategyError)
- void [remove](#) (const string &key) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [read](#) (const string &key, void *const data) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void [replace](#) (const string &key, const void *const data, const uint64_t size) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [length](#) (const string &key) const throw (Error::ObjectDoesNotExist)
- void [flush](#) (const string &key) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [sequence](#) (string &key, void *const data=NULL, int cursor=[BE_RECSTORE_SEQ_NEXT](#)) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Sequence through a [RecordStore](#), returning the key/data pairs.
- void [setCursorAtKey](#) (string &key) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void [changeName](#) (const string &name) throw (Error::ObjectExists, Error::StrategyError)
- bool [needsVacuum](#) ()
- string [getArchiveName](#) () const
- string [getManifestName](#) () const

Static Public Member Functions

- static bool [needsVacuum](#) (const string &name, const string &parentDir) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- static void [vacuum](#) (const string &name, const string &parentDir) throw (Error::ObjectDoesNotExist, Error::StrategyError)

Static Public Attributes

- static const long [OFFSET_RECORD_REMOVED](#) = -1

Additional Inherited Members

E.15.1 Detailed Description

This class implements the [IO::RecordStore](#) interface by storing data items in single file, with an associated manifest file.

Archives consist of binary records written back to back of each other. To pull information out of an archive, a manifest file is written in the same directory as the archive file.

Each record is assigned a string key, which will be required for retrieving the data. As the data is written, a plain text entry is entered into the manifest in the format:

key offset size

where offset is the offset into the archive file key's data chunk resides and size is the length of key's data chunk.

By default, information is not removed when updated in the archive, rather the old information is ignored. Therefore, it is possible to have multiple entries in the manifest for one key. The last entry for the key is considered accurate. If the last offset for a key is ARCHIVE_RECORD_REMOVED, the information is treated as unavailable.

E.15.2 Constructor & Destructor Documentation

E.15.2.1 BiometricEvaluation::IO::ArchiveRecordStore::ArchiveRecordStore (const string & *name*, const string & *description*, const string & *parentDir*) throw (Error::ObjectExists, Error::StrategyError)

Create a new [ArchiveRecordStore](#), read/write mode.

Parameters

in	<i>name</i>	The name of the store.
in	<i>description</i>	The store's description.
in	<i>parentDir</i>	The directory where the store is to be created.

Exceptions

Error::ObjectExists	The store already exists.
Error::StrategyError	An error occurred when accessing the underlying file system.

E.15.2.2 BiometricEvaluation::IO::ArchiveRecordStore::ArchiveRecordStore (const string & *name*, const string & *parentDir*, uint8_t *mode* = IO::READWRITE) throw (Error::ObjectDoesNotExist, Error::StrategyError)

Open an existing [ArchiveRecordStore](#).

Parameters

in	<i>name</i>	The name of the store.
in	<i>parentDir</i>	The directory where the store is to be created.
in	<i>mode</i>	Open mode, read-only or read-write.

Exceptions

Error::ObjectDoesNotExist	The store does not exist.
Error::StrategyError	An error occurred when accessing the underlying file system.

E.15.2.3 BiometricEvaluation::IO::ArchiveRecordStore::~~ArchiveRecordStore ()

Destructor.

E.15.3 Member Function Documentation

E.15.3.1 `uint64_t BiometricEvaluation::IO::ArchiveRecordStore::getSpaceUsed () const throw (Error::StrategyError) [virtual]`

Obtain real storage utilization.

The amount of disk space used, for example. This is the actual space allocated by the underlying storage mechanism, in bytes.

Returns

The amount of backing storage used by the [RecordStore](#).

Exceptions

Error::StrategyError	An error occurred when using the underlying storage system.
--------------------------------------	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.15.3.2 `void BiometricEvaluation::IO::ArchiveRecordStore::sync () const throw (Error::StrategyError) [virtual]`

Synchronize the entire record store to persistent storage.

Exceptions

Error::StrategyError	An error occurred when using the underlying storage system.
--------------------------------------	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.15.3.3 `void BiometricEvaluation::IO::ArchiveRecordStore::insert (const string & key, const void *const data, const uint64_t size) throw (Error::ObjectExists, Error::StrategyError) [virtual]`

Insert a record into the store.

Parameters

in	<i>key</i>	The key of the record to be inserted.
in	<i>data</i>	The data for the record.
in	<i>size</i>	The size, in bytes, of the record.

Exceptions

Error::ObjectExists	A record with the given key is already present.
Error::StrategyError	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.15.3.4 void BiometricEvaluation::IO::ArchiveRecordStore::remove (const string & *key*) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Remove a record from the store.

Parameters

in	<i>key</i>	The key of the record to be removed.
----	------------	--------------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.15.3.5 uint64_t BiometricEvaluation::IO::ArchiveRecordStore::read (const string & *key*, void *const *data*) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Read a complete record from a store. Applications are responsible for allocating storage for the record's data.

Parameters

in	<i>key</i>	The key of the record to be read.
in	<i>data</i>	Pointer to where the data is to be written.

Returns

The size of the record.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.15.3.6 void BiometricEvaluation::IO::ArchiveRecordStore::replace (const string & *key*, const void *const *data*, const uint64_t *size*) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Replace a complete record in a store.

Parameters

in	<i>key</i>	The key of the record to be replaced.
in	<i>data</i>	The data for the record.
in	<i>size</i>	The size of data.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.15.3.7 `uint64_t BiometricEvaluation::IO::ArchiveRecordStore::length (const string & key) const throw (Error::ObjectDoesNotExist) [virtual]`

Return the length of a record.

Parameters

<code>in</code>	<i>key</i>	The key of the record.
-----------------	------------	------------------------

Returns

The record length.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.15.3.8 `void BiometricEvaluation::IO::ArchiveRecordStore::flush (const string & key) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Commit the record's data to storage.

Parameters

<code>in</code>	<i>key</i>	The key of the record to be flushed.
-----------------	------------	--------------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.15.3.9 `uint64_t BiometricEvaluation::IO::ArchiveRecordStore::sequence (string & key, void *const data = NULL, int cursor = BE_RECSTORE_SEQ_NEXT) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Sequence through a [RecordStore](#), returning the key/data pairs.

Sequencing means to start at some point in the store and return the record, then repeatedly calling the sequencor to return the next record. The starting point is typically the first record, and is set to that when the [RecordStore](#) object is created. The starting point can be reset by calling this method with the cursor parameter set to BE_RECSTORE_SEQ_START.

Parameters

out	key	The key of the currently sequenced record.
in	data	Pointer to where the data is to be written. Applications can set data to NULL to indicate only the key is wanted.
in	cursor	The location within the sequence of the key/data pair to return.

Returns

The length of the record currently in sequence.

Exceptions

Error::ObjectDoesNotExist	A record for the key does not exist.
Error::StrategyError	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.15.3.10 `void BiometricEvaluation::IO::ArchiveRecordStore::setCursorAtKey (string & key) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Set the sequence cursor to an arbitrary position within the [RecordStore](#), starting at key. Key will be the first record returned from the next call to [sequence\(\)](#).

Parameters

in	key	The key of the record which will be returned by the first subsequent call to sequence() .
----	-----	---

Exceptions

Error::ObjectDoesNotExist	A record for the key does not exist.
Error::StrategyError	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.15.3.11 void BiometricEvaluation::IO::ArchiveRecordStore::changeName (const string & *name*) throw (Error::ObjectExists, Error::StrategyError) [virtual]

Change the name of the [RecordStore](#).

Parameters

in	<i>name</i>	The new name for the RecordStore .
----	-------------	--

Exceptions

Error::StrategyError	An error occurred when using the underlying storage system, or the name is malformed.
--------------------------------------	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.15.3.12 bool BiometricEvaluation::IO::ArchiveRecordStore::needsVacuum ()

See if the [ArchiveRecordStore](#) would benefit from calling [vacuum\(\)](#) to remove deleted entries, since [vacuum\(\)](#) is an expensive operation.

Returns

true if [vacuum\(\)](#) would be beneficial false otherwise

E.15.3.13 static bool BiometricEvaluation::IO::ArchiveRecordStore::needsVacuum (const string & *name*, const string & *parentDir*) throw (Error::ObjectDoesNotExist, Error::StrategyError) [static]

See if the [ArchiveRecordStore](#) would benefit from calling [vacuum\(\)](#) to remove deleted entries, since [vacuum\(\)](#) is an expensive operation.

Parameters

in	<i>name</i>	The name of the existing RecordStore .
in	<i>parentDir</i>	Where, in the filesystem, the store is rooted.

Exceptions

Error::ObjectDoesNotExist	A record with the given key does not exist.
Error::StrategyError	An error occurred when using the underlying storage system.

Returns

true if [vacuum\(\)](#) would be beneficial false otherwise

E.15.3.14 `static void BiometricEvaluation::IO::ArchiveRecordStore::vacuum (const string & name, const string & parentDir) throw (Error::ObjectDoesNotExist, Error::StrategyError) [static]`

Remove deleted entries from the manifest and archive files to save space on disk.

Parameters

<code>in</code>	<code><i>name</i></code>	The name of the existing RecordStore .
<code>in</code>	<code><i>parentDir</i></code>	Where, in the file system, the store is rooted.

Exceptions

Error::ObjectDoesNotExist	A record with the given key does not exist.
Error::StrategyError	An error occurred when using the underlying storage system.

Note

This is an expensive operation.

E.15.3.15 `string BiometricEvaluation::IO::ArchiveRecordStore::getArchiveName () const`

Obtain the name of the file storing the data for this store.

Returns

Path to archive file.

E.15.3.16 `string BiometricEvaluation::IO::ArchiveRecordStore::getManifestName () const`

Obtain the name of the file storing the manifest data data for this store.

Returns

Path to manifest file.

E.15.4 Member Data Documentation

E.15.4.1 `const long BiometricEvaluation::IO::ArchiveRecordStore::OFFSET_RECORD_REMOVED = -1 [static]`

Offset placeholder indicating a removed record

E.16 BiometricEvaluation::Memory::AutoArray< T > Class Template Reference

A C-style array wrapped in the facade of a C++ STL container.

```
#include <be_memory_autoarray.h>
```

Public Types

- typedef T [value_type](#)
- typedef size_t [size_type](#)
- typedef T * [iterator](#)
- typedef const T * [const_iterator](#)
- typedef T & [reference](#)
- typedef const T & [const_reference](#)

Public Member Functions

- [operator T * \(\)](#)
Convert [AutoArray](#) to T array.
- [operator const T * \(\) const](#)
Convert [AutoArray](#) to const T array.
- [reference operator\[\] \(ptrdiff_t index\)](#)
Subscripting operator overload with unchecked access.
- [const_reference operator\[\] \(ptrdiff_t index\) const](#)
Const subscripting operator overload with unchecked access.
- [reference at \(ptrdiff_t index\) throw \(out_of_range\)](#)
Subscript into the [AutoArray](#) with checked access.
- [const_reference at \(ptrdiff_t index\) const throw \(out_of_range\)](#)
Subscript into the [AutoArray](#) with checked access.
- [iterator begin \(\)](#)
Obtain an iterator to the beginning of the [AutoArray](#).
- [const_iterator begin \(\) const](#)
Obtain an iterator to the beginning of the [AutoArray](#).
- [iterator end \(\)](#)
Obtain an iterator to the end of the [AutoArray](#).
- [const_iterator end \(\) const](#)
Obtain an iterator to the end of the [AutoArray](#).
- [size_type size \(\) const](#)
Obtain the number of accessible elements.
- void [resize \(size_type new_size, bool free=false\) throw \(Error::MemoryError\)](#)
Change the number of accessible elements.
- void [copy \(const_iterator buffer\)](#)
Deep-copy the contents of a buffer into this [AutoArray](#).
- void [copy \(const_iterator buffer, size_type size\)](#)
Deep-copy the contents of a buffer into this [AutoArray](#).
- void [swap \(AutoArray &first, AutoArray &second\)](#)
Swap two AutoArrays.
- void [swap \(AutoArray &other\)](#)
Swap this [AutoArray](#) with other.
- [AutoArray \(size_type size=0\) throw \(Error::MemoryError\)](#)
Construct an [AutoArray](#).

- `AutoArray` (const `AutoArray` &`copy`) throw (Error::MemoryError)
Construct an `AutoArray`.
- `AutoArray` & `operator=` (`AutoArray` other) throw (Error::MemoryError)
Assignment operator overload performing a deep copy.
- `~AutoArray` ()

E.16.1 Detailed Description

```
template<class T>class BiometricEvaluation::Memory::AutoArray< T >
```

A C-style array wrapped in the facade of a C++ STL container.

E.16.2 Member Typedef Documentation

E.16.2.1 `template<class T> typedef T BiometricEvaluation::Memory::AutoArray< T >::value_type`

Type of element

E.16.2.2 `template<class T> typedef size_t BiometricEvaluation::Memory::AutoArray< T >::size_type`

Type of subscripts, counts, etc.

E.16.2.3 `template<class T> typedef T* BiometricEvaluation::Memory::AutoArray< T >::iterator`

Iterator of element

E.16.2.4 `template<class T> typedef const T* BiometricEvaluation::Memory::AutoArray< T >::const_iterator`

Const iterator of element

E.16.2.5 `template<class T> typedef T& BiometricEvaluation::Memory::AutoArray< T >::reference`

Reference to element

E.16.2.6 `template<class T> typedef const T& BiometricEvaluation::Memory::AutoArray< T >::const_reference`

Const reference element

E.16.3 Constructor & Destructor Documentation

E.16.3.1 `template<class T> BiometricEvaluation::Memory::AutoArray< T >::AutoArray (size_type size = 0) throw (Error::MemoryError)`

Construct an [AutoArray](#).

Parameters

<i>in</i>	<i>size</i>	The number of elements this AutoArray should initially hold.
-----------	-------------	--

Exceptions

Error::MemoryError	Could not allocate new memory.
------------------------------------	--------------------------------

E.16.3.2 `template<class T> BiometricEvaluation::Memory::AutoArray< T >::AutoArray (const AutoArray< T > & copy) throw (Error::MemoryError)`

Construct an [AutoArray](#).

Parameters

<i>in</i>	<i>copy</i>	An AutoArray whose contents will be deep copied into the new AutoArray .
-----------	-------------	--

Exceptions

Error::MemoryError	Could not allocate new memory.
------------------------------------	--------------------------------

E.16.3.3 `template<class T> BiometricEvaluation::Memory::AutoArray< T >::~~AutoArray ()`

Destructor

E.16.4 Member Function Documentation

E.16.4.1 `template<class T> BiometricEvaluation::Memory::AutoArray< T >::operator T * ()`

Convert [AutoArray](#) to T array.

Returns

Pointer to the beginning of the underlying array storage.

E.16.4.2 `template<class T> BiometricEvaluation::Memory::AutoArray< T >::operator const T * () const`

Convert [AutoArray](#) to const T array.

Returns

Const pointer to the beginning of the underlying array storage.

E.16.4.3 `template<class T > BiometricEvaluation::Memory::AutoArray< T >::reference
BiometricEvaluation::Memory::AutoArray< T >::operator[] (ptrdiff_t index)`

Subscripting operator overload with unchecked access.

Parameters

<code>in</code>	<code>index</code>	Subscript into underlying storage.
-----------------	--------------------	------------------------------------

Returns

Reference to the element at the specified index.

E.16.4.4 `template<class T > BiometricEvaluation::Memory::AutoArray< T >::const_reference
BiometricEvaluation::Memory::AutoArray< T >::operator[] (ptrdiff_t index) const`

Const subscripting operator overload with unchecked access.

Parameters

<code>in</code>	<code>index</code>	Subscript into underlying storage.
-----------------	--------------------	------------------------------------

Returns

Const reference to the element at the specified index.

E.16.4.5 `template<class T > BiometricEvaluation::Memory::AutoArray< T >::reference
BiometricEvaluation::Memory::AutoArray< T >::at (ptrdiff_t index) throw (out_of_range)`

Subscript into the [AutoArray](#) with checked access.

Parameters

<code>in</code>	<code>index</code>	Subscript into underlying storage.
-----------------	--------------------	------------------------------------

Returns

Reference to the element at the specified index.

Exceptions

<code>out_of_range</code>	Specified index is outside the bounds of this AutoArray .
---------------------------	---

E.16.4.6 `template<class T> BiometricEvaluation::Memory::AutoArray< T >::const_reference
BiometricEvaluation::Memory::AutoArray< T >::at (ptrdiff_t index) const` throw (out_of_range)

Subscript into the [AutoArray](#) with checked access.

Parameters

<i>index</i>	Subscript into underlying storage.
--------------	------------------------------------

Returns

Const reference to the element at the specified index.

Exceptions

<i>out_of_range</i>	Specified index is outside the bounds of this AutoArray .
---------------------	---

E.16.4.7 `template<class T> BiometricEvaluation::Memory::AutoArray< T >::iterator
BiometricEvaluation::Memory::AutoArray< T >::begin ()`

Obtain an iterator to the beginning of the [AutoArray](#).

Returns

Iterator positioned at the first element of the [AutoArray](#).

E.16.4.8 `template<class T> BiometricEvaluation::Memory::AutoArray< T >::const_iterator
BiometricEvaluation::Memory::AutoArray< T >::begin () const`

Obtain an iterator to the beginning of the [AutoArray](#).

Returns

Const iterator positioned at the first element of the [AutoArray](#).

E.16.4.9 `template<class T> BiometricEvaluation::Memory::AutoArray< T >::iterator
BiometricEvaluation::Memory::AutoArray< T >::end ()`

Obtain an iterator to the end of the [AutoArray](#).

Returns

Iterator positioned at the one-past-last element of the [AutoArray](#).

E.16.4.10 `template<class T > BiometricEvaluation::Memory::AutoArray< T >::const_iterator
BiometricEvaluation::Memory::AutoArray< T >::end () const`

Obtain an iterator to the end of the [AutoArray](#).

Returns

Iterator positioned at the one-past-last element of the [AutoArray](#).

E.16.4.11 `template<class T > BiometricEvaluation::Memory::AutoArray< T >::size_type
BiometricEvaluation::Memory::AutoArray< T >::size () const`

Obtain the number of accessible elements.

Returns

Number of accessible elements.

Note

If [resize\(\)](#) has been called, the value returned from [size\(\)](#) may be smaller than the actual allocated size of the underlying storage.

E.16.4.12 `template<class T > void BiometricEvaluation::Memory::AutoArray< T >::resize (size_type
new_size, bool free = false) throw (Error::MemoryError)`

Change the number of accessible elements.

Parameters

in	<i>new_size</i>	The number of elements the AutoArray should have allocated.
in	<i>free</i>	Whether or not excess memory should be freed if the new size is smaller than the current size.

Exceptions

Error::MemoryError	Problem allocating memory.
------------------------------------	----------------------------

E.16.4.13 `template<class T > void BiometricEvaluation::Memory::AutoArray< T >::copy (const_iterator buffer)`

Deep-copy the contents of a buffer into this [AutoArray](#).

Parameters

in	<i>buffer</i>	An allocated buffer whose contents will be deep-copied into this object. Only size() bytes will be copied.
----	---------------	--

Warning

If buffer is smaller in size than the current size of the [AutoArray](#), you MUST call `copy(const_iterator, size_type)`. This method must only be used when buffer is larger than or equal to the size of the [AutoArray](#).

E.16.4.14 `template<class T > void BiometricEvaluation::Memory::AutoArray< T >::copy (const_iterator buffer, size_type size)`

Deep-copy the contents of a buffer into this [AutoArray](#).

Parameters

<i>in</i>	<i>buffer</i>	An allocated buffer whose contents will be deep-copied into this object.
<i>in</i>	<i>size</i>	The number of bytes from buffer that will be deep-copied.

Warning

size must be less than or equal to the size of buffer.

E.16.4.15 `template<class T > void BiometricEvaluation::Memory::AutoArray< T >::swap (AutoArray< T > & first, AutoArray< T > & second)`

Swap two AutoArrays.

Parameters

<i>in/out</i>	first AutoArray that will become second.
<i>in/out</i>	second AutoArray that will become first.

E.16.4.16 `template<class T > void BiometricEvaluation::Memory::AutoArray< T >::swap (AutoArray< T > & other)`

Swap this [AutoArray](#) with other.

Parameters

<i>in/out</i>	other AutoArray that will become this.
---------------	--

Note

Mainly for use when called from `std::swap` total template specialization.

E.16.4.17 `template<class T > BiometricEvaluation::Memory::AutoArray< T > & BiometricEvaluation::Memory::AutoArray< T >::operator= (AutoArray< T > other) throw (Error::MemoryError)`

Assignment operator overload performing a deep copy.

Parameters

in	other	AutoArray to be copied.
----	-------	-------------------------

Returns

Reference to a new AutoArray object, the lvalue AutoArray.

Exceptions

Error::MemoryError	Could not allocate new memory.
--------------------	--------------------------------

Note

The signature for this operator overload is different than a traditional pass by constant reference to make use of the "copy-and-swap" idiom.

E.17 BiometricEvaluation::Memory::AutoBuffer< T > Class Template Reference

Public Types

- typedef T [value_type](#)
Manage a memory buffer.
- typedef T & **reference**
- typedef const T & **const_reference**

Public Member Functions

- **operator T * ()**
- T * **operator-> ()**
- [AutoBuffer](#) & **operator=** (const [AutoBuffer](#) &other)
- **AutoBuffer** (T *data)
- **AutoBuffer** (int(*ctor)(T **), void(*dtor)(T *), int(*copyCtor)(T **, T *)=NULL)
- **AutoBuffer** (const [AutoBuffer](#) ©)

E.17.1 Member Typedef Documentation

E.17.1.1 template<class T> typedef T BiometricEvaluation::Memory::AutoBuffer< T >::value_type

Manage a memory buffer.

It's easier to think of [AutoBuffer](#) as a wrapper for a pointer rather than the object it truly is. Therefore, you can interact with the [AutoBuffer](#) object exactly how you would a traditional pointer, without worrying about memory management.

Say you wanted to use an ANSI_NIST* but didn't want to be responsible for allocating or freeing the memory. Create an [AutoBuffer](#) object like:

```
AutoBuffer<ANSI_NIST> obj = AutoBuffer(allocator_fn,
    deallocator_fn[, copy_constructor]);
```

Notice the [AutoBuffer](#) is for `ANSI_NIST` and not `ANSI_NIST*`, since [AutoBuffer](#) will handle the pointer for you. You can pass the [AutoBuffer<ANSI_NIST>](#) object to any function that takes an `ANSI_NIST*`. For example, it's perfectly valid to pass our 'obj' object above to:

```
write_fmttext(FILE *, ANSI_NIST *)
```

If you want to access a member from 'obj', you can use the dereference operator just like you would on a regular `ANSI_NIST*`:

```
int size = obj->num_bytes;
```

E.18 BiometricEvaluation::DataInterchange::AN2KRecord::CharacterSet Struct Reference

Public Member Functions

- [CharacterSet](#) (uint16_t identifier=0, string commonName="", string version="")
Create a new [CharacterSet](#) struct.

Public Attributes

- uint16_t identifier
- string commonName
- string version

E.18.1 Constructor & Destructor Documentation

E.18.1.1 [BiometricEvaluation::DataInterchange::AN2KRecord::CharacterSet::CharacterSet](#) (uint16_t identifier = 0, string commonName = "", string version = "") [inline]

Create a new [CharacterSet](#) struct.

Parameters

<i>identifier</i>	Numeric identifier of the character set.
<i>commonName</i>	Common name of the character set.
<i>version</i>	Optional version number of the character set.

E.18.2 Member Data Documentation

E.18.2.1 [uint16_t BiometricEvaluation::DataInterchange::AN2KRecord::CharacterSet::identifier](#)

Identifier (000-999)

E.18.2.2 string BiometricEvaluation::DataInterchange::AN2KRecord::CharacterSet::commonName

Common name of the character set

E.18.2.3 string BiometricEvaluation::DataInterchange::AN2KRecord::CharacterSet::version


Optional version of the character set

E.19 BiometricEvaluation::IO::CompressedRecordStore Class Reference

Sibling-implemented [RecordStore](#) with Compression.

```
#include <be_io_compressedrecstore.h>
```

Inheritance diagram for BiometricEvaluation::IO::CompressedRecordStore:



Public Member Functions

- [CompressedRecordStore](#) (const string &name, const string &description, const string &recordStoreType, const string &parentDir, const string &compressorType) throw (Error::ObjectExists, Error::StrategyError)
- [CompressedRecordStore](#) (const string &name, const string &description, const string &recordStoreType, const string &parentDir, const [Compressor::Kind](#) &compressorType) throw (Error::ObjectExists, Error::StrategyError)
- [CompressedRecordStore](#) (const string &name, const string &parentDir, uint8_t mode=IO::READWRITE) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [getSpaceUsed](#) () const throw (Error::StrategyError)

Obtain real storage utilization.

- void [sync](#) () const throw (Error::StrategyError)
- void [insert](#) (const string &key, const void *const data, const uint64_t size) throw (Error::ObjectExists, Error::StrategyError)
- void [remove](#) (const string &key) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [read](#) (const string &key, void *const data) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void [replace](#) (const string &key, const void *const data, const uint64_t size) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [length](#) (const string &key) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void [flush](#) (const string &key) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [sequence](#) (string &key, void *const data=NULL, int cursor=[BE_RECSTORE_SEQ_NEXT](#)) throw (Error::ObjectDoesNotExist, Error::StrategyError)

Sequence through a [RecordStore](#), returning the key/data pairs.

- void [setCursorAtKey](#) (string &key) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void [changeName](#) (const string &name) throw (Error::ObjectExists, Error::StrategyError)

Static Public Attributes

- static const string [BACKING_STORE](#)
- static const string [COMPRESSOR_TYPE_KEY](#)

Additional Inherited Members

E.19.1 Detailed Description

Sibling-implemented [RecordStore](#) with Compression.

E.19.2 Constructor & Destructor Documentation

E.19.2.1 [BiometricEvaluation::IO::CompressedRecordStore::CompressedRecordStore](#) (const string & *name*, const string & *description*, const string & *recordStoreType*, const string & *parentDir*, const string & *compressorType*) throw (Error::ObjectExists, Error::StrategyError)

Create a new [CompressedRecordStore](#), read/write mode.

Parameters

in	<i>name</i>	The name of the store.
in	<i>description</i>	The store's description.
in	<i>recordStoreType</i>	The type of RecordStore subclass the internal RecordStores should be.
in	<i>parentDir</i>	The directory where the store is to be created.
in	<i>compressorType</i>	The type of compression that should be used within the internal RecordStores.

Exceptions

Error::ObjectExists	The store already exists.
Error::StrategyError	An error occurred when accessing the underlying file system.

E.19.2.2 [BiometricEvaluation::IO::CompressedRecordStore::CompressedRecordStore](#) (const string & *name*, const string & *description*, const string & *recordStoreType*, const string & *parentDir*, const Compressor::Kind & *compressorType*) throw (Error::ObjectExists, Error::StrategyError)

Create a new [CompressedRecordStore](#), read/write mode.

Parameters

in	<i>name</i>	The name of the store.
in	<i>description</i>	The store's description.
in	<i>recordStoreType</i>	The type of RecordStore subclass the internal RecordStores should be.

in	<i>parentDir</i>	The directory where the store is to be created.
in	<i>compressorType</i>	The type of compression that should be used within the internal RecordStores.

Exceptions

<i>Error::ObjectExists</i>	The store already exists.
<i>Error::StrategyError</i>	An error occurred when accessing the underlying file system.

E.19.2.3 `BiometricEvaluation::IO::CompressedRecordStore::CompressedRecordStore (const string & name, const string & parentDir, uint8_t mode = IO::READWRITE) throw (Error::ObjectDoesNotExist, Error::StrategyError)`

Open an existing [CompressedRecordStore](#).

Parameters

in	<i>name</i>	The name of the store.
in	<i>parentDir</i>	The directory where the store is to be created.
in	<i>mode</i>	Open mode, read-only or read-write.

Exceptions

<i>Error::ObjectDoesNotExist</i>	The store does not exist.
<i>Error::StrategyError</i>	An error occurred when accessing the underlying file system.

E.19.3 Member Function Documentation

E.19.3.1 `uint64_t BiometricEvaluation::IO::CompressedRecordStore::getSpaceUsed () const throw (Error::StrategyError) [virtual]`

Obtain real storage utilization.

The amount of disk space used, for example. This is the actual space allocated by the underlying storage mechanism, in bytes.

Returns

The amount of backing storage used by the [RecordStore](#).

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.
---	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.19.3.2 void BiometricEvaluation::IO::CompressedRecordStore::sync () const throw (Error::StrategyError) [virtual]

Synchronize the entire record store to persistent storage.

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.
---	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.19.3.3 void BiometricEvaluation::IO::CompressedRecordStore::insert (const string & key, const void *const data, const uint64_t size) throw (Error::ObjectExists, Error::StrategyError) [virtual]

Insert a record into the store.

Parameters

in	<i>key</i>	The key of the record to be inserted.
in	<i>data</i>	The data for the record.
in	<i>size</i>	The size, in bytes, of the record.

Exceptions

<i>Error::ObjectExists</i>	A record with the given key is already present.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.19.3.4 void BiometricEvaluation::IO::CompressedRecordStore::remove (const string & key) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Remove a record from the store.

Parameters

in	<i>key</i>	The key of the record to be removed.
----	------------	--------------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.19.3.5 `uint64_t BiometricEvaluation::IO::CompressedRecordStore::read (const string & key, void *const data) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Read a complete record from a store. Applications are responsible for allocating storage for the record's data.

Parameters

in	<i>key</i>	The key of the record to be read.
in	<i>data</i>	Pointer to where the data is to be written.

Returns

The size of the record.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.19.3.6 `void BiometricEvaluation::IO::CompressedRecordStore::replace (const string & key, const void *const data, const uint64_t size) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Replace a complete record in a store.

Parameters

in	<i>key</i>	The key of the record to be replaced.
in	<i>data</i>	The data for the record.
in	<i>size</i>	The size of data.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.19.3.7 `uint64_t BiometricEvaluation::IO::CompressedRecordStore::length (const string & key) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Return the length of a record.

Parameters

in	<i>key</i>	The key of the record.
----	------------	------------------------

Returns

The record length.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.19.3.8 void [BiometricEvaluation::IO::CompressedRecordStore::flush](#) (const string & *key*) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Commit the record's data to storage.

Parameters

in	<i>key</i>	The key of the record to be flushed.
----	------------	--------------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.19.3.9 uint64_t [BiometricEvaluation::IO::CompressedRecordStore::sequence](#) (string & *key*, void *const *data* = NULL, int *cursor* = BE_RECSTORE_SEQ_NEXT) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Sequence through a [RecordStore](#), returning the key/data pairs.

Sequencing means to start at some point in the store and return the record, then repeatedly calling the sequencor to return the next record. The starting point is typically the first record, and is set to that when the [RecordStore](#) object is created. The starting point can be reset by calling this method with the cursor parameter set to BE_RECSTORE_SEQ_START.

Parameters

out	<i>key</i>	The key of the currently sequenced record.
in	<i>data</i>	Pointer to where the data is to be written. Applications can set data to NULL to indicate only the key is wanted.
in	<i>cursor</i>	The location within the sequence of the key/data pair to return.

Returns

The length of the record currently in sequence.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.19.3.10 void [BiometricEvaluation::IO::CompressedRecordStore::setCursorAtKey](#) (string & *key*) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Set the sequence cursor to an arbitrary position within the [RecordStore](#), starting at key. Key will be the first record returned from the next call to [sequence\(\)](#).

Parameters

in	<i>key</i>	The key of the record which will be returned by the first subsequent call to sequence() .
----	------------	---

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.19.3.11 void [BiometricEvaluation::IO::CompressedRecordStore::changeName](#) (const string & *name*) throw (Error::ObjectExists, Error::StrategyError) [virtual]

Change the name of the [RecordStore](#).

Parameters

in	<i>name</i>	The new name for the RecordStore .
----	-------------	--

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying storage system, or the name is malformed.
-----------------------------	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.19.4 Member Data Documentation

E.19.4.1 `const string BiometricEvaluation::IO::CompressedRecordStore::BACKING_STORE` [static]

Name of the underlying store within this RS

E.19.4.2 `const string BiometricEvaluation::IO::CompressedRecordStore::COMPRESSOR_TYPE_KEY`
[static]

Name of the key storing compressor type

E.20 BiometricEvaluation::Image::CompressionAlgorithm Class Reference

[Image](#) compression algorithms.

```
#include <be_image.h>
```

Public Types

- enum **Kind** {
None = 0, **Facsimile** = 1, **WSQ20** = 2, **JPEGB** = 3,
JPEGL = 4, **JP2** = 5, **JP2L** = 6, **PNG** = 7,
NetPBM = 8 }


E.20.1 Detailed Description

[Image](#) compression algorithms.

E.21 BiometricEvaluation::IO::Compressor Class Reference

```
#include <be_io_compressor.h>
```

Inheritance diagram for BiometricEvaluation::IO::Compressor:



Public Types

- enum [Kind](#) { **GZIP** }

Public Member Functions

- [Compressor](#) ()

- Create a new *Compressor* object.
- virtual `Memory::uint8Array compress` (const uint8_t *const uncompressedData, uint64_t uncompressedDataSize) const =0 throw (Error::StrategyError)
 - *Compress a buffer.*
- virtual `Memory::uint8Array compress` (const `Memory::uint8Array` &uncompressedData) const =0 throw (Error::StrategyError)
 - *Compress a buffer.*
- virtual void `compress` (const uint8_t *const uncompressedData, uint64_t uncompressedDataSize, const string &outputFile) const =0 throw (Error::ObjectExists, Error::StrategyError)
 - *Compress a buffer.*
- virtual void `compress` (const `Memory::uint8Array` &uncompressedData, const string &outputFile) const =0 throw (Error::ObjectExists, Error::StrategyError)
 - *Compress a buffer.*
- virtual `Memory::uint8Array compress` (const string &inputFile) const =0 throw (Error::ObjectDoesNotExist, Error::StrategyError)
 - *Compress a file.*
- virtual void `compress` (const string &inputFile, const string &outputFile) const =0 throw (Error::ObjectDoesNotExist, Error::ObjectExists, Error::StrategyError)
 - *Compress a file.*
- virtual `Memory::uint8Array decompress` (const uint8_t *const compressedData, uint64_t compressedDataSize) const =0 throw (Error::StrategyError)
 - *Decompress a compressed buffer.*
- virtual `Memory::uint8Array decompress` (const `Memory::uint8Array` &compressedData) const =0 throw (Error::StrategyError)
 - *Decompress a compressed buffer.*
- virtual `Memory::uint8Array decompress` (const string &inputFile) const =0 throw (Error::ObjectDoesNotExist, Error::StrategyError)
 - *Decompress a compressed buffer into a file.*
- virtual void `decompress` (const `Memory::uint8Array` &compressedData, const string &outputFile) const =0 throw (Error::ObjectExists, Error::StrategyError)
 - *Decompress a file.*
- virtual void `decompress` (const uint8_t *const compressedData, const uint64_t compressedDataSize, const string &outputFile) const =0 throw (Error::ObjectExists, Error::StrategyError)
 - *Decompress a file.*
- virtual void `decompress` (const string &inputFile, const string &outputFile) const =0 throw (Error::ObjectDoesNotExist, Error::ObjectExists, Error::StrategyError)
 - *Decompress a file.*
- void `setOption` (const string &optionName, const string &optionValue) throw (Error::StrategyError)
 - *Assign a compressor option.*
- void `setOption` (const string &optionName, int64_t optionValue) throw (Error::StrategyError)
 - *Assign a compressor option.*
- string `getOption` (const string &optionName) const throw (Error::ObjectDoesNotExist)
 - *Obtain a compressor option as an integer.*
- int64_t `getOptionAsInteger` (const string &optionName) const throw (Error::ObjectDoesNotExist)
 - *Obtain a compressor option as an integer.*
- void `removeOption` (const string &optionName) throw (Error::ObjectDoesNotExist)
 - *Remove a compressor option.*
- virtual `~Compressor` ()

Static Public Member Functions

- static string [kindToString](#) ([Compressor::Kind](#) compressor) throw (Error::ObjectDoesNotExist)
Convert Kind enumeration to string.
- static [Compressor::Kind](#) [stringToKind](#) (const string &compressor) throw (Error::ObjectDoesNotExist)
Convert string to Kind enumeration.
- static tr1::shared_ptr
< [Compressor](#) > [createCompressor](#) ([Compressor::Kind](#) compressorKind=[Compressor::GZIP](#)) throw (-
Error::ObjectDoesNotExist)

Static Public Attributes

- static const string [GZIPTYPE](#)

E.21.1 Detailed Description

Implementations for compressing and decompressing data

E.21.2 Member Enumeration Documentation

E.21.2.1 enum [BiometricEvaluation::IO::Compressor::Kind](#)

Kinds of Compressors (for factory)

E.21.3 Constructor & Destructor Documentation

E.21.3.1 [BiometricEvaluation::IO::Compressor::Compressor](#) ()

Create a new [Compressor](#) object.

Default compression options will be used.

E.21.3.2 virtual [BiometricEvaluation::IO::Compressor::~Compressor](#) () [virtual]

Destructor

E.21.4 Member Function Documentation

E.21.4.1 static string [BiometricEvaluation::IO::Compressor::kindToString](#) ([Compressor::Kind](#) *compressor*) throw (Error::ObjectDoesNotExist) [static]

Convert Kind enumeration to string.

Parameters

in	<i>compressor</i>	The Compressor to convert.
----	-------------------	--

Returns

String representation of compressor.

Exceptions

<i>Error::ObjectDoesNotExist</i>	compressor is not a valid Compressor type.
----------------------------------	--

E.21.4.2 static [Compressor::Kind](#) BiometricEvaluation::IO::Compressor::stringToKind (const string & *compressor*) throw (Error::ObjectDoesNotExist) [static]

Convert string to Kind enumeration.

Parameters

in	<i>compressor</i>	The Compressor to convert.
----	-------------------	--

Returns

Kind enumeration of compressor.

Exceptions

<i>Error::ObjectDoesNotExist</i>	compressor is not a valid Compressor type.
----------------------------------	--

E.21.4.3 virtual [Memory::uint8Array](#) BiometricEvaluation::IO::Compressor::compress (const [uint8_t](#) *const *uncompressedData*, [uint64_t](#) *uncompressedDataSize*) const throw (Error::StrategyError) [pure virtual]

Compress a buffer.

Parameters

<i>uncompressed-Data</i>	Uncompressed data buffer to compress.
<i>uncompressed-DataSize</i>	Size of uncompressedData.

Returns

Compressed buffer.

Exceptions

<i>Error::StrategyError</i>	Error in compression unit.
-----------------------------	----------------------------

Implemented in [BiometricEvaluation::IO::GZip](#).

E.21.4.4 `virtual Memory::uint8Array BiometricEvaluation::IO::Compressor::compress (const Memory::uint8Array & uncompressedData) const throw (Error::StrategyError) [pure virtual]`

Compress a buffer.

Parameters

<i>uncompressed-Data</i>	Uncompressed data buffer to compress.
--------------------------	---------------------------------------

Returns

Compressed buffer.

Exceptions

Error::StrategyError	Error in decompression unit.
--------------------------------------	------------------------------

Implemented in [BiometricEvaluation::IO::GZip](#).

E.21.4.5 `virtual void BiometricEvaluation::IO::Compressor::compress (const uint8_t *const uncompressedData, uint64_t uncompressedDataSize, const string & outputFile) const throw (Error::ObjectExists, Error::StrategyError) [pure virtual]`

Compress a buffer.

Parameters

<i>uncompressed-Data</i>	Uncompressed data buffer to compress.
<i>uncompressed-DataSize</i>	Size of uncompressedData.
<i>outputFile</i>	Location to save compressed file.

Exceptions

Error::ObjectExists	Output file already exists.
Error::StrategyError	Error in compression unit.

Implemented in [BiometricEvaluation::IO::GZip](#).

E.21.4.6 `virtual void BiometricEvaluation::IO::Compressor::compress (const Memory::uint8Array & uncompressedData, const string & outputFile) const throw (Error::ObjectExists, Error::StrategyError) [pure virtual]`

Compress a buffer.

Parameters

<i>uncompressed-Data</i>	Uncompressed data buffer to compress.
<i>outputFile</i>	Location to save compressed file.

Exceptions

<i>Error::ObjectExists</i>	Output file already exists.
<i>Error::StrategyError</i>	Error in decompression unit.

Implemented in [BiometricEvaluation::IO::GZip](#).

E.21.4.7 `virtual Memory::uint8Array BiometricEvaluation::IO::Compressor::compress (const string & inputFile) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [pure virtual]`

Compress a file.

Parameters

<i>inputFile</i>	Path to file to compress.
------------------	---------------------------

Returns

Compressed buffer.

Exceptions

<i>Error::ObjectDoesNotExist</i>	Input file does not exist.
<i>Error::StrategyError</i>	Error in decompression unit.

Implemented in [BiometricEvaluation::IO::GZip](#).

E.21.4.8 `virtual void BiometricEvaluation::IO::Compressor::compress (const string & inputFile, const string & outputFile) const throw (Error::ObjectDoesNotExist, Error::ObjectExists, Error::StrategyError) [pure virtual]`

Compress a file.

Parameters

<i>inputFile</i>	Path to file to compress.
<i>outputFile</i>	Path to location where compressed version will be saved.

Exceptions

<i>Error::ObjectDoesNotExist</i>	Input file does not exist.
<i>Error::ObjectExists</i>	Output file already exists.
<i>Error::StrategyError</i>	Error in decompression unit.

Implemented in [BiometricEvaluation::IO::GZip](#).

E.21.4.9 `virtual Memory::uint8Array BiometricEvaluation::IO::Compressor::decompress (const uint8_t *const compressedData, uint64_t compressedDataSize) const throw (Error::StrategyError) [pure virtual]`

Decompress a compressed buffer.

Parameters

<i>compressed-Data</i>	Compressed data buffer to decompress.
<i>compressed-DataSize</i>	Size of compressedData.

Returns

Decompressed buffer.

Exceptions

<i>Error::StrategyError</i>	Error in compression unit.
---	--

Implemented in [BiometricEvaluation::IO::GZip](#).

E.21.4.10 `virtual Memory::uint8Array BiometricEvaluation::IO::Compressor::decompress (const Memory::uint8Array & compressedData) const throw (Error::StrategyError) [pure virtual]`

Decompress a compressed buffer.

Parameters

<i>compressed-Data</i>	Compressed data buffer to decompress.
------------------------	---------------------------------------

Returns

Decompressed buffer.

Exceptions

<i>Error::StrategyError</i>	Error in decompression unit.
---	------------------------------

Implemented in [BiometricEvaluation::IO::GZip](#).

E.21.4.11 `virtual Memory::uint8Array BiometricEvaluation::IO::Compressor::decompress (const string & inputFile) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [pure virtual]`

Decompress a compressed buffer into a file.

Parameters

<i>inputFile</i>	Location to save compressed file.
------------------	-----------------------------------

Returns

Decompressed buffer.

Exceptions

<i>Error::StrategyError</i>	Error in decompression unit.
<i>Error::ObjectDoesNotExist</i>	Output file already exists.

Implemented in [BiometricEvaluation::IO::GZip](#).

E.21.4.12 `virtual void BiometricEvaluation::IO::Compressor::decompress (const Memory::uint8Array & compressedData, const string & outputFile) const throw (Error::ObjectExists, Error::StrategyError) [pure virtual]`

Decompress a file.

Parameters

<i>compressed-Data</i>	Compressed data buffer to decompress.
<i>outputFile</i>	Path to location where decompressed version will be saved.

Exceptions

<i>Error::ObjectExists</i>	Output file already exists.
<i>Error::StrategyError</i>	Error in compression unit.

Implemented in [BiometricEvaluation::IO::GZip](#).

E.21.4.13 `virtual void BiometricEvaluation::IO::Compressor::decompress (const uint8_t *const compressedData, const uint64_t compressedDataSize, const string & outputFile) const throw (Error::ObjectExists, Error::StrategyError) [pure virtual]`

Decompress a file.

Parameters

<i>compressed-Data</i>	Compressed data buffer to decompress.
<i>compressed-DataSize</i>	Size of compressedData.
<i>outputFile</i>	Path to location where decompressed version will be saved.

Exceptions

Error::ObjectExists	Output file already exists.
Error::StrategyError	Error in compression unit.

Implemented in [BiometricEvaluation::IO::GZip](#).

E.21.4.14 `virtual void BiometricEvaluation::IO::Compressor::decompress (const string & inputFile, const string & outputFile) const throw (Error::ObjectDoesNotExist, Error::ObjectExists, Error::StrategyError) [pure virtual]`

Decompress a file.

Parameters

<i>inputFile</i>	Path to file to decompress.
<i>outputFile</i>	Path to location where decompressed version will be saved.

Exceptions

Error::ObjectDoesNotExist	Input file does not exist.
Error::ObjectExists	Output file already exists.
Error::StrategyError	Error in compression unit.

Implemented in [BiometricEvaluation::IO::GZip](#).

E.21.4.15 `void BiometricEvaluation::IO::Compressor::setOption (const string & optionName, const string & optionValue) throw (Error::StrategyError)`

Assign a compressor option.

Will overwrite existing values without warning.

Parameters

<i>optionName</i>	Name of the option to add.
<i>optionValue</i>	Value of the option.

Exceptions

<i>Error::StrategyError</i>	Error setting option.
---	---------------------------------------

E.21.4.16 void BiometricEvaluation::IO::Compressor::setOption (const string & *optionName*, int64_t *optionValue*) throw (Error::StrategyError)

Assign a compressor option.

Will overwrite existing values without warning.

Parameters

<i>optionName</i>	Name of the option to add.
<i>optionValue</i>	Value of the option.

Exceptions

<i>Error::StrategyError</i>	Error setting option.
---	---------------------------------------

E.21.4.17 string BiometricEvaluation::IO::Compressor::getOption (const string & *optionName*) const throw (Error::ObjectDoesNotExist)

Obtain a compressor option as an integer.

Parameters

<i>optionName</i>	Name of the option to obtain.
-------------------	-------------------------------

Returns

Value of compressor option.

E.21.4.18 int64_t BiometricEvaluation::IO::Compressor::getOptionAsInteger (const string & *optionName*) const throw (Error::ObjectDoesNotExist)

Obtain a compressor option as an integer.

Parameters

<i>optionName</i>	Name of the option to obtain.
-------------------	-------------------------------

Returns

Value of compressor option.

Exceptions

<i>Error::ObjectDoesNotExist</i>	The option was never set.
--	---------------------------

E.21.4.19 void BiometricEvaluation::IO::Compressor::removeOption (const string & *optionName*) throw (Error::ObjectDoesNotExist)

Remove a compressor option.

Parameters

<i>optionName</i>	Name of the option to remove.
-------------------	-------------------------------

E.21.4.20 static tr1::shared_ptr<Compressor> BiometricEvaluation::IO::Compressor::createCompressor (Compressor::Kind *compressorKind* = Compressor::GZIP) throw (Error::ObjectDoesNotExist) [static]

[Compressor](#) factory.

Parameters

<i>compressorKind</i>	A known kind of compressor.
-----------------------	-----------------------------

Returns

A new compressor with default options.

Exceptions

<i>Error::ObjectDoesNotExist</i>	Invalid compressor type.
--	--------------------------

E.21.5 Member Data Documentation

E.21.5.1 const string BiometricEvaluation::IO::Compressor::GZIPTYPE [static]


String representations of the compressors

E.22 BiometricEvaluation::Error::ConversionError Class Reference

[Error](#) when converting one object into another, a property value from string to int, for example.

```
#include <be_error_exception.h>
```

Inheritance diagram for BiometricEvaluation::Error::ConversionError:



Public Member Functions

- [ConversionError](#) ()
- [ConversionError](#) (string info)

E.22.1 Detailed Description

[Error](#) when converting one object into another, a property value from string to int, for example.

E.22.2 Constructor & Destructor Documentation

E.22.2.1 BiometricEvaluation::Error::ConversionError::ConversionError ()

Construct a [ConversionError](#) object with the default information string.

E.22.2.2 BiometricEvaluation::Error::ConversionError::ConversionError (string info)

Construct a [ConversionError](#) object with an information string appended to the default information string.

E.23 BiometricEvaluation::Image::Coordinate Struct Reference

A structure to contain a two-dimensional coordinate without a specified origin.

```
#include <be_image.h>
```

Public Member Functions

- [Coordinate](#) (const uint32_t x=0, const uint32_t y=0, const float xDistance=0, const float yDistance=0)
Create a [Coordinate](#) struct.

Public Attributes

- uint32_t x
- uint32_t y
- float xDistance
- float yDistance

E.23.1 Detailed Description

A structure to contain a two-dimensional coordinate without a specified origin.

E.23.2 Constructor & Destructor Documentation

E.23.2.1 `BiometricEvaluation::Image::Coordinate::Coordinate (const uint32_t x = 0, const uint32_t y = 0, const float xDistance = 0, const float yDistance = 0)`

Create a [Coordinate](#) struct.

Parameters

in	<i>x</i>	X-coordinate
in	<i>y</i>	Y-coordinate
in	<i>xDistance</i>	X-coordinate distance from origin
in	<i>yDistance</i>	Y-coordinate distance from origin

E.23.3 Member Data Documentation

E.23.3.1 `uint32_t BiometricEvaluation::Image::Coordinate::x`

X-coordinate

E.23.3.2 `uint32_t BiometricEvaluation::Image::Coordinate::y`

Y-coordinate

E.23.3.3 `float BiometricEvaluation::Image::Coordinate::xDistance`

X-coordinate distance from origin

E.23.3.4 `float BiometricEvaluation::Image::Coordinate::yDistance`

Y-coordinate distance from origin

E.24 BiometricEvaluation::Feature::CorePoint Struct Reference

Representation of the core.

```
#include <be_feature_minutiae.h>
```

Public Member Functions

- [CorePoint](#) ([Image::Coordinate](#) coordinate, bool has_angle=false, int angle=0)

Create a [CorePoint](#) struct.

Public Attributes

- [Image::Coordinate](#) **coordinate**
- bool **has_angle**
- int **angle**

E.24.1 Detailed Description

Representation of the core.


A core has a coordinate and an optional angle. The units for the X/Y coordinate and the angle are specific to the record format represented by an object of this class.

E.25 BiometricEvaluation::Error::DataError Class Reference

[Error](#) when reading data from an external source.

```
#include <be_error_exception.h>
```

Inheritance diagram for BiometricEvaluation::Error::DataError:



Public Member Functions

- [DataError](#) ()
- [DataError](#) (string info)

E.25.1 Detailed Description

[Error](#) when reading data from an external source.

Typically occurs when reading data from a standard record, ANST/NIST 2000, for example, and a required field is missing, or a field has invalid data.

E.25.2 Constructor & Destructor Documentation

E.25.2.1 BiometricEvaluation::Error::DataError::DataError ()

Construct a [DataError](#) object with the default information string.

E.25.2.2 BiometricEvaluation::Error::DataError::DataError (string info)


Construct a [DataError](#) object with an information string appended to the default information string.

E.26 BiometricEvaluation::IO::DBRecordStore Class Reference

A class that implements [IO::RecordStore](#) using a Berkeley DB database as the underlying record storage system.

```
#include <be_io_dbrecstore.h>
```

Inheritance diagram for BiometricEvaluation::IO::DBRecordStore:



Public Member Functions

- [DBRecordStore](#) (const string &name, const string &description, const string &parentDir) throw (Error::ObjectExists, Error::StrategyError)
- [DBRecordStore](#) (const string &name, const string &parentDir, uint8_t mode=IO::READWRITE) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [getSpaceUsed](#) () const throw (Error::StrategyError)
Obtain real storage utilization.
- void [sync](#) () const throw (Error::StrategyError)
- void [insert](#) (const string &key, const void *const data, const uint64_t size) throw (Error::ObjectExists, Error::StrategyError)
- void [remove](#) (const string &key) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [read](#) (const string &key, void *const data) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void [replace](#) (const string &key, const void *const data, const uint64_t size) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [length](#) (const string &key) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void [flush](#) (const string &key) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [sequence](#) (string &key, void *const data=NULL, int cursor=BE_RECSTORE_SEQ_NEXT) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Sequence through a [RecordStore](#), returning the key/data pairs.
- void [setCursorAtKey](#) (string &key) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void [changeName](#) (const string &name) throw (Error::ObjectExists, Error::StrategyError)

Additional Inherited Members

E.26.1 Detailed Description

A class that implements [IO::RecordStore](#) using a Berkeley DB database as the underlying record storage system.

E.26.2 Constructor & Destructor Documentation

E.26.2.1 `BiometricEvaluation::IO::DBRecordStore::DBRecordStore (const string & name, const string & description, const string & parentDir) throw (Error::ObjectExists, Error::StrategyError)`

Create a new [DBRecordStore](#), read/write mode.

Parameters

in	<i>name</i>	The name of the store.
in	<i>description</i>	The store's description.
in	<i>parentDir</i>	The directory where the store is to be created.

Exceptions

Error::ObjectExists	The store already exists.
Error::StrategyError	An error occurred when accessing the underlying file system.

E.26.2.2 `BiometricEvaluation::IO::DBRecordStore::DBRecordStore (const string & name, const string & parentDir, uint8_t mode = IO::READWRITE) throw (Error::ObjectDoesNotExist, Error::StrategyError)`

Open an existing [DBRecordStore](#).

Parameters

in	<i>name</i>	The name of the store.
in	<i>parentDir</i>	The directory where the store is to be created.
in	<i>mode</i>	Open mode, read-only or read-write.

Exceptions

Error::ObjectDoesNotExist	The store does not exist.
Error::StrategyError	An error occurred when accessing the underlying file system.

E.26.3 Member Function Documentation

E.26.3.1 `uint64_t BiometricEvaluation::IO::DBRecordStore::getSpaceUsed () const throw (Error::StrategyError) [virtual]`

Obtain real storage utilization.

The amount of disk space used, for example. This is the actual space allocated by the underlying storage mechanism, in bytes.

Returns

The amount of backing storage used by the [RecordStore](#).

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.
---	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.26.3.2 `void BiometricEvaluation::IO::DBRecordStore::sync () const throw (Error::StrategyError)`
[virtual]

Synchronize the entire record store to persistent storage.

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.
---	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.26.3.3 `void BiometricEvaluation::IO::DBRecordStore::insert (const string & key, const void *const data, const uint64_t size) throw (Error::ObjectExists, Error::StrategyError)` [virtual]

Insert a record into the store.

Parameters

in	<i>key</i>	The key of the record to be inserted.
in	<i>data</i>	The data for the record.
in	<i>size</i>	The size, in bytes, of the record.

Exceptions

<i>Error::ObjectExists</i>	A record with the given key is already present.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.26.3.4 `void BiometricEvaluation::IO::DBRecordStore::remove (const string & key) throw (Error::ObjectDoesNotExist, Error::StrategyError)` [virtual]

Remove a record from the store.

Parameters

in	<i>key</i>	The key of the record to be removed.
----	------------	--------------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.26.3.5 `uint64_t BiometricEvaluation::IO::DBRecordStore::read (const string & key, void *const data) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Read a complete record from a store. Applications are responsible for allocating storage for the record's data.

Parameters

in	<i>key</i>	The key of the record to be read.
in	<i>data</i>	Pointer to where the data is to be written.

Returns

The size of the record.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.26.3.6 `void BiometricEvaluation::IO::DBRecordStore::replace (const string & key, const void *const data, const uint64_t size) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Replace a complete record in a store.

Parameters

in	<i>key</i>	The key of the record to be replaced.
in	<i>data</i>	The data for the record.
in	<i>size</i>	The size of data.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.26.3.7 `uint64_t BiometricEvaluation::IO::DBRecordStore::length (const string & key) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Return the length of a record.

Parameters

in	<i>key</i>	The key of the record.
----	------------	------------------------

Returns

The record length.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.26.3.8 void BiometricEvaluation::IO::DBRecordStore::flush (const string & *key*) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Commit the record's data to storage.

Parameters

in	<i>key</i>	The key of the record to be flushed.
----	------------	--------------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.26.3.9 uint64_t BiometricEvaluation::IO::DBRecordStore::sequence (string & *key*, void *const *data* = NULL, int *cursor* = BE_RECSTORE_SEQ_NEXT) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Sequence through a [RecordStore](#), returning the key/data pairs.

Sequencing means to start at some point in the store and return the record, then repeatedly calling the sequencor to return the next record. The starting point is typically the first record, and is set to that when the [RecordStore](#) object is created. The starting point can be reset by calling this method with the cursor parameter set to BE_RECSTORE_SEQ_START.

Parameters

out	<i>key</i>	The key of the currently sequenced record.
in	<i>data</i>	Pointer to where the data is to be written. Applications can set data to NULL to indicate only the key is wanted.
in	<i>cursor</i>	The location within the sequence of the key/data pair to return.

Returns

The length of the record currently in sequence.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.26.3.10 void [BiometricEvaluation::IO::DBRecordStore::setCursorAtKey](#) (string & *key*) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Set the sequence cursor to an arbitrary position within the [RecordStore](#), starting at key. Key will be the first record returned from the next call to [sequence\(\)](#).

Parameters

in	<i>key</i>	The key of the record which will be returned by the first subsequent call to sequence() .
----	------------	---

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.26.3.11 void [BiometricEvaluation::IO::DBRecordStore::changeName](#) (const string & *name*) throw (Error::ObjectExists, Error::StrategyError) [virtual]

Change the name of the [RecordStore](#).

Parameters

in	<i>name</i>	The new name for the RecordStore .
----	-------------	--

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying storage system, or the name is malformed.
-----------------------------	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.27 BiometricEvaluation::Feature::DeltaPoint Struct Reference

Representation of the delta.

```
#include <be_feature_minutiae.h>
```

Public Member Functions

- [DeltaPoint](#) ([Image::Coordinate](#) coordinate, bool has_angle=false, int angle1=0, int angle2=0, int angle3=0)

Create a [DeltaPoint](#) struct.

Public Attributes

- [Image::Coordinate](#) **coordinate**
- bool **has_angle**
- int **angle1**
- int **angle2**
- int **angle3**

E.27.1 Detailed Description

Representation of the delta.

A delta has a coordinate and an optional angle. The units for the X/Y coordinate and the angle are specific to the record format represented by an object of this class.

E.28 BiometricEvaluation::View::AN2KView::DeviceMonitoringMode Class Reference

The level of human monitoring for the image capture device.

```
#include <be_view_an2kview.h>
```

Public Types

- enum [Kind](#) {
 [Controlled](#), [Assisted](#), [Observed](#), [Unattended](#),
 [Unknown](#), [NA](#) }

E.28.1 Detailed Description

The level of human monitoring for the image capture device.

E.28.2 Member Enumeration Documentation

E.28.2.1 enum BiometricEvaluation::View::AN2KView::DeviceMonitoringMode::Kind

Enumerator

- Controlled** Operator physically controls the subject to acquire biometric sample.
- Assisted** Person available to provide assistance to the subject submitting the biometric.
- Observed** Person present to observe the operation of the device but provides no assistance.
- Unattended** No one present to observe or provide assistance.
- Unknown** No information is known.
- NA** Optional field – not specified

E.29 BiometricEvaluation::DataInterchange::AN2KRecord::DomainName Struct Reference

Representation of a domain name for the user-defined Type-2 logical record implementation.

```
#include <be_data_interchange_an2k.h>
```

Public Member Functions

- [DomainName](#) (string [identifier](#)="", string [version](#)="")
Create a [DomainName](#) struct.

Public Attributes

- string [identifier](#)
- string [version](#)

E.29.1 Detailed Description

Representation of a domain name for the user-defined Type-2 logical record implementation.

E.29.2 Constructor & Destructor Documentation

E.29.2.1 BiometricEvaluation::DataInterchange::AN2KRecord::DomainName::DomainName (string *identifier* = "", string *version* = " ") [inline]

Create a [DomainName](#) struct.

Parameters

<i>identifier</i>	Unique identifier for agency, entity, or implementation.
<i>version</i>	Optional unique version number of the implementation of the identifier.

E.29.3 Member Data Documentation

E.29.3.1 `string BiometricEvaluation::DataInterchange::AN2KRecord::DomainName::identifier`

Unique identifier for agency, entity, or implementation.

E.29.3.2 `string BiometricEvaluation::DataInterchange::AN2KRecord::DomainName::version`

Optional version of the implementation

E.30 `BiometricEvaluation::Feature::AN2K7Minutiae::EncodingMethod` Class Reference

Methods for encoding minutiae data in an AN2K record.

```
#include <be_feature_an2k7minutiae.h>
```

Public Types

- enum **Kind** { **Automatic** = 0, **AutomaticUnedited**, **AutomaticEdited**, **Manual** }

E.30.1 Detailed Description

Methods for encoding minutiae data in an AN2K record.

E.31 `BiometricEvaluation::Feature::AN2K7Minutiae::PatternClassification::Entry` Struct Reference

Public Member Functions

- [Entry](#) (bool [standard](#), std::string [code](#))

Public Attributes

- bool [standard](#)
- std::string [code](#)

E.31.1 Constructor & Destructor Documentation

E.31.1.1 `BiometricEvaluation::Feature::AN2K7Minutiae::PatternClassification::Entry::Entry (bool standard, std::string code)`

Create an [Entry](#) struct.

Parameters

<i>standard</i>	Whether or not code is a standard AN2K pattern classification code.
<i>code</i>	AN2K or user-defined pattern classification code.

E.31.2 Member Data Documentation

E.31.2.1 bool BiometricEvaluation::Feature::AN2K7Minutiae::PatternClassification::Entry::standard

Whether code is a standard AN2K pattern classification code.

E.31.2.2 std::string BiometricEvaluation::Feature::AN2K7Minutiae::PatternClassification::Entry::code


AN2K or user-defined pattern classification code.

E.32 BiometricEvaluation::Error::Exception Class Reference

The parent class of all BiometricEvaluation exceptions.

```
#include <be_error_exception.h>
```

Inheritance diagram for BiometricEvaluation::Error::Exception:



Public Member Functions

- [Exception](#) ()
- [Exception](#) (string info)
- string [getInfo](#) ()

E.32.1 Detailed Description

The parent class of all BiometricEvaluation exceptions.

The classes derived from this class will have a default information string set indicating the type of exception. Any additional information string is appended to that string.

E.32.2 Constructor & Destructor Documentation

E.32.2.1 BiometricEvaluation::Error::Exception::Exception ()

Construct an [Exception](#) object without an information string.

E.32.2.2 BiometricEvaluation::Error::Exception::Exception (string *info*)

Construct an [Exception](#) object with an information string.

Parameters

<i>in</i>	<i>info</i>	The information string associated with the exception.
-----------	-------------	---

E.32.3 Member Function Documentation

E.32.3.1 string BiometricEvaluation::Error::Exception::getInfo ()

Obtain the information string associated with the exception.

Returns


The information string.

E.33 BiometricEvaluation::Error::FileError Class Reference

File error when opening, reading, writing, etc.

```
#include <be_error_exception.h>
```

Inheritance diagram for BiometricEvaluation::Error::FileError:



Public Member Functions

- [FileError](#) ()
- [FileError](#) (string *info*)

E.33.1 Detailed Description

File error when opening, reading, writing, etc.

E.33.2 Constructor & Destructor Documentation

E.33.2.1 BiometricEvaluation::Error::FileError::FileError ()

Construct a [FileError](#) object with the default information string.


E.33.2.2 BiometricEvaluation::Error::FileError::FileError (string info)

Construct a [FileError](#) object with an information string appended to the default information string.

E.34 BiometricEvaluation::IO::FileRecordStore Class Reference

```
#include <be_io_filerecstore.h>
```

Inheritance diagram for BiometricEvaluation::IO::FileRecordStore:



Public Member Functions

- [FileRecordStore](#) (const string &name, const string &description, const string &parentDir) throw (Error::ObjectExists, Error::StrategyError)
- [FileRecordStore](#) (const string &name, const string &parentDir, uint8_t mode=IO::READWRITE) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [getSpaceUsed](#) () const throw (Error::StrategyError)

Obtain real storage utilization.

- void [insert](#) (const string &key, const void *const data, const uint64_t size) throw (Error::ObjectExists, Error::StrategyError)
- void [remove](#) (const string &key) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [read](#) (const string &key, void *const data) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- virtual void [replace](#) (const string &key, const void *const data, const uint64_t size) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- virtual uint64_t [length](#) (const string &key) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void [flush](#) (const string &key) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [sequence](#) (string &key, void *const data=NULL, int cursor=BE_RECSTORE_SEQ_NEXT) throw (Error::ObjectDoesNotExist, Error::StrategyError)

Sequence through a [RecordStore](#), returning the key/data pairs.

- void [setCursorAtKey](#) (string &key) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void [changeName](#) (const string &name) throw (Error::ObjectExists, Error::StrategyError)

Protected Member Functions

- string [canonicalName](#) (const string &name) const

Additional Inherited Members

E.34.1 Detailed Description

Class to represent the record store data storage mechanism implemented as files for each record.

Note

For the methods that take a key parameter, [Error::StrategyError](#) will be thrown if the key string is not compliant. A [FileRecordStore](#) has the additional requirement that a key name may not contain path delimiter characters ('/' and '\'), or begin with whitespace.

E.34.2 Constructor & Destructor Documentation

E.34.2.1 `BiometricEvaluation::IO::FileRecordStore::FileRecordStore (const string & name, const string & description, const string & parentDir) throw (Error::ObjectExists, Error::StrategyError)`

Create a new [FileRecordStore](#), read/write mode.

Parameters

in	<i>name</i>	The name of the store.
in	<i>description</i>	The store's description.
in	<i>parentDir</i>	The directory where the store is to be created.

Exceptions

Error::ObjectExists	The store already exists.
Error::StrategyError	An error occurred when accessing the underlying file system.

E.34.2.2 `BiometricEvaluation::IO::FileRecordStore::FileRecordStore (const string & name, const string & parentDir, uint8_t mode = IO::READWRITE) throw (Error::ObjectDoesNotExist, Error::StrategyError)`

Open an existing [FileRecordStore](#).

Parameters

in	<i>name</i>	The name of the store.
in	<i>parentDir</i>	The directory where the store is to be created.
in	<i>mode</i>	Open mode, read-only or read-write.

Exceptions

Error::ObjectDoesNotExist	The store does not exist.
Error::StrategyError	An error occurred when accessing the underlying file system.

E.34.3 Member Function Documentation

E.34.3.1 `uint64_t BiometricEvaluation::IO::FileRecordStore::getSpaceUsed () const throw (Error::StrategyError) [virtual]`

Obtain real storage utilization.

The amount of disk space used, for example. This is the actual space allocated by the underlying storage mechanism, in bytes.

Returns

The amount of backing storage used by the [RecordStore](#).

Exceptions

Error::StrategyError	An error occurred when using the underlying storage system.
--------------------------------------	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.34.3.2 `void BiometricEvaluation::IO::FileRecordStore::insert (const string & key, const void *const data, const uint64_t size) throw (Error::ObjectExists, Error::StrategyError) [virtual]`

Insert a record into the store.

Parameters

in	<i>key</i>	The key of the record to be inserted.
in	<i>data</i>	The data for the record.
in	<i>size</i>	The size, in bytes, of the record.

Exceptions

Error::ObjectExists	A record with the given key is already present.
Error::StrategyError	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.34.3.3 `void BiometricEvaluation::IO::FileRecordStore::remove (const string & key) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Remove a record from the store.

Parameters

in	<i>key</i>	The key of the record to be removed.
----	------------	--------------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.34.3.4 `uint64_t BiometricEvaluation::IO::FileRecordStore::read (const string & key, void *const data) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Read a complete record from a store. Applications are responsible for allocating storage for the record's data.

Parameters

in	<i>key</i>	The key of the record to be read.
in	<i>data</i>	Pointer to where the data is to be written.

Returns

The size of the record.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.34.3.5 `virtual void BiometricEvaluation::IO::FileRecordStore::replace (const string & key, const void *const data, const uint64_t size) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Replace a complete record in a store.

Parameters

in	<i>key</i>	The key of the record to be replaced.
in	<i>data</i>	The data for the record.
in	<i>size</i>	The size of data.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.34.3.6 `virtual uint64_t BiometricEvaluation::IO::FileRecordStore::length (const string & key) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Return the length of a record.

Parameters

<code>in</code>	<code>key</code>	The key of the record.
-----------------	------------------	------------------------

Returns

The record length.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.34.3.7 `void BiometricEvaluation::IO::FileRecordStore::flush (const string & key) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Commit the record's data to storage.

Parameters

<code>in</code>	<code>key</code>	The key of the record to be flushed.
-----------------	------------------	--------------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.34.3.8 `uint64_t BiometricEvaluation::IO::FileRecordStore::sequence (string & key, void *const data = NULL, int cursor = BE_RECSTORE_SEQ_NEXT) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Sequence through a [RecordStore](#), returning the key/data pairs.

Sequencing means to start at some point in the store and return the record, then repeatedly calling the sequencor to return the next record. The starting point is typically the first record, and is set to that when the [RecordStore](#) object is created. The starting point can be reset by calling this method with the cursor parameter set to BE_RECSTORE_SEQ_START.

Parameters

out	<i>key</i>	The key of the currently sequenced record.
in	<i>data</i>	Pointer to where the data is to be written. Applications can set data to NULL to indicate only the key is wanted.
in	<i>cursor</i>	The location within the sequence of the key/data pair to return.

Returns

The length of the record currently in sequence.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.34.3.9 void BiometricEvaluation::IO::FileRecordStore::setCursorAtKey (string & *key*) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Set the sequence cursor to an arbitrary position within the [RecordStore](#), starting at *key*. *Key* will be the first record returned from the next call to [sequence\(\)](#).

Parameters

in	<i>key</i>	The key of the record which will be returned by the first subsequent call to sequence() .
----	------------	---

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.34.3.10 void BiometricEvaluation::IO::FileRecordStore::changeName (const string & *name*) throw (Error::ObjectExists, Error::StrategyError) [virtual]

Change the name of the [RecordStore](#).

Parameters

in	<i>name</i>	The new name for the RecordStore .
----	-------------	--

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying storage system, or the name is malformed.
---	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.35 BiometricEvaluation::Finger::FingerImageCode Class Reference

```
#include <be_finger.h>
```

Public Types

- enum **Kind** {
EJI = 0, RolledTip, FullFingerRolled, FullFingerPlainLeft,
FullFingerPlainCenter, FullFingerPlainRight, ProximalSegment, DistalSegment,
MedialSegment, NA }

E.35.1 Detailed Description

Joint and tip codes.

E.36 BiometricEvaluation::Feature::AN2K7Minutiae::FingerprintReadingSystem Struct Reference

Representation of information about a fingerprint reader system.

```
#include <be_feature_an2k7minutiae.h>
```

Public Attributes

- string [name](#)
- EncodingMethod::Kind [method](#)
- string [equipment](#)

E.36.1 Detailed Description

Representation of information about a fingerprint reader system.

E.36.2 Member Data Documentation**E.36.2.1 string BiometricEvaluation::Feature::AN2K7Minutiae::FingerprintReadingSystem::name**

Name for system that encoded minutiae

E.36.2.2 EncodingMethod::Kind BiometricEvaluation::Feature::AN2K7Minutiae::FingerprintReadingSystem::method

Method used to encoded minutiae

E.36.2.3 string BiometricEvaluation::Feature::AN2K7Minutiae::FingerprintReadingSystem::equipment

Optional ID for equipment used in system

E.37 BiometricEvaluation::Finger::AN2KViewCapture::FingerSegmentPosition Struct Reference

Locations of an individual finger segment in a slap.

```
#include <be_finger_an2kview_capture.h>
```

Public Member Functions

- [FingerSegmentPosition](#) (const Finger::Position::Kind [fingerPosition](#), const Image::CoordinateSet [coordinates](#))

Create an *FingerSegmentPosition* struct.

Public Attributes

- Finger::Position::Kind [fingerPosition](#)
- Image::CoordinateSet [coordinates](#)

E.37.1 Detailed Description

Locations of an individual finger segment in a slap.

E.37.2 Constructor & Destructor Documentation

E.37.2.1 BiometricEvaluation::Finger::AN2KViewCapture::FingerSegmentPosition::FingerSegmentPosition (const Finger::Position::Kind *fingerPosition*, const Image::CoordinateSet *coordinates*)

Create an [FingerSegmentPosition](#) struct.

Parameters

<i>fingerPosition</i>	Finger depicted in this segment.
<i>coordinates</i>	Collection of coordinates that compose the segment bonding polygon.

E.37.3 Member Data Documentation

E.37.3.1 Finger::Position::Kind BiometricEvaluation::Finger::AN2KViewCapture::FingerSegmentPosition::fingerPosition

[Finger](#) depicted in this segment

E.37.3.2 Image::CoordinateSet BiometricEvaluation::Finger::AN2KViewCapture::FingerSegmentPosition::coordinates


Points composing the segmented polygon

E.38 BiometricEvaluation::Process::ForkManager Class Reference

[Manager](#) implementation that starts Workers by calling fork(2).

```
#include <be_process_forkmanager.h>
```

Inheritance diagram for BiometricEvaluation::Process::ForkManager:



Public Member Functions

- [ForkManager](#) ()
- `tr1::shared_ptr< WorkerController > addWorker (tr1::shared_ptr< Worker > worker)`
Adds a [Worker](#) to be managed by this [Manager](#).
- `void startWorkers (bool wait=true, bool communicate=false) throw (Error::ObjectExists, Error::StrategyError)`
Begin [Worker](#)'s work.
- `void startWorker (tr1::shared_ptr< WorkerController > worker, bool wait=true, bool communicate=false) throw (Error::ObjectExists, Error::StrategyError)`
Start a worker.
- `int32_t stopWorker (tr1::shared_ptr< WorkerController > workerController) throw (Error::ObjectDoesNotExist, Error::StrategyError)`
Ask [Worker](#) to exit.
- `void broadcastSignal (int signo)`
Send a POSIX signal to all workers.
- `bool responsibleFor (const pid_t pid) const`
Obtain whether or not this [ForkManager](#) is responsible for a particular PID.
- `void setNotWorking (const pid_t pid)`
Set Status.isWorking for PID to false.
- `void markAllFinished ()`
Call [setNotWorking\(\)](#) for all PIDs known to this [ForkManager](#).

- bool [getIsWorkingStatus](#) (const pid_t pid) const
Get Status.isWorking for PID.
- [~ForkManager](#) ()
ForkManager destructor.

Static Public Attributes

- static std::list< [ForkManager](#) * > [FORKMANAGERS](#)
List of all instantiated ForkManagers.

Additional Inherited Members

E.38.1 Detailed Description

[Manager](#) implementation that starts Workers by calling fork(2).

E.38.2 Constructor & Destructor Documentation

E.38.2.1 BiometricEvaluation::Process::ForkManager::ForkManager ()

[ForkManager](#) constructor.

E.38.3 Member Function Documentation

E.38.3.1 tr1::shared_ptr<WorkerController> BiometricEvaluation::Process::ForkManager::addWorker (tr1::shared_ptr< Worker > worker) [virtual]

Adds a [Worker](#) to be managed by this [Manager](#).

Parameters

<i>worker</i>	A Worker instance to run.
---------------	---

Returns

shared_ptr to worker.

Implements [BiometricEvaluation::Process::Manager](#).

E.38.3.2 void BiometricEvaluation::Process::ForkManager::startWorkers (bool wait = true, bool communicate = false) throw (Error::ObjectExists, Error::StrategyError) [virtual]

Begin [Worker](#)'s work.

Parameters

<i>in</i>	<i>wait</i>	Whether or not to wait for all Workers to return before returning.
<i>in</i>	<i>communicate</i>	Whether or not to enable communication among the Workers and Managers.

Exceptions

<i>Error::ObjectExists</i>	At least one Worker is already working.
<i>Error::StrategyError</i>	Problem forking.

Implements [BiometricEvaluation::Process::Manager](#).

E.38.3.3 `void BiometricEvaluation::Process::ForkManager::startWorker (tr1::shared_ptr< WorkerController > worker, bool wait = true, bool communicate = false) throw (Error::ObjectExists, Error::StrategyError) [virtual]`

Start a worker.

Parameters

	<i>worker</i>	Pointer to a WorkerController that is being managed by this Manager instance.
	<i>wait</i>	Whether or not to wait for this Worker to exit before returning control to the caller.
<i>in</i>	<i>communicate</i>	Whether or not to enable communication among the Workers and Managers.

Exceptions

<i>Error::ObjectExists</i>	worker is already working.
<i>Error::StrategyError</i>	worker is not managed by this Manager instance.

Implements [BiometricEvaluation::Process::Manager](#).

E.38.3.4 `int32_t BiometricEvaluation::Process::ForkManager::stopWorker (tr1::shared_ptr< WorkerController > workerController) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Ask [Worker](#) to exit.

Sends SIGUSR1 to the [Worker](#), which [ForkManager](#) will handle automatically.

Parameters

<i>worker-Controller</i>	Pointer to the ForkWorkerController that should be stopped.
--------------------------	---

Returns

Exit status of worker.

Exceptions

<i>Error::ObjectDoesNotExist</i>	worker is not working.
<i>Error::StrategyError</i>	Problem sending the signal.

Attention

Do not call [stopWorker\(\)](#) when communication is enabled unless you will be finished with communication for all Workers at that point. This creates a race condition for reads()/writes() when the [Worker](#) exits.

Implements [BiometricEvaluation::Process::Manager](#).

E.38.3.5 void BiometricEvaluation::Process::ForkManager::broadcastSignal (int *signo*)

Send a POSIX signal to all workers.

Parameters

in	<i>signo</i>	The signal to send.
----	--------------	---------------------

E.38.3.6 bool BiometricEvaluation::Process::ForkManager::responsibleFor (const pid_t *pid*) const

Obtain whether or not this [ForkManager](#) is responsible for a particular PID.

Parameters

in	<i>pid</i>	PID in question
----	------------	-----------------

Returns

true if this [ForkManager](#) spawned pid, false otherwise.

E.38.3.7 void BiometricEvaluation::Process::ForkManager::setNotWorking (const pid_t *pid*)

Set Status.isWorking for PID to false.

Parameters

in	<i>pid</i>	PID whose inWorking flag should be set to false
----	------------	---

Exceptions

Error::ObjectDoesNotExist	PID not under this manager's control.
---	---------------------------------------

E.38.3.8 bool BiometricEvaluation::Process::ForkManager::getIsWorkingStatus (const pid_t *pid*) const

Get Status.isWorking for PID.

Parameters

in	<i>pid</i>	PID whose inWorking flag should be queried
----	------------	--

Exceptions

<i>Error::ObjectDoesNotExist</i>	PID not under this manager's control.
----------------------------------	---------------------------------------

E.38.4 Member Data Documentation

E.38.4.1 `std::list<ForkManager*> BiometricEvaluation::Process::ForkManager::FORKMANAGERS`
[static]

List of all instantiated ForkManagers.


This is not a list of managed pointers to ForkManagers. If it was, the smart pointer's destructor would attempt to delete the object being pointed to at program termination, which is ultimately sometime after the destructor of the [ForkManager](#) itself was called.

E.39 BiometricEvaluation::Process::ForkWorkerController Class Reference

Wrapper of a [Worker](#) returned from a [Process::ForkManager](#).

```
#include <be_process_forkmanager.h>
```

Inheritance diagram for BiometricEvaluation::Process::ForkWorkerController:



Public Member Functions

- `bool isWorking () const`
Obtain whether or not [Worker](#) is working.
- `void reset () throw (Error::ObjectExists)`
Reuse the [Worker](#).
- `pid_t getPID () const`
Obtain the PID of this process this instance represents.
- `~ForkWorkerController ()`
[ForkWorkerController](#) destructor.

Static Public Member Functions

- `static void _stop (int signal)`
Tell `_staticWorker` to stop.

Friends

- void [ForkManager::startWorkers](#) (bool wait, bool communicate) throw (Error::ObjectExists, Error::StrategyError)
Begin [Worker](#)'s work.
- void [ForkManager::startWorker](#) (tr1::shared_ptr< [WorkerController](#) > worker, bool wait, bool communicate) throw (Error::ObjectExists, Error::StrategyError)
Restart a completed [Worker](#).
- int32_t [ForkManager::stopWorker](#) (tr1::shared_ptr< [WorkerController](#) > workerController) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Ask [Worker](#) to exit.
- tr1::shared_ptr< [WorkerController](#) > [ForkManager::addWorker](#) (tr1::shared_ptr< [Worker](#) > worker)
Adds a [Worker](#) to be managed by this [Manager](#).

Additional Inherited Members

E.39.1 Detailed Description

Wrapper of a [Worker](#) returned from a [Process::ForkManager](#).

E.39.2 Member Function Documentation

E.39.2.1 bool BiometricEvaluation::Process::ForkWorkerController::isWorking () const [virtual]

Obtain whether or not [Worker](#) is working.

Returns

Whether or not the [Worker](#) is working.

Implements [BiometricEvaluation::Process::WorkerController](#).

E.39.2.2 void BiometricEvaluation::Process::ForkWorkerController::reset () throw (Error::ObjectExists) [virtual]

Reuse the [Worker](#).

Exceptions

Error::ObjectExists	The previously started Worker is still running.
-------------------------------------	---

Reimplemented from [BiometricEvaluation::Process::WorkerController](#).

E.39.2.3 pid_t BiometricEvaluation::Process::ForkWorkerController::getPID () const

Obtain the PID of this process this instance represents.

Returns

pid of the process this instance represents.

Note

Call `isRunning()` before doing anything with the PID returned from this function.

E.39.2.4 static void BiometricEvaluation::Process::ForkWorkerController::_stop (int *signal*) [static]

Tell `_staticWorker` to stop.

Called by the child process instance when SIGUSR1 is received.

Parameters

<i>signal</i>	The signal caught that prompted this function to be called (SIGUSR1).
---------------	---

E.39.3 Friends And Related Function Documentation**E.39.3.1 void ForkManager::startWorkers (bool *wait*, bool *communicate*) throw (Error::ObjectExists, Error::StrategyError) [friend]**

Begin [Worker](#)'s work.

Parameters

in	<i>wait</i>	Whether or not to wait for all Workers to return before returning.
in	<i>communicate</i>	Whether or not to enable communication among the Workers and Managers.

Exceptions

Error::ObjectExists	One or more of the Workers is already working.
Error::StrategyError	Problem forking.

E.39.3.2 void ForkManager::startWorker (tr1::shared_ptr< WorkerController > *worker*, bool *wait*, bool *communicate*) throw (Error::ObjectExists, Error::StrategyError) [friend]

Restart a completed [Worker](#).

Parameters

	<i>worker</i>	Pointer to a WorkerController that is being managed by this Manager instance.
	<i>wait</i>	Whether or not to wait for this Worker to exit before returning control to the caller.
in	<i>communicate</i>	Whether or not to enable communication among the Workers and Managers.

Exceptions

<i>Error::ObjectExists</i>	worker is already working.
<i>Error::StrategyError</i>	worker is not managed by this Manager instance.

E.39.3.3 `int32_t ForkManager::stopWorker (tr1::shared_ptr< WorkerController > workerController)
throw (Error::ObjectDoesNotExist, Error::StrategyError) [friend]`

Ask [Worker](#) to exit.

Sends SIGUSR1 to the [Worker](#), which [ForkManager](#) will handle automatically.

Parameters

<i>worker-Controller</i>	Pointer to the ForkWorkerController that should be stopped.
--------------------------	---

Returns

Exit status of worker.

Exceptions

<i>Error::ObjectDoesNotExist</i>	worker is not working.
<i>Error::StrategyError</i>	Problem sending the signal.

E.39.3.4 `tr1::shared_ptr<WorkerController> ForkManager::addWorker (tr1::shared_ptr< Worker > worker) [friend]`

Adds a [Worker](#) to be managed by this [Manager](#).

Parameters

<i>worker</i>	A Worker instance to run.
---------------	---

Returns


shared_ptr to worker.

E.40 BiometricEvaluation::IO::GZip Class Reference

[Compressor](#) for gzip compression from zlib.

```
#include <be_io_gzip.h>
```

Inheritance diagram for BiometricEvaluation::IO::GZip:



Public Member Functions

- [Memory::uint8Array compress](#) (const uint8_t *const uncompressedData, uint64_t uncompressedDataSize) const throw (Error::StrategyError)
Compress a buffer.
- [Memory::uint8Array compress](#) (const [Memory::uint8Array](#) &uncompressedData) const throw (Error::StrategyError)
Compress a buffer.
- void [compress](#) (const uint8_t *const uncompressedData, uint64_t uncompressedDataSize, const string &outputFile) const throw (Error::ObjectExists, Error::StrategyError)
Compress a buffer.
- void [compress](#) (const [Memory::uint8Array](#) &uncompressedData, const string &outputFile) const throw (Error::ObjectExists, Error::StrategyError)
Compress a buffer.
- [Memory::uint8Array compress](#) (const string &inputFile) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
Compress a file.
- void [compress](#) (const string &inputFile, const string &outputFile) const throw (Error::ObjectDoesNotExist, Error::ObjectExists, Error::StrategyError)
Compress a file.
- [Memory::uint8Array decompress](#) (const uint8_t *const compressedData, uint64_t compressedDataSize) const throw (Error::StrategyError)
Decompress a compressed buffer.
- [Memory::uint8Array decompress](#) (const [Memory::uint8Array](#) &compressedData) const throw (Error::StrategyError)
Decompress a compressed buffer.
- [Memory::uint8Array decompress](#) (const string &input) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
Decompress a compressed buffer into a file.
- void [decompress](#) (const string &inputFile, const string &outputFile) const throw (Error::ObjectDoesNotExist, Error::ObjectExists, Error::StrategyError)
Decompress a file.
- void [decompress](#) (const uint8_t *const compressedData, const uint64_t compressedDataSize, const string &outputFile) const throw (Error::ObjectExists, Error::StrategyError)
Decompress a file.
- void [decompress](#) (const [Memory::uint8Array](#) &compressedData, const string &outputFile) const throw (Error::ObjectExists, Error::StrategyError)
Decompress a file.

Static Public Attributes

- static const string [COMPRESSION_LEVEL](#)
- static const string [COMPRESSION_STRATEGY](#)
- static const string [COMPRESSION_METHOD](#)
- static const string [INPUT_DATA_TYPE](#)
- static const string [WINDOW_BITS](#)
- static const string [MEMORY_LEVEL](#)
- static const string [CHUNK_SIZE](#)

Additional Inherited Members

E.40.1 Detailed Description

[Compressor](#) for gzip compression from zlib.

E.40.2 Member Function Documentation

E.40.2.1 `Memory::uint8Array BiometricEvaluation::IO::GZip::compress (const uint8_t *const uncompressedData, uint64_t uncompressedDataSize) const throw (Error::StrategyError) [virtual]`

Compress a buffer.

Parameters

<i>uncompressed-Data</i>	Uncompressed data buffer to compress.
<i>uncompressed-DataSize</i>	Size of uncompressedData.

Returns

Compressed buffer.

Exceptions

Error::StrategyError	Error in compression unit.
--------------------------------------	--

Implements [BiometricEvaluation::IO::Compressor](#).

E.40.2.2 `Memory::uint8Array BiometricEvaluation::IO::GZip::compress (const Memory::uint8Array &uncompressedData) const throw (Error::StrategyError) [virtual]`

Compress a buffer.

Parameters

<i>uncompressed-Data</i>	Uncompressed data buffer to compress.
--------------------------	---------------------------------------

Returns

Compressed buffer.

Exceptions

<i>Error::StrategyError</i>	Error in decompression unit.
---	------------------------------

Implements [BiometricEvaluation::IO::Compressor](#).

E.40.2.3 void BiometricEvaluation::IO::GZip::compress (const uint8_t *const *uncompressedData*, uint64_t *uncompressedDataSize*, const string & *outputFile*) const throw (Error::ObjectExists, Error::StrategyError) [virtual]

Compress a buffer.

Parameters

<i>uncompressed-Data</i>	Uncompressed data buffer to compress.
<i>uncompressed-DataSize</i>	Size of uncompressedData.
<i>outputFile</i>	Location to save compressed file.

Exceptions

<i>Error::ObjectExists</i>	Output file already exists.
<i>Error::StrategyError</i>	Error in compression unit.

Implements [BiometricEvaluation::IO::Compressor](#).

E.40.2.4 void BiometricEvaluation::IO::GZip::compress (const Memory::uint8Array & *uncompressedData*, const string & *outputFile*) const throw (Error::ObjectExists, Error::StrategyError) [virtual]

Compress a buffer.

Parameters

<i>uncompressed-Data</i>	Uncompressed data buffer to compress.
<i>outputFile</i>	Location to save compressed file.

Exceptions

<i>Error::ObjectExists</i>	Output file already exists.
<i>Error::StrategyError</i>	Error in decompression unit.

Implements [BiometricEvaluation::IO::Compressor](#).

E.40.2.5 `Memory::uint8Array BiometricEvaluation::IO::GZip::compress (const string & inputFile) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Compress a file.

Parameters

<i>inputFile</i>	Path to file to compress.
------------------	---------------------------

Returns

Compressed buffer.

Exceptions

<i>Error::ObjectDoesNotExist</i>	Input file does not exist.
<i>Error::StrategyError</i>	Error in decompression unit.

Implements [BiometricEvaluation::IO::Compressor](#).

E.40.2.6 `void BiometricEvaluation::IO::GZip::compress (const string & inputFile, const string & outputFile) const throw (Error::ObjectDoesNotExist, Error::ObjectExists, Error::StrategyError) [virtual]`

Compress a file.

Parameters

<i>inputFile</i>	Path to file to compress.
<i>outputFile</i>	Path to location where compressed version will be saved.

Exceptions

<i>Error::ObjectDoesNotExist</i>	Input file does not exist.
<i>Error::ObjectExists</i>	Output file already exists.
<i>Error::StrategyError</i>	Error in decompression unit.

Implements [BiometricEvaluation::IO::Compressor](#).

E.40.2.7 `Memory::uint8Array BiometricEvaluation::IO::GZip::decompress (const uint8_t *const compressedData, uint64_t compressedDataSize) const throw (Error::StrategyError)` [virtual]

Decompress a compressed buffer.

Parameters

<i>compressed-Data</i>	Compressed data buffer to decompress.
<i>compressed-DataSize</i>	Size of compressedData.

Returns

Decompressed buffer.

Exceptions

<i>Error::StrategyError</i>	Error in compression unit.
---	----------------------------

Implements [BiometricEvaluation::IO::Compressor](#).

E.40.2.8 `Memory::uint8Array BiometricEvaluation::IO::GZip::decompress (const Memory::uint8Array & compressedData) const throw (Error::StrategyError)` [virtual]

Decompress a compressed buffer.

Parameters

<i>compressed-Data</i>	Compressed data buffer to decompress.
------------------------	---------------------------------------

Returns

Decompressed buffer.

Exceptions

<i>Error::StrategyError</i>	Error in decompression unit.
---	------------------------------

Implements [BiometricEvaluation::IO::Compressor](#).

E.40.2.9 `Memory::uint8Array BiometricEvaluation::IO::GZip::decompress (const string & inputFile) const throw (Error::ObjectDoesNotExist, Error::StrategyError)` [virtual]

Decompress a compressed buffer into a file.

Parameters

<i>inputFile</i>	Location to save compressed file.
------------------	-----------------------------------

Returns

Decompressed buffer.

Exceptions

<i>Error::StrategyError</i>	Error in decompression unit.
<i>Error::ObjectDoesNotExist</i>	Output file already exists.

Implements [BiometricEvaluation::IO::Compressor](#).

E.40.2.10 void BiometricEvaluation::IO::GZip::decompress (const string & *inputFile*, const string & *outputFile*) const throw (Error::ObjectDoesNotExist, Error::ObjectExists, Error::StrategyError) [virtual]

Decompress a file.

Parameters

<i>inputFile</i>	Path to file to decompress.
<i>outputFile</i>	Path to location where decompressed version will be saved.

Exceptions

<i>Error::ObjectDoesNotExist</i>	Input file does not exist.
<i>Error::ObjectExists</i>	Output file already exists.
<i>Error::StrategyError</i>	Error in compression unit.

Implements [BiometricEvaluation::IO::Compressor](#).

E.40.2.11 void BiometricEvaluation::IO::GZip::decompress (const uint8_t *const *compressedData*, const uint64_t *compressedDataSize*, const string & *outputFile*) const throw (Error::ObjectExists, Error::StrategyError) [virtual]

Decompress a file.

Parameters

<i>compressed-Data</i>	Compressed data buffer to decompress.
<i>compressed-DataSize</i>	Size of compressedData.
<i>outputFile</i>	Path to location where decompressed version will be saved.

Exceptions

<i>Error::ObjectExists</i>	Output file already exists.
<i>Error::StrategyError</i>	Error in compression unit.

Implements [BiometricEvaluation::IO::Compressor](#).

E.40.2.12 `void BiometricEvaluation::IO::GZip::decompress (const Memory::uint8Array & compressedData,
const string & outputFile) const throw (Error::ObjectExists, Error::StrategyError)
[virtual]`

Decompress a file.

Parameters

<i>compressed-Data</i>	Compressed data buffer to decompress.
<i>outputFile</i>	Path to location where decompressed version will be saved.

Exceptions

<i>Error::ObjectExists</i>	Output file already exists.
<i>Error::StrategyError</i>	Error in compression unit.

Implements [BiometricEvaluation::IO::Compressor](#).

E.40.3 Member Data Documentation

E.40.3.1 `const string BiometricEvaluation::IO::GZip::COMPRESSION_LEVEL` [static]

How thorough the compression should be

E.40.3.2 `const string BiometricEvaluation::IO::GZip::COMPRESSION_STRATEGY` [static]

Which underlying algorithm to use

E.40.3.3 `const string BiometricEvaluation::IO::GZip::COMPRESSION_METHOD` [static]

Which underlying method in the compressor

E.40.3.4 `const string BiometricEvaluation::IO::GZip::INPUT_DATA_TYPE` [static]

The type of data being compressed

E.40.3.5 `const string BiometricEvaluation::IO::GZip::WINDOW_BITS` [static]

Window size

E.40.3.6 `const string BiometricEvaluation::IO::GZip::MEMORY_LEVEL` [static]

How much memory for internal compression state

E.40.3.7 `const string BiometricEvaluation::IO::GZip::CHUNK_SIZE` [static]


How many bytes to work at a time

E.41 BiometricEvaluation::Image::Image Class Reference

Represent attributes common to all images.

```
#include <be_image_image.h>
```

Inheritance diagram for BiometricEvaluation::Image::Image:



Public Member Functions

- **Image** (const uint8_t *data, const uint64_t size, const [Size](#) dimensions, const uint32_t depth, const [Resolution](#) resolution, const CompressionAlgorithm::Kind compression) throw (Error::DataError, Error::StrategyError)
Parent constructor for all [Image](#) classes.
- **Image** (const uint8_t *data, const uint64_t size, const CompressionAlgorithm::Kind compression) throw (Error::DataError, Error::StrategyError)
Parent constructor for all [Image](#) classes.
- CompressionAlgorithm::Kind **getCompressionAlgorithm** () const
Accessor for the [CompressionAlgorithm](#) of the image.
- [Resolution](#) **getResolution** () const
Accessor for the resolution of the image.
- [Memory::AutoArray](#)< uint8_t > **getData** () const
Accessor for the image data. The data returned is likely encoded in a specialized format.
- virtual [Memory::AutoArray](#)< uint8_t > **getRawData** () const =0 throw (Error::DataError)
Accessor for the raw image data. The data returned should not be compressed or encoded.
- virtual [Memory::AutoArray](#)< uint8_t > **getRawGrayscaleData** (uint8_t depth=8) const =0 throw (Error::DataError, Error::ParameterError)
Accessor for decompressed data in grayscale.
- [Size](#) **getDimensions** () const
Accessor for the dimensions of the image in pixels.
- uint32_t **getDepth** () const
Accessor for the color depth of the image in bits.

Static Public Member Functions

- static uint64_t [valueInColorspace](#) (uint64_t color, uint64_t maxColorValue, uint8_t depth)
Calculate an equivalent color value for a color in an alternate colorspace.
- static tr1::shared_ptr< [Image](#) > [openImage](#) (const uint8_t *data, const uint64_t size) throw (Error::DataError, Error::StrategyError)
Determine the image type of a buffer of image data and create an [Image](#) object.
- static tr1::shared_ptr< [Image](#) > [openImage](#) (const [Memory::uint8Array](#) &data) throw (Error::DataError, Error::StrategyError)
Determine the image type of a buffer of image data and create an [Image](#) object.
- static tr1::shared_ptr< [Image](#) > [openImage](#) (const string &path) throw (Error::DataError, Error::ObjectDoesNotExist, Error::StrategyError)
Determine the image type of an image file and create an [Image](#) object.
- static CompressionAlgorithm::Kind [getCompressionAlgorithm](#) (const uint8_t *data, const uint64_t size)
Determine the compression algorithm of a buffer of image data.
- static CompressionAlgorithm::Kind [getCompressionAlgorithm](#) (const [Memory::uint8Array](#) &data)
Determine the compression algorithm of a buffer of image data.
- static CompressionAlgorithm::Kind [getCompressionAlgorithm](#) (const string &path) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Determine the compression algorithm of a file.

Static Public Attributes

- static const uint32_t [bitsPerComponent](#) = 8

Protected Member Functions

- void [setResolution](#) (const [Resolution](#) resolution)
Mutator for the resolution of the image .
- void [setDimensions](#) (const [Size](#) dimensions)
Mutator for the dimensions of the image in pixels.
- void [setDepth](#) (const uint32_t depth)
Mutator for the color depth of the image in bits.

Protected Attributes

- [Memory::AutoArray](#)< uint8_t > [_raw_data](#)

E.41.1 Detailed Description

Represent attributes common to all images.

Images are represented by their size, depth, and resolution on the X and Y axes. The image data can be of any format, raw, [JPEG](#), etc. Implementations of this abstraction provide the [getRawData\(\)](#) method to convert image data to 'raw' format.

[Image](#) resolution is in pixels per centimeter, and the coordinate system has the origin at the upper left of the image.

E.41.2 Constructor & Destructor Documentation

E.41.2.1 `BiometricEvaluation::Image::Image (const uint8_t * data, const uint64_t size, const Size dimensions, const uint32_t depth, const Resolution resolution, const CompressionAlgorithm::Kind compression) throw (Error::DataError, Error::StrategyError)`

Parent constructor for all [Image](#) classes.

Parameters

in	<i>data</i>	The image data.
in	<i>size</i>	The size of the image data, in bytes.
in	<i>dimensions</i>	The width and height of the image in pixels.
in	<i>depth</i>	The image depth, in bits-per-pixel.
in	<i>resolution</i>	The resolution of the image
in	<i>compression</i>	The CompressionAlgorithm of data.

Exceptions

Error::StrategyError	Error manipulating data.
Error::StrategyError	Error while creating Image .

E.41.2.2 `BiometricEvaluation::Image::Image (const uint8_t * data, const uint64_t size, const CompressionAlgorithm::Kind compression) throw (Error::DataError, Error::StrategyError)`

Parent constructor for all [Image](#) classes.

Parameters

in	<i>data</i>	The image data.
in	<i>size</i>	The size of the image data, in bytes.
in	<i>compression</i>	The CompressionAlgorithm of data.

Exceptions

Error::DataError	Error manipulating data.
Error::StrategyError	Error while creating Image .

E.41.3 Member Function Documentation

E.41.3.1 `CompressionAlgorithm::Kind BiometricEvaluation::Image::Image::getCompressionAlgorithm () const`

Accessor for the [CompressionAlgorithm](#) of the image.

Returns

Type of compression used on the data that will be returned from [getData\(\)](#).

E.41.3.2 Resolution `BiometricEvaluation::Image::Image::getResolution () const`

Accessor for the resolution of the image.

Returns

[Resolution](#) struct

E.41.3.3 Memory::AutoArray<uint8_t> `BiometricEvaluation::Image::Image::getData () const`

Accessor for the image data. The data returned is likely encoded in a specialized format.

Returns

[Image](#) data.

E.41.3.4 virtual Memory::AutoArray<uint8_t> `BiometricEvaluation::Image::Image::getRawData () const` throw (`Error::DataError`) [pure virtual]

Accessor for the raw image data. The data returned should not be compressed or encoded.

Returns

[Raw](#) image data.

Exceptions

Error::DataError	Error decompressing image data.
----------------------------------	---

Implemented in [BiometricEvaluation::Image::NetPBM](#), [BiometricEvaluation::Image::JPEG](#), [BiometricEvaluation::Image::JPEG2000](#), [BiometricEvaluation::Image::PNG](#), [BiometricEvaluation::Image::JPEGL](#), [BiometricEvaluation::Image::Raw](#), and [BiometricEvaluation::Image::WSQ](#).

E.41.3.5 virtual Memory::AutoArray<uint8_t> `BiometricEvaluation::Image::Image::getRawGrayscaleData (uint8_t depth = 8) const` throw (`Error::DataError`, `Error::ParameterError`) [pure virtual]

Accessor for decompressed data in grayscale.

Parameters

<i>depth</i>	The desired bit depth of the resulting raw image. This value may either be 8 or 1.
--------------	--

Returns

[Raw](#) image buffer.

Exceptions

Error::DataError	Error decompressing image data.
Error::ParameterError	Invalid value for depth.

Note

This method does not save a cached copy of the decompressed image because the bit depth of the image can be changed between calls.

This method always returns an image that uses 8 bits to represent a single pixel. depth adjusts the number of pixels used to determine the color of the pixel in the 8 bit container, currently 1 (2 gray levels) or 8 (256 gray levels).

Implemented in [BiometricEvaluation::Image::NetPBM](#), [BiometricEvaluation::Image::JPEG2000](#), [BiometricEvaluation::Image::PNG](#), [BiometricEvaluation::Image::JPEG](#), [BiometricEvaluation::Image::Raw](#), [BiometricEvaluation::Image::WSQ](#), and [BiometricEvaluation::Image::JPEGL](#).

E.41.3.6 Size [BiometricEvaluation::Image::Image::getDimensions](#) () const

Accessor for the dimensions of the image in pixels.

Returns

[Coordinate](#) object containing dimensions in pixels.

E.41.3.7 `uint32_t` [BiometricEvaluation::Image::Image::getDepth](#) () const

Accessor for the color depth of the image in bits.

Returns

The color depth of the image (bit).

E.41.3.8 `static uint64_t` [BiometricEvaluation::Image::Image::valueInColorspace](#) (`uint64_t color`, `uint64_t maxColorValue`, `uint8_t depth`) `[static]`

Calculate an equivalent color value for a color in an alternate colorspace.

Parameters

<i>color</i>	Value for color in original colorspace.
<i>maxColorValue</i>	Maximum value for colors in original colorspace.
<i>depth</i>	Desired bit-depth of the new colorspace.

Returns

A value equivalent to color in depth-bit space.

E.41.3.9 `static tr1::shared_ptr<Image> BiometricEvaluation::Image::Image::openImage (const uint8_t * data, const uint64_t size) throw (Error::DataError, Error::StrategyError) [static]`

Determine the image type of a buffer of image data and create an [Image](#) object.

Parameters

in	<i>data</i>	The image data.
in	<i>size</i>	The size of the image data, in bytes.

Returns

[Image](#) representation of the input data buffer.

Exceptions

Error::DataError	Error manipulating data.
Error::StrategyError	Error while creating Image .

E.41.3.10 `static tr1::shared_ptr<Image> BiometricEvaluation::Image::Image::openImage (const Memory::uint8Array & data) throw (Error::DataError, Error::StrategyError) [static]`

Determine the image type of a buffer of image data and create an [Image](#) object.

Parameters

in	<i>data</i>	The image data.
----	-------------	-----------------

Returns

[Image](#) representation of the input data buffer.

Exceptions

Error::DataError	Error manipulating data.
Error::StrategyError	Error while creating Image .

E.41.3.11 `static tr1::shared_ptr<Image> BiometricEvaluation::Image::Image::openImage (const string & path) throw (Error::DataError, Error::ObjectDoesNotExist, Error::StrategyError) [static]`

Determine the image type of an image file and create an [Image](#) object.

Parameters

in	<i>path</i>	Path to image data.
----	-------------	---------------------

Returns

[Image](#) representation of the input data buffer.

Exceptions

Error::DataError	Error manipulating data.
Error::ObjectDoesNotExist	No file at specified path.
Error::StrategyError	Error while creating Image .

E.41.3.12 `static CompressionAlgorithm::Kind BiometricEvaluation::Image::Image::getCompressionAlgorithm (const uint8_t* data, const uint64_t size) [static]`

Determine the compression algorithm of a buffer of image data.

Parameters

in	<i>data</i>	The image data.
in	<i>size</i>	The size of the image data, in bytes.

Returns

Compression algorithm used in the buffer.

Attention

`CompressionAlgorithm::None` is returned if no compression algorithm known to the Biometric Evaluation [Framework](#) is found.

E.41.3.13 `static CompressionAlgorithm::Kind BiometricEvaluation::Image::Image::getCompressionAlgorithm (const Memory::uint8Array & data) [static]`

Determine the compression algorithm of a buffer of image data.

Parameters

in	<i>data</i>	The image data.
----	-------------	-----------------

Returns

Compression algorithm used in the buffer.

Attention

CompressionAlgorithm::None is returned if no compression algorithm known to the Biometric Evaluation Framework is found.

E.41.3.14 `static CompressionAlgorithm::Kind BiometricEvaluation::Image::Image::getCompressionAlgorithm (const string & path) throw (Error::ObjectDoesNotExist, Error::StrategyError) [static]`

Determine the compression algorithm of a file.

Parameters

in	<i>path</i>	Path to file.
----	-------------	---------------

Returns

Compression algorithm used in the file.

Exceptions

<i>Error::ObjectDoesNotExist</i>	path does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Attention

CompressionAlgorithm::None is returned if no compression algorithm known to the Biometric Evaluation Framework is found.

E.41.3.15 `void BiometricEvaluation::Image::Image::setResolution (const Resolution resolution) [protected]`

Mutator for the resolution of the image .

Parameters

in	<i>resolution</i>	Resolution struct.
----	-------------------	------------------------------------

E.41.3.16 `void BiometricEvaluation::Image::Image::setDimensions (const Size dimensions) [protected]`

Mutator for the dimensions of the image in pixels.

Parameters

in	<i>dimensions</i>	Dimensions of image (pixel).
----	-------------------	------------------------------

E.41.3.17 `void BiometricEvaluation::Image::Image::setDepth (const uint32_t depth)` [protected]

Mutator for the color depth of the image in bits.

Parameters

<i>in</i>	<i>depth</i>	The color depth of the image (bit).
-----------	--------------	-------------------------------------

E.41.4 Member Data Documentation

E.41.4.1 `const uint32_t BiometricEvaluation::Image::Image::bitsPerComponent = 8` [static]

Number of bits per color component

E.41.4.2 `Memory::AutoArray<uint8_t> BiometricEvaluation::Image::Image::_raw_data` [mutable], [protected]

[Raw](#) image data, populated on demand

E.42 BiometricEvaluation::Finger::Impression Class Reference

[Finger](#) and palm impression types.

```
#include <be_finger.h>
```

Public Types

- enum **Kind** {
LiveScanPlain = 0, **LiveScanRolled**, **NonLiveScanPlain**, **NonLiveScanRolled**,
LatentImpression, **LatentTracing**, **LatentPhoto**, **LatentLift**,
LiveScanVerticalSwipe, **LiveScanPalm**, **NonLiveScanPalm**, **LatentPalmImpression**,
LatentPalmTracing, **LatentPalmPhoto**, **LatentPalmLift**, **LiveScanOpticalContactPlain**,
LiveScanOpticalContactRolled, **LiveScanNonOpticalContactPlain**, **LiveScanNonOpticalContact-**
Rolled, **LiveScanOpticalContactlessPlain**,
LiveScanOpticalContactlessRolled, **LiveScanNonOpticalContactlessPlain**, **LiveScanNonOpticalContactless-**
Rolled, **Other**,
Unknown }

E.42.1 Detailed Description


[Finger](#) and palm impression types.

E.43 BiometricEvaluation::Feature::INCITSMinutiae Class Reference

A class to represent a set of minutiae in an ANSI/INCITS record.

```
#include <be_feature_incitsminutiae.h>
```

Inheritance diagram for BiometricEvaluation::Feature::INCITSMinutiae:



Public Member Functions

- MinutiaeFormat::Kind [getFormat](#) () const
Obtain the minutiae format kind.
- MinutiaPointSet [getMinutiaPoints](#) () const
Obtain the set of finger minutiae data points. The set may be empty.
- RidgeCountItemSet [getRidgeCountItems](#) () const
Obtain the set of ridge count data items. The set may be empty.
- CorePointSet [getCores](#) () const
Obtains the set of core positions. The set may be empty.
- DeltaPointSet [getDeltas](#) () const
Obtains the set of delta positions. The set may be empty.
- [INCITSMinutiae](#) (const MinutiaPointSet &mps, const RidgeCountItemSet &rcis, const CorePointSet &cps, const DeltaPointSet &dps)
Construct an INCITS [Minutiae](#) object from its components.
- [INCITSMinutiae](#) ()
Default constructor for an INCITS [Minutiae](#) object.
- void [setMinutiaPoints](#) (const MinutiaPointSet &mps)
Mutator for the minutiae point set.
- void [setRidgeCountItems](#) (const RidgeCountItemSet &rcis)
Mutator for the ridge count items.
- void [setCorePointSet](#) (const CorePointSet &cps)
Mutator for the set of core points.
- void [setDeltaPointSet](#) (const DeltaPointSet &dps)
Mutator for the set of delta points.

Static Public Attributes

- static const string **FMR_ANSI_SPEC_VERSION**
- static const string **FMR_ISO_SPEC_VERSION**
- static const string **FMR_ANSI07_SPEC_VERSION**
- static const uint8_t **FMR_SPEC_VERSION_LEN** = 4
- static const uint32_t **FED_HEADER_LENGTH** = 4
- static const uint32_t **FED_RCD_ITEM_LENGTH** = 3
- static const uint16_t **FMD_MINUTIA_TYPE_MASK** = 0xC000
- static const uint16_t **FMD_RESERVED_MASK** = 0xC000

- static const uint16_t **FMD_MINUTIA_TYPE_SHIFT** = 14
- static const uint16_t **FMD_RESERVED_SHIFT** = 14
- static const uint16_t **FMD_X_COORD_MASK** = 0x3FFF
- static const uint16_t **FMD_Y_COORD_MASK** = 0x3FFF
- static const uint16_t **FMD_ISO_COMPACT_MINUTIA_TYPE_MASK** = 0xC0
- static const uint16_t **FMD_ISO_COMPACT_MINUTIA_TYPE_SHIFT** = 6
- static const uint16_t **FMD_ISO_COMPACT_MINUTIA_ANGLE_MASK** = 0x3F
- static const uint16_t **FMD_MIN_MINUTIA_QUALITY** = 0
- static const uint16_t **FMD_MAX_MINUTIA_QUALITY** = 100
- static const uint16_t **FMD_UNKNOWN_MINUTIA_QUALITY** = 0
- static const uint16_t **FMD_MIN_MINUTIA_ANGLE** = 0
- static const uint16_t **FMD_MAX_MINUTIA_ANGLE** = 179
- static const uint16_t **FMD_MAX_MINUTIA_ISONC_ANGLE** = 255
- static const uint16_t **FMD_MAX_MINUTIA_ISOCC_ANGLE** = 63
- static const uint16_t **FMD_ANSI_ANGLE_UNIT** = 2
- static const uint16_t **FMD_ISO_ANGLE_UNIT**
- static const uint16_t **FMD_ISOCC_ANGLE_UNIT**
- static const uint16_t **FMD_MINUTIA_TYPE_OTHER** = 0
- static const uint16_t **FMD_MINUTIA_TYPE_RIDGE_ENDING** = 1
- static const uint16_t **FMD_MINUTIA_TYPE_BIFURCATION** = 2
- static const uint16_t **FMR_MIN_FINGER_QUALITY** = 0
- static const uint16_t **FMR_MAX_FINGER_QUALITY** = 100
- static const uint16_t **ISO_UNKNOWN_FINGER_QUALITY** = 0
- static const uint16_t **FED_RESERVED** = 0x0000
- static const uint16_t **FED_RIDGE_COUNT** = 0x0001
- static const uint16_t **FED_CORE_AND_DELTA** = 0x0002
- static const uint16_t **RCE_NONSPECIFIC** = 0x00
- static const uint16_t **RCE_FOUR_NEIGHBOR** = 0x01
- static const uint16_t **RCE_EIGHT_NEIGHBOR** = 0x02
- static const uint16_t **CORE_TYPE_NONANGULAR** = 0x00
- static const uint16_t **CORE_TYPE_ANGULAR** = 0x01
- static const uint16_t **DELTA_TYPE_NONANGULAR** = 0x00
- static const uint16_t **DELTA_TYPE_ANGULAR** = 0x01

E.43.1 Detailed Description

A class to represent a set of minutiae in an ANSI/INCITS record.

The base INCTISMinutiae class is responsible for reading minutiae data points and extended data. Each minutiae point, ridge count item, core, and delta is represented in the native ANSI/INCITS format. Objects of this base class cannot be instantiated, but rather derived classes are used to represent minutiae data taken from the INCITS-derived record formats.

E.43.2 Constructor & Destructor Documentation

E.43.2.1 BiometricEvaluation::Feature::INCITSMinutiae::INCITSMinutiae (const MinutiaPointSet & *mps*, const RidgeCountItemSet & *rcis*, const CorePointSet & *cps*, const DeltaPointSet & *dps*)

Construct an INCITS [Minutiae](#) object from its components.

The buffer index must be set to the location in the buffer to start reading minutiae data points and extended data.

Parameters

in	<i>mps</i>	The set of minutiae points.
in	<i>rcis</i>	The set of ridge count items.
in	<i>cps</i>	The set of core points.
in	<i>dps</i>	The set of delta points.

E.43.3 Member Function Documentation

E.43.3.1 void BiometricEvaluation::Feature::INCITSMinutiae::setMinutiaPoints (const MinutiaPointSet & *mps*)

Mutator for the minutiae point set.

Parameters

in	<i>mps</i>	The minutiae points.
----	------------	----------------------

E.43.3.2 void BiometricEvaluation::Feature::INCITSMinutiae::setRidgeCountItems (const RidgeCountItemSet & *rcis*)

Mutator for the ridge count items.

Parameters

in	<i>rcis</i>	The set of ridge count items.
----	-------------	-------------------------------

E.43.3.3 void BiometricEvaluation::Feature::INCITSMinutiae::setCorePointSet (const CorePointSet & *cps*)

Mutator for the set of core points.

Parameters

in	<i>cps</i>	The set of core points.
----	------------	-------------------------

E.43.3.4 void BiometricEvaluation::Feature::INCITSMinutiae::setDeltaPointSet (const DeltaPointSet & *dps*)

Mutator for the set of delta points.

Parameters


in	dps	The set of delta point items.
----	-----	-------------------------------

E.44 BiometricEvaluation::Finger::INCITSView Class Reference

A class to represent single finger view and derived information.

```
#include <be_finger_incitsview.h>
```

Inheritance diagram for BiometricEvaluation::Finger::INCITSView:



Public Member Functions

- [Feature::INCITSMinutiae](#) [getMinutiaeData](#) () const
Obtain the set of minutiae records.
- [Finger::Position::Kind](#) [getPosition](#) () const
Obtain the finger position.
- [Finger::Impression::Kind](#) [getImpressionType](#) () const
Obtain the finger impression code.
- [uint32_t](#) [getQuality](#) () const
Obtain the finger quality value.
- [uint16_t](#) [getCaptureEquipmentID](#) () const
Obtain the capture equipment identifier.
- [bool](#) [isAppendixFCompliant](#) () const
Obtain the capture equipment compliance indicator for 'Appendix F'.
- [tr1::shared_ptr< Image::Image >](#) [getImage](#) () const
Obtain the image used for the finger view.
- [Image::Size](#) [getImageSize](#) () const
Obtain the image size.
- [Image::Resolution](#) [getImageResolution](#) () const
Obtain the image resolution.
- [uint32_t](#) [getImageDepth](#) () const
Obtain the image depth.
- [Image::CompressionAlgorithm::Kind](#) [getCompressionAlgorithm](#) () const
Obtain the compression algorithm used on the image.
- [Image::Resolution](#) [getScanResolution](#) () const
Obtain the image scan resolution.

Static Public Member Functions

- static Finger::Position::Kind [convertPosition](#) (int incitsFGP) throw (Error::DataError)
Convert a finger position code from an INCITS finger record to the common code.
- static Finger::Impression::Kind [convertImpression](#) (int incitsIMP) throw (Error::DataError)
Convert a impression type code from an INCITS finger record to the common code.

Static Public Attributes

- static const uint32_t **FMR_ANSI2004_STANDARD** = 1
- static const uint32_t **FMR_ISO2005_STANDARD** = 2
- static const uint32_t **FMR_ANSI2007_STANDARD** = 3
- static const string **FMR_BASE_FORMAT_ID**
- static const uint32_t **FMR_SPEC_VERSION_LEN** = 4
- static const string **FMR_BASE_SPEC_VERSION**
- static const string **FMR_ANSI2007_SPEC_VERSION**
- static const uint16_t **FMR_HDR_SCANNER_ID_MASK** = 0x0FFF
- static const uint16_t **FMR_HDR_COMPLIANCE_MASK** = 0xF000
- static const uint8_t **FMR_HDR_COMPLIANCE_SHIFT** = 12
- static const uint16_t **FMR_HDR_APPENDIX_F_MASK** = 0x0008
- static const uint8_t **FVMR_VIEW_NUMBER_MASK** = 0xF0
- static const uint8_t **FVMR_VIEW_NUMBER_SHIFT** = 4
- static const uint8_t **FVMR_IMPRESSION_MASK** = 0x0F

Protected Member Functions

- [INCITSView](#) (const std::string &fmrFilename, const std::string &firFilename, const uint32_t viewNumber) throw (Error::DataError, Error::FileError)
Construct the common components of an INCITS finger view from records contained in files.
- [INCITSView](#) (const [Memory::uint8Array](#) &fmrBuffer, const [Memory::uint8Array](#) &firBuffer, const uint32_t viewNumber) throw (Error::DataError)
Construct an INCITS finger view from records contained in buffers.
- [Memory::uint8Array](#) const & [getFMRData](#) () const
Obtain a reference to the finger minutiae record data buffer.
- [Memory::uint8Array](#) const & [getFIRData](#) () const
Obtain a reference to the finger image record data buffer.
- void [setMinutiaeData](#) (const [Feature::INCITSMinutiae](#) &fmd)
Mutator for the [Feature::INCITSMinutiae](#) item.
- void [setPosition](#) (const Finger::Position::Kind &position)
Mutator for the position.
- void [setImpressionType](#) (const Finger::Impression::Kind &impression)
Mutator for the impression type.
- void [setQuality](#) (uint32_t quality)
Mutator for the finger quality value.
- void [setViewNumber](#) (uint32_t viewNumber)
Mutator for the finger view number.

- void [setCaptureEquipmentID](#) (uint16_t id)
Mutator for the equipment ID.
- void [setCBEFFProductIDs](#) (uint16_t owner, uint16_t type)
Mutator for the CBEFF Product ID owner and type.
- void [setAppendixFCompliance](#) (bool flag)
Mutator for the Appendix F compliance indicator.
- void [setImageSize](#) (const [Image::Size](#) &imageSize)
Mutator for the image size.
- void [setImageResolution](#) (const [Image::Resolution](#) &imageResolution)
Mutator for the image resolution.
- void [setScanResolution](#) (const [Image::Resolution](#) &scanResolution)
Mutator for the image scan resolution.
- void [setImageData](#) (const [Memory::uint8Array](#) &imageData)
Mutator for the image data.
- void [readFMRHeader](#) ([Memory::IndexedBuffer](#) &buf, const uint32_t formatStandard) throw (Error::ParameterError, Error::DataError)
Read the common finger minutiae record header from an INCITS record.
- void [readFVMR](#) ([Memory::IndexedBuffer](#) &buf) throw (Error::DataError)
Read the common finger view record information from an INCITS record.
- virtual Feature::MinutiaPointSet [readMinutiaeDataPoints](#) ([Memory::IndexedBuffer](#) &buf, uint32_t count) throw (Error::DataError)
Read the minutiae data points, and extended data blocks.
- virtual void [readExtendedDataBlock](#) ([Memory::IndexedBuffer](#) &buf) throw (Error::DataError)
Read the common extended data block.
- virtual Feature::RidgeCountItemSet [readRidgeCountData](#) ([Memory::IndexedBuffer](#) &buf, uint32_t dataLength) throw (Error::DataError)
Read the ridge count data.
- virtual void [readCoreDeltaData](#) ([Memory::IndexedBuffer](#) &buf, uint32_t dataLength, Feature::CorePointSet &cores, Feature::DeltaPointSet &deltas)=0 throw (Error::DataError)
Read the core points data.

E.44.1 Detailed Description

A class to represent single finger view and derived information.

A base [Finger::INCITSView](#) object represents an INCITS/ANSI or ISO finger view. This class defines the common interface for all ANSI/ISO views as well as common implementations. Subclasses specialize this class in order to represent other versions of the ANSI/ISO specs. Objects of this class cannot be created.

E.44.2 Constructor & Destructor Documentation

E.44.2.1 [BiometricEvaluation::Finger::INCITSView::INCITSView](#) (const std::string & *fmrFilename*, const std::string & *firFilename*, const uint32_t *viewNumber*) throw (Error::DataError, Error::FileError) [protected]

Construct the common components of an INCITS finger view from records contained in files.

See documentation in child classes of INCITS for information on constructing INCITS-derived finger views.

Parameters

in	<i>fmrFilename</i>	The name of the file containing the complete finger minutiae record.
in	<i>firFilename</i>	The name of the file containing the complete finger image record.
in	<i>viewNumber</i>	The finger view number to use.

Exceptions

<i>Error::DataError</i>	Invalid record format.
<i>Error::FileError</i>	Could not open or read from file.

E.44.2.2 `BiometricEvaluation::Finger::INCITSView::INCITSView (const Memory::uint8Array & fmrBuffer, const Memory::uint8Array & firBuffer, const uint32_t viewNumber) throw (Error::DataError) [protected]`

Construct an INCITS finger view from records contained in buffers.

See documentation in child classes of INCITS for information on constructing INCITS-derived finger views.

Parameters

in	<i>fmrBuffer</i>	The buffer containing the complete finger minutiae record.
in	<i>firBuffer</i>	The buffer containing the complete finger image record.
in	<i>viewNumber</i>	The finger view number to use.

Exceptions

<i>Error::DataError</i>	Invalid record format.
---	------------------------

E.44.3 Member Function Documentation

E.44.3.1 `static Finger::Position::Kind BiometricEvaluation::Finger::INCITSView::convertPosition (int incitsFGP) throw (Error::DataError) [static]`

Convert a finger position code from an INCITS finger record to the common code.

Parameters

in	<i>incitsFGP</i>	A finger position code as defined by the INCITS standard.
----	------------------	---

Exceptions

<i>Error::DataError</i>	The position code is invalid.
---	-------------------------------

Returns

The finger position code in common notation.

E.44.3.2 static Finger::Impression::Kind BiometricEvaluation::Finger::INCITSView::convertImpression (int *incitsIMP*) throw (Error::DataError) [static]

Convert a impression type code from an INCITS finger record to the common code.

Parameters

in	<i>incitsIMP</i>	A finger impression type code as defined by the INCITS standard.
----	------------------	--

Exceptions

<i>Error::DataError</i>	The impression type code is invalid.
---	--------------------------------------

Returns

The finger impression type code in common notation.

E.44.3.3 Finger::Position::Kind BiometricEvaluation::Finger::INCITSView::getPosition () const

Obtain the finger position.

Returns

The finger position.

E.44.3.4 Finger::Impression::Kind BiometricEvaluation::Finger::INCITSView::getImpressionType () const

Obtain the finger impression code.

Returns

The finger impression code.

E.44.3.5 uint32_t BiometricEvaluation::Finger::INCITSView::getQuality () const

Obtain the finger quality value.

Returns

The finger quality value.

E.44.3.6 uint16_t BiometricEvaluation::Finger::INCITSView::getCaptureEquipmentID () const

Obtain the capture equipment identifier.

Returns

The equipment ID.

E.44.3.7 bool BiometricEvaluation::Finger::INCITSView::isAppendixFCompliant () const

Obtain the capture equipment compliance indicator for 'Appendix F'.

Returns

True if 'Appendix F' compliant, false otherwise.

E.44.3.8 tr1::shared_ptr<Image::Image> BiometricEvaluation::Finger::INCITSView::getImage () const
[virtual]

Obtain the image used for the finger view.

Not all finger views will have an image, however the derived information, such as minutiae, may be present.

Implements [BiometricEvaluation::View::View](#).

E.44.3.9 Image::Size BiometricEvaluation::Finger::INCITSView::getImageSize () const [virtual]

Obtain the image size.

This value is as present in the biometric record, and not in the image data itself. Normally, this value and the actual image size must be equal, but applications can check for inconsistencies. In the case of raw images, however, the value obtained with this method must be accepted as correct.

Implements [BiometricEvaluation::View::View](#).

E.44.3.10 Image::Resolution BiometricEvaluation::Finger::INCITSView::getImageResolution () const
[virtual]

Obtain the image resolution.

[Image](#) resolution is taken from the biometric record, and not from the image data. In some cases, the resolution may be the components of the pixel ratio, and applications must check the [Image::Resolution::units](#) field for value NA.

Implements [BiometricEvaluation::View::View](#).

E.44.3.11 uint32_t BiometricEvaluation::Finger::INCITSView::getImageDepth () const [virtual]

Obtain the image depth.

This value is as present in the biometric record, and not in the image data itself. Normally, this value and the actual image depth must be equal, but applications can check for inconsistencies. In the case of raw images, however, the value obtained with this method must be accepted as correct.

Implements [BiometricEvaluation::View::View](#).

E.44.3.12 Image::CompressionAlgorithm::Kind BiometricEvaluation::Finger::INCITSView::getCompression-Algorithm () const [virtual]

Obtain the compression algorithm used on the image.

This value is as present in the biometric record, and not obtained from the image data itself.

Implements [BiometricEvaluation::View::View](#).

E.44.3.13 `Image::Resolution BiometricEvaluation::Finger::INCITSView::getScanResolution () const`
[virtual]

Obtain the image scan resolution.

This value is as present in the biometric record, and not in the image data itself. Normally, this value and the actual image resolution must be equal, but applications can check for inconsistencies.

Implements [BiometricEvaluation::View::View](#).

E.44.3.14 `Memory::uint8Array const& BiometricEvaluation::Finger::INCITSView::getFMRData () const`
[protected]

Obtain a reference to the finger minutiae record data buffer.

Returns

The entire finger minutiae record data.

E.44.3.15 `Memory::uint8Array const& BiometricEvaluation::Finger::INCITSView::getFIRData () const`
[protected]

Obtain a reference to the finger image record data buffer.

Returns

The entire finger image record data.

E.44.3.16 `void BiometricEvaluation::Finger::INCITSView::setMinutiaeData (const Feature::INCITSMinutiae & fmd)` [protected]

Mutator for the [Feature::INCITSMinutiae](#) item.

Parameters

in	<i>fmd</i>	The minutiae data object.
----	------------	---------------------------

E.44.3.17 `void BiometricEvaluation::Finger::INCITSView::setPosition (const Finger::Position::Kind & position)` [protected]

Mutator for the position.

Parameters

in	<i>position</i>	The finger position.
----	-----------------	----------------------

E.44.3.18 void BiometricEvaluation::Finger::INCITSView::setImpressionType (const Finger::Impression::Kind & *impression*) [protected]

Mutator for the impression type.

Parameters

in	<i>impression</i>	The finger impression type code.
----	-------------------	----------------------------------

E.44.3.19 void BiometricEvaluation::Finger::INCITSView::setQuality (uint32_t *quality*) [protected]

Mutator for the finger quality value.

Parameters

in	<i>quality</i>	The quality value.
----	----------------	--------------------

E.44.3.20 void BiometricEvaluation::Finger::INCITSView::setViewNumber (uint32_t *viewNumber*) [protected]

Mutator for the finger view number.

Parameters

in	<i>viewNumber</i>	The view number value.
----	-------------------	------------------------

E.44.3.21 void BiometricEvaluation::Finger::INCITSView::setCaptureEquipmentID (uint16_t *id*) [protected]

Mutator for the equipment ID.

Parameters

in	<i>id</i>	The equipment ID value.
----	-----------	-------------------------

E.44.3.22 void BiometricEvaluation::Finger::INCITSView::setCBEFFProductIDs (uint16_t *owner*, uint16_t *type*) [protected]

Mutator for the CBEFF Product ID owner and type.

Parameters

in	<i>owner</i>	The CBEFF ID of the product owner.
in	<i>type</i>	The CBEFF ID of the product type.

E.44.3.23 void BiometricEvaluation::Finger::INCITSView::setAppendixFCompliance (bool *flag*)
[protected]

Mutator for the Appendix F compliance indicator.

Parameters

in	<i>flag</i>	True if the capture equipment is 'Appendix F' compliant, false if not.
----	-------------	--

E.44.3.24 void BiometricEvaluation::Finger::INCITSView::setImageSize (const Image::Size & *imageSize*)
[protected]

Mutator for the image size.

Parameters

in	<i>imageSize</i>	The image size object.
----	------------------	------------------------

E.44.3.25 void BiometricEvaluation::Finger::INCITSView::setImageResolution (const Image::Resolution & *imageResolution*) [protected]

Mutator for the image resolution.

Parameters

in	<i>image-Resolution</i>	The image resolution object.
----	-------------------------	------------------------------

E.44.3.26 void BiometricEvaluation::Finger::INCITSView::setScanResolution (const Image::Resolution & *scanResolution*) [protected]

Mutator for the image scan resolution.

Parameters

in	<i>scanResolution</i>	The image scan resolution object.
----	-----------------------	-----------------------------------

E.44.3.27 void BiometricEvaluation::Finger::INCITSView::setImageData (const Memory::uint8Array & *imageData*) [protected]

Mutator for the image data.

Parameters

in	<i>imageData</i>	The image data object.
----	------------------	------------------------

E.44.3.28 `void BiometricEvaluation::Finger::INCITSView::readFMRHeader (Memory::IndexedBuffer & buf, const uint32_t formatStandard) throw (Error::ParameterError, Error::DataError) [protected]`

Read the common finger minutiae record header from an INCITS record.

For ANSI-2004 and ISO-2005 record formats, the finger minutiae record header is (mostly) the same.

Parameters

in	<i>buf</i>	The indexed buffer containing the record data. The index of the buffer will be changed to the location after the header.
in	<i>formatStandard</i>	Value indicating which header version to read; one of FMR_ANSI2004_STANDARD or FMR_ISO2005_STANDARD.

Exceptions

<i>ParameterError</i>	The specVersion parameter is incorrect.
<i>DataError</i>	The INCITS record has invalid or missing data.

E.44.3.29 `void BiometricEvaluation::Finger::INCITSView::readFVMR (Memory::IndexedBuffer & buf) throw (Error::DataError) [protected]`

Read the common finger view record information from an INCITS record.

A [Finger View](#) from an INCITS record includes image information, minutiae, and extended data (ridge counts, cores/deltas, etc.) For ANSI-2004 and ISO-2005 record formats, the finger view representation is the same, so this functions parses those record formats. The minutiae data items are also read, as well as any extended data.

Parameters

in, out	<i>buf</i>	The indexed buffer containing the record data. The index of the buffer will be changed to the location after the finger view, including the extended data.
---------	------------	--

Exceptions

<i>DataError</i>	The INCITS record has invalid or missing data.
------------------	--

E.44.3.30 `virtual Feature::MinutiaPointSet BiometricEvaluation::Finger::INCITSView::readMinutiaeDataPoints (Memory::IndexedBuffer & buf, uint32_t count) throw (Error::DataError) [protected], [virtual]`

Read the minutiae data points, and extended data blocks.

Function to be implemented by derived classes to read the minutiae data points and extended data block ac-

ording to the specific standard they represent.

Parameters

in	<i>buf</i>	The indexed buffer containing the record data. The index of the buffer will be changed to the location after the finger view, including the extended data.
in	<i>count</i>	Number of minutiae data points to read.

Exceptions

<i>DataError</i>	The INCITS record has invalid or missing data.
------------------	--

E.44.3.31 `virtual void BiometricEvaluation::Finger::INCITSView::readExtendedDataBlock (Memory::IndexedBuffer & buf) throw (Error::DataError) [protected], [virtual]`

Read the common extended data block.

Parameters

in, out	<i>buf</i>	The indexed buffer containing the record data. The index of the buffer will be changed to the location after the extended data block.
---------	------------	---

Exceptions

<i>DataError</i>	The INCITS record has invalid or missing data.
------------------	--

E.44.3.32 `virtual Feature::RidgeCountItemSet BiometricEvaluation::Finger::INCITSView::readRidgeCountData (Memory::IndexedBuffer & buf, uint32_t dataLength) throw (Error::DataError) [protected], [virtual]`

Read the ridge count data.

This method reads data in the base INCITS format as defined in INCITS/ANSI 378-2004. This method may be overridden by derived classes to read data in a different record format.

Parameters

in, out	<i>buf</i>	The indexed buffer containing the record data. On function exit, the buffer index will be set to the location after the last ridge count item.
in	<i>dataLength</i>	The length of the entire ridge count data block.

E.44.3.33 `virtual void BiometricEvaluation::Finger::INCITSView::readCoreDeltaData (Memory::IndexedBuffer & buf, uint32_t dataLength, Feature::CorePointSet & cores, Feature::DeltaPointSet & deltas) throw (Error::DataError) [protected], [pure virtual]`

Read the core points data.

This method must be overridden by derived classes to read data in a specific record format.

Parameters

in, out	<i>buf</i>	The indexed buffer containing the record data. On function exit, the buffer index will be set to the location after the last core point data item.
out	<i>cores</i>	The set of core data items.
out	<i>deltas</i>	The set of delta data items.
in	<i>dataLength</i>	The length of the entire ridge count data block.

Implemented in [BiometricEvaluation::Finger::ANSI2007View](#), [BiometricEvaluation::Finger::ISO2005View](#), and [BiometricEvaluation::Finger::ANSI2004View](#).

E.45 BiometricEvaluation::Memory::IndexedBuffer Class Reference

Manage a memory buffer with an index.

```
#include <be_memory_indexedbuffer.h>
```

Public Member Functions

- **operator uint8_t * ()**
- **uint8_t * operator-> ()**
- **IndexedBuffer & operator= (const IndexedBuffer &other)**
- **IndexedBuffer ()**
Create an indexed buffer of zero length.
- **IndexedBuffer (uint32_t size)**
Create an indexed buffer of a given length.
- **IndexedBuffer (uint8_t *data, uint32_t size)**
Create an indexed buffer around an existing buffer of a given length.
- **IndexedBuffer (const IndexedBuffer ©)**
Copy constructor.
- **uint32_t getSize ()**
Obtain the current size of the buffer.
- **uint32_t getIndex ()**
Obtain the current index into the buffer.
- **void setIndex (uint32_t index) throw (Error::ParameterError)**
Set the current index into the buffer.
- **uint8_t scanU8Val () throw (Error::DataError)**
Obtain the next element of the buffer and increment the current index value.
- **uint16_t scanU16Val () throw (Error::DataError)**
Obtain the next two elements of the buffer and increment the current index value.
- **uint16_t scanBeU16Val () throw (Error::DataError)**
Obtain the next two elements of the buffer, scanned as a big-endian value, and increment the current index value.
- **uint32_t scanU32Val () throw (Error::DataError)**
Obtain the next four elements of the buffer and increment the current index value by four.

- `uint32_t scanBeU32Val ()` throw (Error::DataError)
Obtain the next four elements of the buffer, scanned as a big-endian value, and increment the current index value.
- `uint64_t scanU64Val ()` throw (Error::DataError)
Obtain the next eight elements of the buffer and increment the current index value by eight.
- `uint32_t scan (void *buf, const uint32_t len)` throw (Error::DataError)
Obtain the next 'n' elements of the buffer and increment the current index value by n.
- `uint8_t & operator[] (ptrdiff_t i)`
Subscripting operator.
- `const uint8_t & operator[] (ptrdiff_t i) const`
Constant subscripting operator.

E.45.1 Detailed Description

Manage a memory buffer with an index.

The memory buffer is treated as an array of unsigned eight bit values. This class provides safe access to the array with methods to retrieve 8/16/32/64-bit elements, or and arbitrary segment starting at the index, from the array while advancing the current index. An exception is thrown by these methods whenever the retrieval would reach beyond the size of the buffer.

The buffer can also be accessed directly by subscripting.

E.45.2 Constructor & Destructor Documentation

E.45.2.1 BiometricEvaluation::Memory::IndexedBuffer::IndexedBuffer (uint8_t * data, uint32_t size)

Create an indexed buffer around an existing buffer of a given length.

An object constructed in this manner will not free the underlying data buffer.

E.45.3 Member Function Documentation

E.45.3.1 uint32_t BiometricEvaluation::Memory::IndexedBuffer::getSize ()

Obtain the current size of the buffer.

Returns

The current buffer size.

E.45.3.2 uint32_t BiometricEvaluation::Memory::IndexedBuffer::getIndex ()

Obtain the current index into the buffer.

Returns

The current buffer index.

E.45.3.3 void BiometricEvaluation::Memory::IndexedBuffer::setIndex (uint32_t *index*) throw (Error::ParameterError)

Set the current index into the buffer.

Parameters

<i>in</i>	<i>index</i>	The index value to set.
-----------	--------------	-------------------------

Exceptions

<i>Error::ParameterError</i>	The index parameter is too large.
--	-----------------------------------

E.45.3.4 uint8_t BiometricEvaluation::Memory::IndexedBuffer::scanU8Val () throw (Error::DataError)

Obtain the next element of the buffer and increment the current index value.

Exceptions

<i>Error::DataError</i>	The buffer is exhausted.
---	--------------------------

Returns

The next element of the buffer as an unsigned 8-bit value.

E.45.3.5 uint16_t BiometricEvaluation::Memory::IndexedBuffer::scanU16Val () throw (Error::DataError)

Obtain the next two elements of the buffer and increment the current index value.

Exceptions

<i>Error::DataError</i>	The buffer is exhausted.
---	--------------------------

Returns

The next element of the buffer as an unsigned 16-bit value.

E.45.3.6 uint16_t BiometricEvaluation::Memory::IndexedBuffer::scanBeU16Val () throw (Error::DataError)

Obtain the next two elements of the buffer, scanned as a big-endian value, and increment the current index value.

Exceptions

<i>Error::DataError</i>	The buffer is exhausted.
---	--------------------------

Returns

The next element of the buffer as an unsigned 16-bit value.

E.45.3.7 `uint32_t BiometricEvaluation::Memory::IndexedBuffer::scanU32Val () throw (Error::DataError)`

Obtain the next four elements of the buffer and increment the current index value by four.

Exceptions

<i>Error::DataError</i>	The buffer is exhausted.
---	--------------------------

Returns

The next element of the buffer as an unsigned 32-bit value.

E.45.3.8 `uint32_t BiometricEvaluation::Memory::IndexedBuffer::scanBeU32Val () throw (Error::DataError)`

Obtain the next four elements of the buffer, scanned as a big-endian value, and increment the current index value.

Exceptions

<i>Error::DataError</i>	The buffer is exhausted.
---	--------------------------

Returns

The next element of the buffer as an unsigned 32-bit value.

E.45.3.9 `uint64_t BiometricEvaluation::Memory::IndexedBuffer::scanU64Val () throw (Error::DataError)`

Obtain the next eight elements of the buffer and increment the current index value by eight.

Exceptions

<i>Error::DataError</i>	The buffer is exhausted.
---	--------------------------

Returns

The next element of the buffer as an unsigned 64-bit value.

E.45.3.10 `uint32_t BiometricEvaluation::Memory::IndexedBuffer::scan (void * buf, const uint32_t len) throw (Error::DataError)`

Obtain the next 'n' elements of the buffer and increment the current index value by n.

Parameters

in	<i>buf</i>	Buffer to store the copied data. Can be NULL. The current index is incremented.
in	<i>len</i>	The number of elements to copy.

Exceptions

<i>Error::DataError</i>	The buffer is exhausted.
---	--------------------------

Returns

The number of elements copied.

E.45.3.11 `uint8_t& BiometricEvaluation::Memory::IndexedBuffer::operator[] (ptrdiff_t i)`

Subscripting operator.

Provides array-like access to elements of the buffer. This operation will not affect the current index value.

Parameters

in	<i>i</i>	The subscript.
----	----------	----------------

Returns

Reference to element '*i*' of the buffer.

E.45.3.12 `const uint8_t& BiometricEvaluation::Memory::IndexedBuffer::operator[] (ptrdiff_t i) const`

Constant subscripting operator.

Provides read-only array-like access to elements of the buffer. This operation will not affect the current index value.

Parameters

in	<i>i</i>	The subscript.
----	----------	----------------

Returns


Reference to const element '*i*' of the buffer.

E.46 BiometricEvaluation::Finger::ISO2005View Class Reference

A class to represent single finger view and derived information.

```
#include <be_finger_iso2005view.h>
```

Inheritance diagram for BiometricEvaluation::Finger::ISO2005View:



Public Member Functions

- [ISO2005View](#) (const std::string &fmrFilename, const std::string &firFilename, const uint32_t view-Number) throw (Error::DataError, Error::FileError)

Construct an ISO-2005 finger view from records contained in files.

- [ISO2005View](#) ([Memory::uint8Array](#) &fmrBuffer, [Memory::uint8Array](#) &firBuffer, const uint32_t view-Number) throw (Error::DataError)

Construct an ISO-2005 finger view from records contained in buffers.

Static Public Attributes

- static const uint16_t **CORE_TYPE_MASK** = 0xC000
- static const uint16_t **CORE_TYPE_SHIFT** = 14
- static const uint16_t **CORE_NUM_CORES_MASK** = 0x3F
- static const uint16_t **CORE_X_COORD_MASK** = 0x3FFF
- static const uint16_t **CORE_Y_COORD_MASK** = 0x3FFF
- static const uint16_t **CORE_MIN_NUM** = 0
- static const uint16_t **DELTA_TYPE_MASK** = 0xC000
- static const uint16_t **DELTA_TYPE_SHIFT** = 14
- static const uint16_t **DELTA_NUM_DELTAS_MASK** = 0x3F
- static const uint16_t **DELTA_X_COORD_MASK** = 0x3FFF
- static const uint16_t **DELTA_Y_COORD_MASK** = 0x3FFF

Protected Member Functions

- virtual void [readCoreDeltaData](#) ([Memory::IndexedBuffer](#) &buf, uint32_t dataLength, Feature::Core-PointSet &cores, Feature::DeltaPointSet &deltas) throw (Error::DataError)

Read the core points data.

Additional Inherited Members

E.46.1 Detailed Description

A class to represent single finger view and derived information.

A [Finger::ISO2005View](#) object represents a finger view from a ISO/IEC-2005 [Finger](#) Minutiae Record.

E.46.2 Constructor & Destructor Documentation

E.46.2.1 BiometricEvaluation::Finger::ISO2005View::ISO2005View (const std::string & *fmrFilename*, const std::string & *firFilename*, const uint32_t *viewNumber*) throw (Error::DataError, Error::FileError)

Construct an ISO-2005 finger view from records contained in files.

A view can be constructed from a single record, with information missing as appropriate. For example, if a view is constructed with just the minutiae record, no image would be part of the view. However, the image size etc. would be present because that information is also present in the minutiae record.

Parameters

in	<i>fmrFilename</i>	The name of the file containing the complete finger minutiae record.
in	<i>firFilename</i>	The name of the file containing the complete finger image record.
in	<i>viewNumber</i>	The finger view number to use.

E.46.2.2 BiometricEvaluation::Finger::ISO2005View::ISO2005View (Memory::uint8Array & *fmrBuffer*, Memory::uint8Array & *firBuffer*, const uint32_t *viewNumber*) throw (Error::DataError)

Construct an ISO-2005 finger view from records contained in buffers.

A view can be constructed from a single record, with information missing as appropriate. For example, if a view is constructed with just the minutiae record, no image would be part of the view. However, the image size etc. would be present because that information is also present in the minutiae record.

Parameters

in	<i>fmrBuffer</i>	The buffer containing the complete finger minutiae record.
in	<i>firBuffer</i>	The buffer containing the complete finger image record.
in	<i>viewNumber</i>	The finger view number to use.

Exceptions

<i>Error::DataError</i>	Invalid record format.
---	------------------------

E.46.3 Member Function Documentation

E.46.3.1 virtual void BiometricEvaluation::Finger::ISO2005View::readCoreDeltaData (Memory::IndexedBuffer & *buf*, uint32_t *dataLength*, Feature::CorePointSet & *cores*, Feature::DeltaPointSet & *deltas*) throw (Error::DataError) [protected], [virtual]

Read the core points data.

This method must be overridden by derived classes to read data in a specific record format.

Parameters

in, out	<i>buf</i>	The indexed buffer containing the record data. On function exit, the buffer index will be set to the location after the last core point data item.
out	<i>cores</i>	The set of core data items.

out	<i>deltas</i>	The set of delta data items.
in	<i>dataLength</i>	The length of the entire ridge count data block.


Implements [BiometricEvaluation::Finger::INCITSView](#).

E.47 BiometricEvaluation::Image::JPEG Class Reference

A JPEG-encoded image.

```
#include <be_image_jpeg.h>
```

Inheritance diagram for BiometricEvaluation::Image::JPEG:



Public Member Functions

- **JPEG** (const uint8_t *data, const uint64_t size) throw (Error::DataError, Error::StrategyError)
- [Memory::AutoArray](#)< uint8_t > [getRawGrayscaleData](#) (uint8_t depth=8) const throw (Error::DataError, Error::ParameterError)
Accessor for decompressed data in grayscale.
- [Memory::AutoArray](#)< uint8_t > [getRawData](#) () const throw (Error::DataError)
Accessor for the raw image data. The data returned should not be compressed or encoded.

Static Public Member Functions

- static bool [isJPEG](#) (const uint8_t *data, const size_t size)
- static int [getc_skip_marker_segment](#) (const unsigned short marker, unsigned char **cbufptr, unsigned char *ebufptr)

Additional Inherited Members

E.47.1 Detailed Description

A JPEG-encoded image.

E.47.2 Member Function Documentation

E.47.2.1 [Memory::AutoArray](#)<uint8_t> [BiometricEvaluation::Image::JPEG::getRawGrayscaleData](#) (uint8_t *depth* = 8) const throw (Error::DataError, Error::ParameterError) [virtual]

Accessor for decompressed data in grayscale.

Parameters

<i>depth</i>	The desired bit depth of the resulting raw image. This value may either be 8 or 1.
--------------	--

Returns

[Raw](#) image buffer.

Exceptions

Error::DataError	Error decompressing image data.
Error::ParameterError	Invalid value for depth.

Note

This method does not save a cached copy of the decompressed image because the bit depth of the image can be changed between calls.

This method always returns an image that uses 8 bits to represent a single pixel. *depth* adjusts the number of pixels used to determine the color of the pixel in the 8 bit container, currently 1 (2 gray levels) or 8 (256 gray levels).

Implements [BiometricEvaluation::Image::Image](#).

E.47.2.2 `Memory::AutoArray<uint8_t> BiometricEvaluation::Image::JPEG::getRawData () const throw (Error::DataError) [virtual]`

Accessor for the raw image data. The data returned should not be compressed or encoded.

Returns

[Raw](#) image data.

Exceptions

Error::DataError	Error decompressing image data.
----------------------------------	---------------------------------

Implements [BiometricEvaluation::Image::Image](#).

E.47.2.3 `static bool BiometricEvaluation::Image::JPEG::isJPEG (const uint8_t * data, const size_t size) [static]`

Whether or not data is a Lossy [JPEG](#) image.

Parameters

<i>in</i>	<i>data</i>	The buffer to check.
<i>in</i>	<i>size</i>	The size of data.

Returns


true if data appears to be a Lossy [JPEG](#) image, false otherwise

E.48 BiometricEvaluation::Image::JPEG2000 Class Reference

A JPEG-2000-encoded image.

```
#include <be_image_jpeg2000.h>
```

Inheritance diagram for BiometricEvaluation::Image::JPEG2000:

**Public Member Functions**

- [JPEG2000](#) (const uint8_t *data, const uint64_t size, const int8_t codec=2) throw (Error::DataError, Error::StrategyError)
Create a new *JPEG2000* object.
- [Memory::AutoArray](#)< uint8_t > [getRawData](#) () const throw (Error::DataError)
Accessor for the raw image data. The data returned should not be compressed or encoded.
- [Memory::AutoArray](#)< uint8_t > [getRawGrayscaleData](#) (uint8_t depth=8) const throw (Error::DataError, Error::ParameterError)
Accessor for decompressed data in grayscale.

Static Public Member Functions

- static bool [isJPEG2000](#) (const uint8_t *data)

Additional Inherited Members**E.48.1 Detailed Description**

A JPEG-2000-encoded image.

E.48.2 Constructor & Destructor Documentation

E.48.2.1 [BiometricEvaluation::Image::JPEG2000::JPEG2000](#) (const uint8_t * *data*, const uint64_t *size*, const int8_t *codec* = 2) throw (Error::DataError, Error::StrategyError)

Create a new [JPEG2000](#) object.

Parameters

in	<i>data</i>	The image data.
in	<i>size</i>	The size of the image data, in bytes.
in	<i>codec</i>	The codec used to encode data.

Exceptions

<i>Error::DataError</i>	Error manipulating data.
<i>Error::StrategyError</i>	Error while creating Image .

E.48.3 Member Function Documentation

E.48.3.1 `Memory::AutoArray<uint8_t> BiometricEvaluation::Image::JPEG2000::getRawData () const throw (Error::DataError) [virtual]`

Accessor for the raw image data. The data returned should not be compressed or encoded.

Returns

[Raw](#) image data.

Exceptions

<i>Error::DataError</i>	Error decompressing image data.
---	---------------------------------

Implements [BiometricEvaluation::Image::Image](#).

E.48.3.2 `Memory::AutoArray<uint8_t> BiometricEvaluation::Image::JPEG2000::getRawGrayscaleData (uint8_t depth = 8) const throw (Error::DataError, Error::ParameterError) [virtual]`

Accessor for decompressed data in grayscale.

Parameters

<i>depth</i>	The desired bit depth of the resulting raw image. This value may either be 8 or 1.
--------------	--

Returns

[Raw](#) image buffer.

Exceptions

<i>Error::DataError</i>	Error decompressing image data.
<i>Error::ParameterError</i>	Invalid value for depth.

Note

This method does not save a cached copy of the decompressed image because the bit depth of the image can be changed between calls.

This method always returns an image that uses 8 bits to represent a single pixel. depth adjusts the number of pixels used to determine the color of the pixel in the 8 bit container, currently 1 (2 gray levels) or 8 (256 gray levels).

Implements [BiometricEvaluation::Image::Image](#).

E.48.3.3 `static bool BiometricEvaluation::Image::JPEG2000::isJPEG2000 (const uint8_t * data) [static]`

Whether or not data is a JPEG-2000 image.

Parameters

<code>in</code>	<code>data</code>	The buffer to check.
-----------------	-------------------	----------------------

Returns


true if data appears to be a JPEG-2000 image, false otherwise.

E.49 BiometricEvaluation::Image::JPEGL Class Reference

A Lossless JPEG-encoded image.

```
#include <be_image_jpegl.h>
```

Inheritance diagram for BiometricEvaluation::Image::JPEGL:

**Public Member Functions**

- **JPEGL** (const uint8_t *data, const uint64_t size) throw (Error::DataError, Error::StrategyError)
- [Memory::AutoArray](#)< uint8_t > [getRawGrayscaleData](#) (uint8_t depth=8) const throw (Error::DataError, Error::ParameterError)
Accessor for decompressed data in grayscale.
- [Memory::AutoArray](#)< uint8_t > [getRawData](#) () const throw (Error::DataError)
Accessor for the raw image data. The data returned should not be compressed or encoded.

Static Public Member Functions

- static bool [isJPEGL](#) (const uint8_t *data, const size_t size)

Additional Inherited Members

E.49.1 Detailed Description

A Lossless JPEG-encoded image.

E.49.2 Member Function Documentation

E.49.2.1 `Memory::AutoArray<uint8_t> BiometricEvaluation::Image::JPEG::getRawGrayscaleData (uint8_t depth = 8) const throw (Error::DataError, Error::ParameterError) [virtual]`

Accessor for decompressed data in grayscale.

Parameters

<i>depth</i>	The desired bit depth of the resulting raw image. This value may either be 8 or 1.
--------------	--

Returns

[Raw](#) image buffer.

Exceptions

Error::DataError	Error decompressing image data.
Error::ParameterError	Invalid value for depth.

Note

This method does not save a cached copy of the decompressed image because the bit depth of the image can be changed between calls.

This method always returns an image that uses 8 bits to represent a single pixel. *depth* adjusts the number of pixels used to determine the color of the pixel in the 8 bit container, currently 1 (2 gray levels) or 8 (256 gray levels).

Implements [BiometricEvaluation::Image::Image](#).

E.49.2.2 `Memory::AutoArray<uint8_t> BiometricEvaluation::Image::JPEG::getRawData () const throw (Error::DataError) [virtual]`

Accessor for the raw image data. The data returned should not be compressed or encoded.

Returns

[Raw](#) image data.

Exceptions

Error::DataError	Error decompressing image data.
----------------------------------	---

Implements [BiometricEvaluation::Image::Image](#).

E.49.2.3 `static bool BiometricEvaluation::Image::JPEGL::isJPEGL (const uint8_t * data, const size_t size)`
`[static]`

Whether or not data is a Lossless [JPEG](#) image.

Parameters


in	<i>data</i>	The buffer to check.
in	<i>size</i>	The size of data.

Returns

true if data appears to be a Lossless [JPEG](#) image, false otherwise.

E.50 BiometricEvaluation::IO::ListRecordStore Class Reference

Inheritance diagram for BiometricEvaluation::IO::ListRecordStore:



Public Member Functions

- [ListRecordStore](#) (const string &name, const string &parentDir) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- [~ListRecordStore](#) ()
- void [insert](#) (const string &key, const void *const data, const uint64_t size) throw (Error::ObjectExists, Error::StrategyError)
- void [remove](#) (const string &key) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [read](#) (const string &key, void *const data) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void [replace](#) (const string &key, const void *const data, const uint64_t size) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t [length](#) (const string &key) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void [flush](#) (const string &key) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void [sync](#) () const throw (Error::StrategyError)
- uint64_t [sequence](#) (string &key, void *const data=NULL, int cursor=[BE_RECSTORE_SEQ_NEXT](#)) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Sequence through a [RecordStore](#), returning the key/data pairs.
- void [setCursorAtKey](#) (string &key) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void [changeName](#) (const string &name) throw (Error::ObjectExists, Error::StrategyError)
- uint64_t [getSpaceUsed](#) () const throw (Error::StrategyError)
Obtain real storage utilization.

Static Public Attributes

- static const string [SOURCERECORDSTOREPROPERTY](#)
- static const string [KEYLISTFILENAME](#)

Additional Inherited Members

E.50.1 Constructor & Destructor Documentation

E.50.1.1 `BiometricEvaluation::IO::ListRecordStore::ListRecordStore (const string & name, const string & parentDir) throw (Error::ObjectDoesNotExist, Error::StrategyError)`

Constructor, always opening read-only

E.50.1.2 `BiometricEvaluation::IO::ListRecordStore::~~ListRecordStore ()`

Destructor

E.50.2 Member Function Documentation

E.50.2.1 `void BiometricEvaluation::IO::ListRecordStore::insert (const string & key, const void *const data, const uint64_t size) throw (Error::ObjectExists, Error::StrategyError) [virtual]`

Insert a record into the store.

Parameters

in	<i>key</i>	The key of the record to be inserted.
in	<i>data</i>	The data for the record.
in	<i>size</i>	The size, in bytes, of the record.

Exceptions

Error::ObjectExists	A record with the given key is already present.
Error::StrategyError	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.50.2.2 `void BiometricEvaluation::IO::ListRecordStore::remove (const string & key) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Remove a record from the store.

Parameters

in	<i>key</i>	The key of the record to be removed.
----	------------	--------------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.50.2.3 `uint64_t BiometricEvaluation::IO::ListRecordStore::read (const string & key, void *const data) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Read a complete record from a store. Applications are responsible for allocating storage for the record's data.

Parameters

in	<i>key</i>	The key of the record to be read.
in	<i>data</i>	Pointer to where the data is to be written.

Returns

The size of the record.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.50.2.4 `void BiometricEvaluation::IO::ListRecordStore::replace (const string & key, const void *const data, const uint64_t size) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Replace a complete record in a store.

Parameters

in	<i>key</i>	The key of the record to be replaced.
in	<i>data</i>	The data for the record.
in	<i>size</i>	The size of data.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.50.2.5 `uint64_t BiometricEvaluation::IO::ListRecordStore::length (const string & key) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Return the length of a record.

Parameters

<i>in</i>	<i>key</i>	The key of the record.
-----------	------------	------------------------

Returns

The record length.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.50.2.6 `void BiometricEvaluation::IO::ListRecordStore::flush (const string & key) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Commit the record's data to storage.

Parameters

<i>in</i>	<i>key</i>	The key of the record to be flushed.
-----------	------------	--------------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.50.2.7 `void BiometricEvaluation::IO::ListRecordStore::sync () const throw (Error::StrategyError) [virtual]`

Synchronize the entire record store to persistent storage.

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.
---	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.50.2.8 `uint64_t BiometricEvaluation::IO::ListRecordStore::sequence (string & key, void *const data = NULL, int cursor = BE_RECSTORE_SEQ_NEXT) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Sequence through a [RecordStore](#), returning the key/data pairs.

Sequencing means to start at some point in the store and return the record, then repeatedly calling the sequencor to return the next record. The starting point is typically the first record, and is set to that when the [RecordStore](#) object is created. The starting point can be reset by calling this method with the cursor parameter set to BE_RECSTORE_SEQ_START.

Parameters

out	key	The key of the currently sequenced record.
in	data	Pointer to where the data is to be written. Applications can set data to NULL to indicate only the key is wanted.
in	cursor	The location within the sequence of the key/data pair to return.

Returns

The length of the record currently in sequence.

Exceptions

Error::ObjectDoesNotExist	A record for the key does not exist.
Error::StrategyError	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.50.2.9 `void BiometricEvaluation::IO::ListRecordStore::setCursorAtKey (string & key) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Set the sequence cursor to an arbitrary position within the [RecordStore](#), starting at key. Key will be the first record returned from the next call to [sequence\(\)](#).

Parameters

in	key	The key of the record which will be returned by the first subsequent call to sequence() .
----	-----	---

Exceptions

Error::ObjectDoesNotExist	A record for the key does not exist.
Error::StrategyError	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.50.2.10 void BiometricEvaluation::IO::ListRecordStore::changeName (const string & *name*) throw (Error::ObjectExists, Error::StrategyError) [virtual]

Change the name of the [RecordStore](#).

Parameters

in	<i>name</i>	The new name for the RecordStore .
----	-------------	--

Exceptions

Error::StrategyError	An error occurred when using the underlying storage system, or the name is malformed.
--------------------------------------	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.50.2.11 uint64_t BiometricEvaluation::IO::ListRecordStore::getSpaceUsed () const throw (Error::StrategyError) [virtual]

Obtain real storage utilization.

The amount of disk space used, for example. This is the actual space allocated by the underlying storage mechanism, in bytes.

Returns

The amount of backing storage used by the [RecordStore](#).

Exceptions

Error::StrategyError	An error occurred when using the underlying storage system.
--------------------------------------	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.50.3 Member Data Documentation

E.50.3.1 const string BiometricEvaluation::IO::ListRecordStore::SOURCERECORDSTOREPROPERTY [static]

Property key for the source [RecordStore](#)

E.50.3.2 const string BiometricEvaluation::IO::ListRecordStore::KEYLISTFILENAME [static]

File name containing the list of keys

E.51 BiometricEvaluation::IO::LogCabinet Class Reference

```
#include <be_io_logcabinet.h>
```

Public Member Functions

- [LogCabinet](#) (const string &name, const string &description, const string &parentDir) throw (Error::ObjectExists, Error::StrategyError)
- [LogCabinet](#) (const string &name, const string &parentDir) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- `tr1::shared_ptr< LogSheet > newLogSheet` (const string &name, const string &description) throw (Error::ObjectExists, Error::StrategyError)
- string [getName](#) ()
- string [getDescription](#) ()
- unsigned int [getCount](#) ()

Static Public Member Functions

- static void [remove](#) (const string &name, const string &parentDir) throw (Error::ObjectDoesNotExist, Error::StrategyError)

E.51.1 Detailed Description

A class to represent a collection of log sheets.

E.51.2 Constructor & Destructor Documentation

E.51.2.1 BiometricEvaluation::IO::LogCabinet::LogCabinet (const string & *name*, const string & *description*, const string & *parentDir*) throw (Error::ObjectExists, Error::StrategyError)

Create a new [LogCabinet](#) in the file system.

Parameters

in	<i>name</i>	The name of the LogCabinet to be created.
in	<i>description</i>	The text used to describe the cabinet.
in	<i>parentDir</i>	Where, in the file system, the cabinet is to be stored. This directory must exist.

Exceptions

Error::ObjectExists	The cabinet was previously created.
Error::StrategyError	
Error::StrategyError	An error occurred when using the underlying file system, or name or parentDir is malformed.

E.51.2.2 BiometricEvaluation::IO::LogCabinet::LogCabinet (const string & *name*, const string & *parentDir*) throw (Error::ObjectDoesNotExist, Error::StrategyError)

Open an existing [LogCabinet](#).

Parameters

in	<i>name</i>	The name of the LogCabinet to be created.
in	<i>parentDir</i>	Where, in the file system, the cabinet is to be stored. This directory must exist.

Exceptions

Error::ObjectDoesNotExist	The cabinet does not exist in the file system.
Error::StrategyError	An error occurred when using the underlying file system, or name or parentDir is malformed.

E.51.3 Member Function Documentation

E.51.3.1 tr1::shared_ptr<LogSheet> BiometricEvaluation::IO::LogCabinet::newLogSheet (const string & *name*, const string & *description*) throw (Error::ObjectExists, Error::StrategyError)

Create a new [LogSheet](#) within the [LogCabinet](#).

Parameters

in	<i>name</i>	The name of the LogSheet to be created.
in	<i>description</i>	The text used to describe the sheet. This text is written into the log file prior to any entries.

Returns

An object pointer to the new log sheet.

Exceptions

Error::ObjectExists	The sheet was previously created.
Error::StrategyError	An error occurred when using the underlying file system, or name or parentDir is malformed.

E.51.3.2 string BiometricEvaluation::IO::LogCabinet::getName ()

Obtain the name of the [LogCabinet](#).

@ returns The name of the [LogCabinet](#).

E.51.3.3 `string BiometricEvaluation::IO::LogCabinet::getDescription ()`

Obtain the description of the [LogCabinet](#).

@ returns The description of the [LogCabinet](#).

E.51.3.4 `unsigned int BiometricEvaluation::IO::LogCabinet::getCount ()`

Obtain the number of items in the [LogCabinet](#).

@ returns The number of LogSheets manages by the cabinet.

E.51.3.5 `static void BiometricEvaluation::IO::LogCabinet::remove (const string & name, const string & parentDir) throw (Error::ObjectDoesNotExist, Error::StrategyError) [static]`

Remove a [LogCabinet](#).

Parameters

in	<i>name</i>	The name of the LogCabinet to be removed.
in	<i>parentDir</i>	Where, in the file system, the sheet is to be stored. This directory must exist.

Exceptions


<i>Error::ObjectDoesNotExist</i>	The LogCabinet does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying file system, or name or parentDir is malformed.

E.52 BiometricEvaluation::IO::LogSheet Class Reference

A class to represent a single logging mechanism.

```
#include <be_io_logsheets.h>
```

Inheritance diagram for BiometricEvaluation::IO::LogSheet:

**Public Member Functions**

- [LogSheet](#) (const string &name, const string &description, const string &parentDir) throw (Error::ObjectExists, Error::StrategyError)

Create a new log sheet.

- [LogSheet](#) (const string &name, const string &parentDir) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Open an existing new log sheet for appending.
- virtual [~LogSheet](#) ()
- virtual void [write](#) (const string &entry) throw (Error::StrategyError)
Write a string as an entry to the log file.
- virtual void [writeComment](#) (const string &comment) throw (Error::StrategyError)
Write a string as a comment to the log file.
- virtual void [newEntry](#) () throw (Error::StrategyError)
Start a new entry, causing the existing entry to be closed.
- virtual string [getCurrentEntry](#) ()
Obtain the contents of the current entry currently under construction.
- virtual void [resetCurrentEntry](#) ()
- virtual uint32_t [getCurrentEntryNumber](#) ()
Obtain the current entry number.
- virtual void [sync](#) () throw (Error::StrategyError)
Synchronize any buffered data to the underlying log file.
- void [setAutoSync](#) (bool state)
- string [sequence](#) (bool comments=false, bool [trim](#)=true, int32_t cursor=[BE_LOGSHEET_SEQ_NEXT](#)) throw (Error::FileError, Error::ObjectDoesNotExist, Error::StrategyError)
Sequence through a [LogSheet](#), returning one entry per invocation.

Static Public Member Functions

- static string [trim](#) (const string &entry)
Trim delimiters from [LogSheet](#) entries.
- static void [mergeLogSheets](#) (vector< tr1::shared_ptr< [LogSheet](#) > > &logSheets) throw (Error::FileError, Error::StrategyError)
Merge multiple [LogSheets](#) into a single [LogSheet](#).

Static Public Attributes

- static const char [CommentDelimiter](#) = '#'
- static const char [EntryDelimiter](#) = 'E'
- static const string [DescriptionTag](#)
- static const int32_t [BE_LOGSHEET_SEQ_START](#) = 1
- static const int32_t [BE_LOGSHEET_SEQ_NEXT](#) = 2

Protected Member Functions

- [LogSheet](#) (const [LogSheet](#) &)
- [LogSheet](#) & [operator=](#) (const [LogSheet](#) &)
- void [updateCursor](#) () throw (Error::FileError)
Update the cursor position of the sequence file.

Protected Attributes

- uint32_t [_entryNumber](#)
- auto_ptr< std::fstream > [_theLogFile](#)
- bool [_autoSync](#)
- tr1::shared_ptr< std::fstream > [_sequenceFile](#)
- streamoff [_cursor](#)

E.52.1 Detailed Description

A class to represent a single logging mechanism.

A [LogSheet](#) is a string stream, so applications can write into the stream as a staging area using the << operator, then start a new entry by calling [newEntry\(\)](#). Entries in the log file are prefixed with an entry number, which is incremented when the entry is written (either by directly calling [write\(\)](#), or calling [newEntry\(\)](#)).

A [LogSheet](#) object can be constructed and passed back to the client by the [LogCabinet](#) object. All sheets created in the manner are placed in a common area maintained by the cabinet.

Note

By default, the entries in the [LogSheet](#) may not be immediately written to the file system, depending on the buffering behavior of the operating system. Applications can force a write by invoking [sync\(\)](#), or force a write at every new log entry by invoking [setAutoSync\(true\)](#).

Entries created by applications may be composed of more than one line (each separated by the newline character). The text at the beginning of a line should not "look like" an entry number:

Edddd

i.e. the entry delimiter followed by some digits. [LogSheet](#) won't check for that condition, but any existing [LogSheet](#) that is re-opened for append may have an incorrect starting entry number.

E.52.2 Constructor & Destructor Documentation

E.52.2.1 [BiometricEvaluation::IO::LogSheet::LogSheet \(const string & name, const string & description, const string & parentDir \) throw \(Error::ObjectExists, Error::StrategyError\)](#)

Create a new log sheet.

Parameters

in	<i>name</i>	The name of the LogSheet to be created.
in	<i>description</i>	The text used to describe the sheet. This text is written into the log file prior to any entries.
in	<i>parentDir</i>	Where, in the file system, the sheet is to be stored. This directory must exist.

Exceptions

Error::ObjectExists	The sheet was previously created.
Error::StrategyError	An error occurred when using the underlying file system, or name or parentDir is malformed.

E.52.2.2 BiometricEvaluation::IO::LogSheet::LogSheet (const string & *name*, const string & *parentDir*) throw (Error::ObjectDoesNotExist, Error::StrategyError)

Open an existing new log sheet for appending.

On open, the current entry counter is set to the last entry number plus one.

Note

Opening a large [LogSheet](#) may be a costly operation.

Parameters

in	<i>name</i>	The name of the LogSheet to be opened.
in	<i>parentDir</i>	Where, in the file system, the sheet is stored.

Exceptions

Error::ObjectDoesNotExist	The sheet does not exist.
Error::StrategyError	An error occurred when using the underlying file system, or name or parentDir is malformed.

E.52.2.3 virtual BiometricEvaluation::IO::LogSheet::~~LogSheet () [virtual]

Destructor

E.52.2.4 BiometricEvaluation::IO::LogSheet::LogSheet (const LogSheet &) [protected]

Prevent copying of [LogSheet](#) objects

E.52.3 Member Function Documentation

E.52.3.1 virtual void BiometricEvaluation::IO::LogSheet::write (const string & *entry*) throw (Error::StrategyError) [virtual]

Write a string as an entry to the log file.

This does not affect the current log entry buffer, but does increment the entry number.

Parameters

in	<i>entry</i>	The text of the log entry.
----	--------------	----------------------------

Exceptions

Error::StrategyError	An error occurred when using the underlying file system.
--------------------------------------	--

E.52.3.2 `virtual void BiometricEvaluation::IO::LogSheet::writeComment (const string & comment) throw (Error::StrategyError) [virtual]`

Write a string as a comment to the log file.

This does not affect the current log entry buffer, and does not increment the entry number. A comment line is prefixed with CommentDelimiter followed by a space by this method.

Parameters

<i>in</i>	<i>comment</i>	The text of the comment.
-----------	----------------	--------------------------

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying file system.
---	--

E.52.3.3 `virtual void BiometricEvaluation::IO::LogSheet::newEntry () throw (Error::StrategyError) [virtual]`

Start a new entry, causing the existing entry to be closed.

Applications do not have to call this method for the first entry, however, as the stream is ready for writing upon construction.

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying file system.
---	--

E.52.3.4 `virtual string BiometricEvaluation::IO::LogSheet::getCurrentEntry () [virtual]`

Obtain the contents of the current entry currently under construction.

Returns

The text of the current entry.

E.52.3.5 `virtual void BiometricEvaluation::IO::LogSheet::resetCurrentEntry () [virtual]`

Reset the current entry buffer to the beginning.

E.52.3.6 `virtual uint32_t BiometricEvaluation::IO::LogSheet::getCurrentEntryNumber () [virtual]`

Obtain the current entry number.

Returns

The current entry number.

E.52.3.7 `virtual void BiometricEvaluation::IO::LogSheet::sync () throw (Error::StrategyError)`
`[virtual]`

Synchronize any buffered data to the underlying log file.

This syncing is dependent on the behavior of the underlying filesystem and operating system.

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying file system.
---	--

E.52.3.8 `void BiometricEvaluation::IO::LogSheet::setAutoSync (bool state)`

Turn on/off auto-sync of the data. Applications can gain login performance by turning off auto-sysnc, or gain reliability by turning it on.

Parameters

<i>state</i>	When true, the data is sync'd whenever newEntry() is or write() is called. When false, sync() must be called to force a write.
--------------	--

E.52.3.9 `string BiometricEvaluation::IO::LogSheet::sequence (bool comments = false, bool trim = true, int32_t cursor = BE_LOGSHEET_SEQ_NEXT) throw (Error::FileError, Error::ObjectDoesNotExist, Error::StrategyError)`

Sequence through a [LogSheet](#), returning one entry per invocation.

Parameters

<i>comments</i>	Include comments when sequencing
<i>trim</i>	Whether or not to include entry delimiters.
<i>cursor</i>	The location within the sequence to return.

Returns

The contents of the sequenced entry, as was originally given to [write\(\)](#).

Exceptions

<i>Error::FileError</i> , <i>Error</i>	occured while performing file IO .
<i>Error::ObjectDoesNotExist</i>	The LogSheet cannot be found on disk.
<i>Error::StrategyError</i>	Invalid cursor position or the contents of the LogSheet is malformed.

E.52.3.10 `static string BiometricEvaluation::IO::LogSheet::trim (const string & entry)` `[static]`

Trim delimiters from [LogSheet](#) entries.

Works for comments and numbered entries.

Parameters

<i>in</i>	<i>entry</i>	The entry to trim.
-----------	--------------	--------------------

Returns

Delimiter-less entry.

E.52.3.11 `static void BiometricEvaluation::IO::LogSheet::mergeLogSheets (vector< tr1::shared_ptr< LogSheet > > &logSheets) throw (Error::FileError, Error::StrategyError) [static]`

Merge multiple LogSheets into a single [LogSheet](#).

LogSheets 2 - n will be appended to [LogSheet](#) 1.

Parameters

<i>logSheets</i>	LogSheets to merge.
------------------	---------------------

Exceptions

Error::FileError	Error during log sequence.
Error::StrategyError	Error during log sequence.

E.52.3.12 `LogSheet& BiometricEvaluation::IO::LogSheet::operator= (const LogSheet &) [protected]`

Prevent copying of [LogSheet](#) objects

E.52.3.13 `void BiometricEvaluation::IO::LogSheet::updateCursor () throw (Error::FileError) [protected]`

Update the cursor position of the sequence file.

Exceptions

Error::FileError	Error getting file position from sequence file.
----------------------------------	---

E.52.4 Member Data Documentation

E.52.4.1 `const char BiometricEvaluation::IO::LogSheet::CommentDelimiter = '#' [static]`

Delimiter for a comment line in the log sheet.

E.52.4.2 `const char BiometricEvaluation::IO::LogSheet::EntryDelimiter = 'E'` `[static]`

Delimiter for an entry line in the log sheet.

E.52.4.3 `const string BiometricEvaluation::IO::LogSheet::DescriptionTag` `[static]`

The tag for the description string.

E.52.4.4 `const int32_t BiometricEvaluation::IO::LogSheet::BE_LOGSHEET_SEQ_START = 1` `[static]`

Sequence from beginning

E.52.4.5 `const int32_t BiometricEvaluation::IO::LogSheet::BE_LOGSHEET_SEQ_NEXT = 2` `[static]`

Sequence from current position

E.52.4.6 `uint32_t BiometricEvaluation::IO::LogSheet::_entryNumber` `[protected]`

Number of the current entry

E.52.4.7 `auto_ptr<std::fstream> BiometricEvaluation::IO::LogSheet::theLogFile` `[protected]`

Stream used for writing the log file

E.52.4.8 `bool BiometricEvaluation::IO::LogSheet::_autoSync` `[protected]`

Whether or not to [sync\(\)](#) on [write\(\)](#)

E.52.4.9 `tr1::shared_ptr<std::fstream> BiometricEvaluation::IO::LogSheet::_sequenceFile` `[protected]`

Stream used for sequencing

E.52.4.10 `streamoff BiometricEvaluation::IO::LogSheet::_cursor` `[protected]`


Position of the sequencer, relative to SOF

E.53 BiometricEvaluation::Process::Manager Class Reference

An interface for intranode process management classes.

```
#include <be_process_manager.h>
```

Inheritance diagram for BiometricEvaluation::Process::Manager:



Public Member Functions

- [Manager \(\)](#)
Manager constructor.
- virtual `tr1::shared_ptr`
`< WorkerController > addWorker (tr1::shared_ptr< Worker > worker)=0`
Adds a Worker to be managed by this Manager.
- virtual `uint32_t` `getNumCompletedWorkers ()` const throw (Error::StrategyError)
Obtain the number of Workers that have exited.
- virtual `uint32_t` `getNumActiveWorkers ()` const throw (Error::StrategyError)
Obtain the number of Workers that are still working.
- virtual `uint32_t` `getTotalWorkers ()` const
Obtain the number of Workers this class is handling.
- virtual void `startWorkers (bool wait=true, bool communicate=false)=0` throw (Error::ObjectExists, Error::StrategyError)
Begin Worker's work.
- virtual void `startWorker (tr1::shared_ptr< WorkerController > worker, bool wait=true, bool communicate=false)=0` throw (Error::ObjectExists, Error::StrategyError)
Start a Worker.
- virtual void `reset ()` throw (Error::ObjectExists)
Reuse all Workers.
- virtual `int32_t` `stopWorker (tr1::shared_ptr< WorkerController > worker)=0` throw (Error::ObjectDoesNotExist, Error::StrategyError)
Ask Worker to return as soon as possible.
- virtual bool `waitForMessage (tr1::shared_ptr< WorkerController > &sender, int *nextFD=NULL, int numSeconds=-1)` const
Wait for a message from a Worker.
- virtual bool `getNextMessage (tr1::shared_ptr< WorkerController > &sender, Memory::uint8Array &message, int numSeconds=-1)` const throw (Error::ObjectDoesNotExist, Error::StrategyError)
Obtain a message from a Worker.
- virtual void `broadcastMessage (Memory::uint8Array &message)` const throw (Error::StrategyError)
Send one message to all Workers.
- virtual `~Manager ()`
Manager destructor.

Protected Member Functions

- virtual void `_wait ()=0`
Do not return until all spawned processes exited.

Protected Attributes

- `vector< tr1::shared_ptr< WorkerController > > _workers`
- `vector< tr1::shared_ptr< WorkerController > > _pendingExit`

E.53.1 Detailed Description

An interface for intranode process management classes.

E.53.2 Member Function Documentation

E.53.2.1 `virtual tr1::shared_ptr<WorkerController> BiometricEvaluation::Process::Manager::addWorker (tr1::shared_ptr< Worker > worker)` `[pure virtual]`

Adds a [Worker](#) to be managed by this [Manager](#).

Parameters

<i>worker</i>	A Worker instance to run.
---------------	---

Returns

`shared_ptr` to worker.

Implemented in [BiometricEvaluation::Process::ForkManager](#), and [BiometricEvaluation::Process::POSIXThreadManager](#).

E.53.2.2 `virtual uint32_t BiometricEvaluation::Process::Manager::getNumCompletedWorkers () const throw (Error::StrategyError)` `[virtual]`

Obtain the number of Workers that have exited.

Returns

The number of Workers that have exited.

Exceptions

Error::StrategyError	No Workers have started working yet.
--------------------------------------	--------------------------------------

E.53.2.3 `virtual uint32_t BiometricEvaluation::Process::Manager::getNumActiveWorkers () const throw (Error::StrategyError)` `[virtual]`

Obtain the number of Workers that are still working.

Returns

The number of Workers that are still working.

Exceptions

<i>Error::StrategyError</i>	No Workers have started working yet.
---	--------------------------------------

E.53.2.4 `virtual uint32_t BiometricEvaluation::Process::Manager::getTotalWorkers () const` [virtual]

Obtain the number of Workers this class is handling.

Returns

Number of Workers.

E.53.2.5 `virtual void BiometricEvaluation::Process::Manager::startWorkers (bool wait = true, bool communicate = false) throw (Error::ObjectExists, Error::StrategyError)` [pure virtual]

Begin [Worker](#)'s work.

Parameters

in	<i>wait</i>	Whether or not to wait for all Workers to return before returning.
in	<i>communicate</i>	Whether or not to enable communication among the Workers and Managers.

Exceptions

<i>Error::ObjectExists</i>	At least one Worker is already working.
<i>Error::StrategyError</i>	Problem starting Workers.

Implemented in [BiometricEvaluation::Process::ForkManager](#), and [BiometricEvaluation::Process::POSIXThreadManager](#).

E.53.2.6 `virtual void BiometricEvaluation::Process::Manager::startWorker (tr1::shared_ptr< WorkerController > worker, bool wait = true, bool communicate = false) throw (Error::ObjectExists, Error::StrategyError)` [pure virtual]

Start a [Worker](#).

Parameters

	<i>worker</i>	Pointer to a WorkerController that is being managed by this Manager instance.
	<i>wait</i>	Whether or not to wait for this Worker to exit before returning control to the caller.
in	<i>communicate</i>	Whether or not to enable communication among the Workers and Managers.

Exceptions

<i>Error::ObjectExists</i>	worker is already working.
<i>Error::StrategyError</i>	worker is not managed by this Manager instance.

Note

Some implementations of this interface may call the system exit function from this routine. Therefore, the application's implementation of workerMain() should release all resources before returning.

Implemented in [BiometricEvaluation::Process::ForkManager](#), and [BiometricEvaluation::Process::POSIXThreadManager](#).

E.53.2.7 `virtual void BiometricEvaluation::Process::Manager::reset () throw (Error::ObjectExists)`
[virtual]

Reuse all Workers.

Exceptions

<i>Error::ObjectExists</i>	At least one Worker is still working.
--	---

E.53.2.8 `virtual int32_t BiometricEvaluation::Process::Manager::stopWorker (tr1::shared_ptr< WorkerController > worker) throw (Error::ObjectDoesNotExist, Error::StrategyError)`
[pure virtual]

Ask [Worker](#) to return as soon as possible.

Parameters

<i>worker</i>	Pointer to the WorkerController that should be stopped.
---------------	---

Returns

Return code of worker.

Exceptions

<i>Error::ObjectDoesNotExist</i>	worker is not working.
<i>Error::StrategyError</i>	Problem asking worker to stop.

Implemented in [BiometricEvaluation::Process::ForkManager](#), and [BiometricEvaluation::Process::POSIXThreadManager](#).

E.53.2.9 `virtual bool BiometricEvaluation::Process::Manager::waitForMessage (tr1::shared_ptr< WorkerController > & sender, int * nextFD = NULL, int numSeconds = -1) const` [virtual]

Wait for a message from a [Worker](#).

Parameters

out	<i>sender</i>	Reference to a shared pointer of the WorkerController that sent the message.
in, out	<i>nextFD</i>	Location to store a pipe that has data to read.
in	<i>numSeconds</i>	Number of seconds to wait for a message, or < 0 to block.

Returns

true if there is a [Worker](#) sending a message false otherwise or if an error occurred.

E.53.2.10 `virtual bool BiometricEvaluation::Process::Manager::getNextMessage (tr1::shared_ptr< WorkerController > & sender, Memory::uint8Array & message, int numSeconds = -1) const` throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Obtain a message from a [Worker](#).

Parameters

out	<i>sender</i>	Reference to a shared pointer of the WorkerController that sent the message.
out	<i>message</i>	Reference to a buffer to hold the message.
in	<i>numSeconds</i>	Number of seconds to wait for a message, or < 0 to block.

Returns

true if there is a message, false otherwise.

Exceptions

Error::ObjectDoesNotExist	(Unexpected) widowed pipe.
Error::StrategyError	Error receiving message.

E.53.2.11 `virtual void BiometricEvaluation::Process::Manager::broadcastMessage (Memory::uint8Array & message) const` throw (Error::StrategyError) [virtual]

Send one message to all Workers.

Parameters

<i>message</i>	The message to send to all Workers.
----------------	-------------------------------------

Exceptions

<i>Error::StrategyError</i>	Error propagated from the WorkerController .
---	--

E.53.3 Member Data Documentation

E.53.3.1 `vector<tr1::shared_ptr<WorkerController> > BiometricEvaluation::Process::Manager::_workers`
[protected]

Workers that have been added.

E.53.3.2 `vector<tr1::shared_ptr<WorkerController> > BiometricEvaluation::Process::Manager::_pending-Exit` [protected]

Workers that are about to exit (stop requested).

E.54 BiometricEvaluation::IO::ManifestEntry Struct Reference

```
#include <be_io_archiverecstore.h>
```

Public Attributes

- long [offset](#)
- uint64_t [size](#)

E.54.1 Detailed Description

Info about a single archive element

E.54.2 Member Data Documentation

E.54.2.1 long `BiometricEvaluation::IO::ManifestEntry::offset`

The offset from the beginning of the file/memory

E.54.2.2 uint64_t `BiometricEvaluation::IO::ManifestEntry::size`


The length from offset this element spans

E.55 BiometricEvaluation::Error::MemoryError Class Reference

An error occurred when allocating an object.

```
#include <be_error_exception.h>
```

Inheritance diagram for BiometricEvaluation::Error::MemoryError:



Public Member Functions

- [MemoryError](#) ()
- [MemoryError](#) (string info)

E.55.1 Detailed Description

An error occurred when allocating an object.

E.55.2 Constructor & Destructor Documentation

E.55.2.1 BiometricEvaluation::Error::MemoryError::MemoryError ()

Construct a [MemoryError](#) object with the default information string.

E.55.2.2 BiometricEvaluation::Error::MemoryError::MemoryError (string info)


Construct a [MemoryError](#) object with an information string appended to the default information string.

E.56 BiometricEvaluation::Feature::Minutiae Class Reference

A class to represent a set of minutiae data points.

```
#include <be_feature_minutiae.h>
```

Inheritance diagram for BiometricEvaluation::Feature::Minutiae:



Public Member Functions

- virtual MinutiaeFormat::Kind [getFormat](#) () const =0
Obtain the minutiae format kind.

- virtual MinutiaPointSet [getMinutiaPoints](#) () const =0
Obtain the set of finger minutiae data points. The set may be empty.
- virtual RidgeCountItemSet [getRidgeCountItems](#) () const =0
Obtain the set of ridge count data items. The set may be empty.
- virtual CorePointSet [getCores](#) () const =0
Obtains the set of core positions. The set may be empty.
- virtual DeltaPointSet [getDeltas](#) () const =0
Obtains the set of delta positions. The set may be empty.

E.56.1 Detailed Description

A class to represent a set of minutiae data points.

Each set includes the core and delta data points, if they are included in the source record. This class represents an interface that subclasses of this class will implement, providing more information on the minutioe that is specific to the record format represented by that class.

E.57 BiometricEvaluation::Feature::MinutiaeFormat Class Reference

Enumerate the minutiae format standards.

```
#include <be_feature_minutiae.h>
```

Public Types

- enum **Kind** {
 AN2K7 = 0, **IAFIS**, **Cogent**, **Motorola**,
 Sagem, **NEC**, **Identix**, **M1** }

E.57.1 Detailed Description

Enumerate the minutiae format standards.

E.58 BiometricEvaluation::Feature::MinutiaeType Class Reference

Enumerate the types of minutiae: Ridge Ending, Bifurcation, Compound, or other.

```
#include <be_feature_minutiae.h>
```

Public Types

- enum **Kind** { **RidgeEnding** = 0, **Bifurcation**, **Compound**, **Other** }

E.58.1 Detailed Description

Enumerate the types of minutiae: Ridge Ending, Bifurcation, Compound, or other.

E.59 BiometricEvaluation::Feature::MinutiaPoint Struct Reference

Representation of a finger minutiae data point.

```
#include <be_feature_minutiae.h>
```

Public Attributes

- unsigned int **index**
- bool **has_type**
- MinutiaeType::Kind **type**
- [Image::Coordinate](#) **coordinate**
- unsigned int **theta**
- bool **has_quality**
- unsigned int **quality**

E.59.1 Detailed Description


Representation of a finger minutiae data point.

E.60 BiometricEvaluation::Image::NetPBM Class Reference

A NetPBM-encoded image.

```
#include <be_image_netpbm.h>
```

Inheritance diagram for BiometricEvaluation::Image::NetPBM:



Public Types

- enum **Kind** {
 ASCIIPortableBitmap = 1, ASCIIPortableGraymap = 2, ASCIIPortablePixmap = 3, BinaryPortable-
 Bitmap = 4,
 BinaryPortableGraymap = 5, BinaryPortablePixmap = 6 }

Public Member Functions

- **NetPBM** (const uint8_t *data, const uint64_t size) throw (Error::DataError, Error::StrategyError)
- **Memory::AutoArray**< uint8_t > **getRawData** () const throw (Error::DataError)
Accessor for the raw image data. The data returned should not be compressed or encoded.
- **Memory::AutoArray**< uint8_t > **getRawGrayscaleData** (uint8_t depth=8) const throw (Error::DataError, Error::ParameterError)
Accessor for decompressed data in grayscale.

Static Public Member Functions

- static bool **isNetPBM** (const uint8_t *data, const size_t size)
- static void **skipLine** (**Memory::uint8Array** &data, size_t &offset) throw (out_of_range)
Skip an entire line of input, placing offset at the first character after the newline.
- static void **skipComment** (**Memory::uint8Array** &data, size_t &offset) throw (out_of_range)
Skip a block of comments in input.
- static string **getNextValue** (**Memory::uint8Array** &data, size_t &offset, size_t sizeOfValue=0)
Obtain the next space-separated value from data, beginning at offset.
- static **Memory::uint8Array** **ASCIIBitmapTo8Bit** (**Memory::uint8Array** &bitmap, uint32_t width, uint32_t height) throw (out_of_range)
Convert an ASCII bitmap (1-bit depth) buffer into an 8-bit depth buffer.
- static **Memory::uint8Array** **ASCIIPixmapToBinaryPixmap** (**Memory::uint8Array** &ASCIIBuf, uint32_t width, uint32_t height, uint8_t depth, uint32_t maxColor) throw (out_of_range, Error::ParameterError)
Convert an ASCII pixel map buffer into a binary pixel map buffer.
- static **Memory::uint8Array** **BinaryBitmapTo8Bit** (**Memory::uint8Array** &bitmap, uint32_t width, uint32_t height) throw (out_of_range)
Convert an binary bitmap (1-bit depth) buffer into an 8-bit depth buffer.

Additional Inherited Members

E.60.1 Detailed Description

A NetPBM-encoded image.

Note

While a **NetPBM** file can contain more than one image, this class will only support the first image found in any file, also known as the "plain" **NetPBM** format.

E.60.2 Member Function Documentation

E.60.2.1 **Memory::AutoArray**<uint8_t> **BiometricEvaluation::Image::NetPBM::getRawData** () const throw (Error::DataError) [virtual]

Accessor for the raw image data. The data returned should not be compressed or encoded.

Returns

[Raw](#) image data.

Exceptions

Error::DataError	Error decompressing image data.
----------------------------------	---

Note

The raw data returned from this method is encoded at the same bit depth as the compressed data, except in the case of 1-bit (bitmap) images, which are expanded to 8-bit.

Implements [BiometricEvaluation::Image::Image](#).

E.60.2.2 `Memory::AutoArray<uint8_t> BiometricEvaluation::Image::NetPBM::getRawGrayscaleData (uint8_t depth = 8) const throw (Error::DataError, Error::ParameterError) [virtual]`

Accessor for decompressed data in grayscale.

Parameters

<i>depth</i>	The desired bit depth of the resulting raw image. This value may either be 8 or 1.
--------------	--

Returns

[Raw](#) image buffer.

Exceptions

Error::DataError	Error decompressing image data.
Error::ParameterError	Invalid value for depth.

Note

This method does not save a cached copy of the decompressed image because the bit depth of the image can be changed between calls.

This method always returns an image that uses 8 bits to represent a single pixel. depth adjusts the number of pixels used to determine the color of the pixel in the 8 bit container, currently 1 (2 gray levels) or 8 (256 gray levels).

Implements [BiometricEvaluation::Image::Image](#).

E.60.2.3 `static bool BiometricEvaluation::Image::NetPBM::isNetPBM (const uint8_t * data, const size_t size) [static]`

Whether or not data is a netpbm image.

Parameters

<i>in</i>	<i>data</i>	The buffer to check.
<i>in</i>	<i>size</i>	The size of data.

Returns

true if data appears to be a netpbm image, false otherwise.

E.60.2.4 `static void BiometricEvaluation::Image::NetPBM::skipLine (Memory::uint8Array & data, size_t & offset) throw (out_of_range) [static]`

Skip an entire line of input, placing offset at the first character after the newline.

Parameters

<i>data</i>	Buffer with line to be skipped.
<i>offset</i>	Position within data from which the rest of the line should be read.

Exceptions

<i>out_of_range</i>	End of line not encountered before end of data or on last line of data.
---------------------	---

E.60.2.5 `static void BiometricEvaluation::Image::NetPBM::skipComment (Memory::uint8Array & data, size_t & offset) throw (out_of_range) [static]`

Skip a block of comments in input.

Parameters

<i>data</i>	Buffer with comment to be skipped.
<i>offset</i>	Position within data from which the rest of the line should be read.

Exceptions

<i>out_of_range</i>	End of line not encountered before end of data or on last line of data.
---------------------	---

E.60.2.6 `static string BiometricEvaluation::Image::NetPBM::getNextValue (Memory::uint8Array & data, size_t & offset, size_t sizeOfValue = 0) [static]`

Obtain the next space-separated value from data, beginning at offset.

Parameters

<i>data</i>	Buffer where next value will be obtained.
<i>offset</i>	Current starting position within data.
<i>sizeOfValue</i>	In the event that the values in data are not space-separated, return a value when it reaches sizeOfValue length. 0 assumes space-separated.

Returns

Next value from data.

E.60.2.7 static Memory::uint8Array BiometricEvaluation::Image::NetPBM::ASCIIBitmapTo8Bit (Memory::uint8Array & *bitmap*, uint32_t *width*, uint32_t *height*) throw (out_of_range) [static]

Convert an ASCII bitmap (1-bit depth) buffer into an 8-bit depth buffer.

Parameters

<i>bitmap</i>	Bitmap data buffer.
<i>width</i>	Width of image in bitmap.
<i>height</i>	Height of image in bitmap.

Returns

8-bit depth representation of bitmap

Exceptions

<i>out_of_range</i>	Error extracting a value from the bitmap.
---------------------	---

E.60.2.8 static Memory::uint8Array BiometricEvaluation::Image::NetPBM::ASCIIPixmapToBinaryPixmap (Memory::uint8Array & *ASCIIBuf*, uint32_t *width*, uint32_t *height*, uint8_t *depth*, uint32_t *maxColor*) throw (out_of_range, Error::ParameterError) [static]

Convert an ASCII pixel map buffer into a binary pixel map buffer.

Parameters

<i>ASCIIBuf</i>	ASCII pixel map data buffer.
<i>width</i>	Width of image in pixel map.
<i>height</i>	Height of image in pixel map.
<i>depth</i>	Depth of image in pixel map.
<i>maxColor</i>	Maximum color value per pixel. Intensities will be scaled based on this value.

Returns

Binary pixel map representation of the ASCII pixel map in the same depth as the original.

Exceptions

<i>out_of_range</i>	Error extracting a value from the pixel map.
<i>Error::ParameterError</i>	Invalid value for depth, must be a multiple of Image::bitsPerComponent .

E.60.2.9 `static Memory::uint8Array BiometricEvaluation::Image::NetPBM::BinaryBitmapTo8Bit (Memory::uint8Array & bitmap, uint32_t width, uint32_t height) throw (out_of_range) [static]`

Convert an binary bitmap (1-bit depth) buffer into an 8-bit depth buffer.

Parameters

<i>bitmap</i>	Bitmap data buffer.
<i>width</i>	Width of image in bitmap.
<i>height</i>	Height of image in bitmap.

Returns

8-bit depth representation of bitmap

Exceptions


<i>out_of_range</i>	Error extracting a value from the bitmap.
---------------------	---

E.61 BiometricEvaluation::Error::NotImplemented Class Reference

A [NotImplemented](#) object is thrown when the underlying implementation of this interface has not or could not be created.

```
#include <be_error_exception.h>
```

Inheritance diagram for BiometricEvaluation::Error::NotImplemented:



Public Member Functions

- [NotImplemented](#) ()
- [NotImplemented](#) (string info)

E.61.1 Detailed Description

A [NotImplemented](#) object is thrown when the underlying implementation of this interface has not or could not be created.

E.61.2 Constructor & Destructor Documentation

E.61.2.1 BiometricEvaluation::Error::NotImplemented::NotImplemented ()

Construct a [NotImplemented](#) object with the default information string.

E.61.2.2 BiometricEvaluation::Error::NotImplemented::NotImplemented (string *info*)


Construct a [NotImplemented](#) object with an information string appended to the default information string.

E.62 BiometricEvaluation::Error::ObjectDoesNotExist Class Reference

The named object does not exist.

```
#include <be_error_exception.h>
```

Inheritance diagram for BiometricEvaluation::Error::ObjectDoesNotExist:



Public Member Functions

- [ObjectDoesNotExist](#) ()
- [ObjectDoesNotExist](#) (string *info*)

E.62.1 Detailed Description

The named object does not exist.

E.62.2 Constructor & Destructor Documentation

E.62.2.1 BiometricEvaluation::Error::ObjectDoesNotExist::ObjectDoesNotExist ()

Construct a [ObjectDoesNotExist](#) object with the default information string.

E.62.2.2 BiometricEvaluation::Error::ObjectDoesNotExist::ObjectDoesNotExist (string *info*)


Construct a [ObjectDoesNotExist](#) object with an information string appended to the default information string.

E.63 BiometricEvaluation::Error::ObjectExists Class Reference

The named object exists and will not be replaced.

```
#include <be_error_exception.h>
```

Inheritance diagram for BiometricEvaluation::Error::ObjectExists:



Public Member Functions

- [ObjectExists](#) ()
- [ObjectExists](#) (string info)

E.63.1 Detailed Description

The named object exists and will not be replaced.

E.63.2 Constructor & Destructor Documentation

E.63.2.1 BiometricEvaluation::Error::ObjectExists::ObjectExists ()

Construct a [ObjectExists](#) object with the default information string.

E.63.2.2 BiometricEvaluation::Error::ObjectExists::ObjectExists (string info)


Construct a [ObjectExists](#) object with an information string appended to the default information string.

E.64 BiometricEvaluation::Error::ObjectIsClosed Class Reference

The object is closed.

```
#include <be_error_exception.h>
```

Inheritance diagram for BiometricEvaluation::Error::ObjectIsClosed:



Public Member Functions

- [ObjectIsClosed](#) ()

- [ObjectIsClosed](#) (string info)

E.64.1 Detailed Description

The object is closed.

E.64.2 Constructor & Destructor Documentation

E.64.2.1 BiometricEvaluation::Error::ObjectIsClosed::ObjectIsClosed ()

Construct a [ObjectIsClosed](#) object with the default information string.

E.64.2.2 BiometricEvaluation::Error::ObjectIsClosed::ObjectIsClosed (string *info*)


Construct a [ObjectIsClosed](#) object with an information string appended to the default information string.

E.65 BiometricEvaluation::Error::ObjectIsOpen Class Reference

The object is already opened.

```
#include <be_error_exception.h>
```

Inheritance diagram for BiometricEvaluation::Error::ObjectIsOpen:



Public Member Functions

- [ObjectIsOpen](#) ()
- [ObjectIsOpen](#) (string info)

E.65.1 Detailed Description

The object is already opened.

E.65.2 Constructor & Destructor Documentation

E.65.2.1 BiometricEvaluation::Error::ObjectIsOpen::ObjectIsOpen ()

Construct a [ObjectIsOpen](#) object with the default information string.

E.65.2.2 BiometricEvaluation::Error::ObjectIsOpen::ObjectIsOpen (string *info*)

Construct a [ObjectIsOpen](#) object with an information string appended to the default information string.

E.66 BiometricEvaluation::Memory::OrderedMap< Key, T > Class Template Reference

```
#include <be_memory_orderedmap.h>
```

Public Types

- typedef
std::tr1::unordered_map< Key,
T > **container**
- typedef [OrderedMapIterator](#)
< Key, T > **iterator**
- typedef
[OrderedMapConstIterator](#)< Key,
T > **const_iterator**
- typedef container::size_type **size_type**
- typedef container::value_type **value_type**
- typedef Key **key_type**
- typedef T **mapped_type**
- typedef container::key_equal **key_equal**

Public Member Functions

- [OrderedMap](#) ()
- bool [push_back](#) (const value_type &value)
Insert an element at the end of the collection.
- void [erase](#) ([iterator](#) pos)
Remove an element from the collection.
- void [erase](#) (const Key &key)
Remove an element from the collection.
- [iterator](#) [begin](#) ()
- [const_iterator](#) [begin](#) () const
- [iterator](#) [end](#) ()
- [const_iterator](#) [end](#) () const
- size_type [size](#) () const
- bool [keyExists](#) (const Key &key) const
Determine if a value exists in the container.
- const [OrderedMapIterator](#)< Key, T > [find](#) (const Key &key) const
Obtain an iterator to a particular key.
- std::tr1::shared_ptr< value_type > [find_quick](#) (const Key &key) const
- T & [operator](#)[] (const Key &key)

Subscripting operator:

- `key_equal` **key_eq** () const
- [~OrderedMap](#) ()

Friends

- class **OrderedMapIterator**< **Key**, **T** >
- class **OrderedMapConstIterator**< **Key**, **T** >

E.66.1 Detailed Description

template<class Key, class T>class BiometricEvaluation::Memory::OrderedMap< Key, T >

A map where insertion order is preserved and elements are unique.

E.66.2 Constructor & Destructor Documentation

E.66.2.1 template<class Key , class T > BiometricEvaluation::Memory::OrderedMap< Key, T >::OrderedMap ()

Constructor.

E.66.2.2 template<class Key , class T > BiometricEvaluation::Memory::OrderedMap< Key, T >::~~OrderedMap ()

Destructor

E.66.3 Member Function Documentation

E.66.3.1 template<class Key , class T > bool BiometricEvaluation::Memory::OrderedMap< Key, T >::push_back (const value_type & *value*)

Insert an element at the end of the collection.

Parameters

<i>value</i>	Value to insert.
--------------	------------------

Returns

Whether or not the object was inserted.

Note

Complexity: Average case: O(1), worst case O([size\(\)](#)).

E.66.3.2 `template<class Key, class T> void BiometricEvaluation::Memory::OrderedMap< Key, T >::erase (iterator pos)`

Remove an element from the collection.

Parameters

<i>pos</i>	Iterator to element at the position which should be removed.
------------	--

Note

Complexity: Average case: O(1), worst case O([size\(\)](#)).

E.66.3.3 `template<class Key, class T> void BiometricEvaluation::Memory::OrderedMap< Key, T >::erase (const Key & key)`

Remove an element from the collection.

Parameters

<i>pos</i>	Key of the element to remove.
------------	-------------------------------

E.66.3.4 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMap< Key, T >::iterator BiometricEvaluation::Memory::OrderedMap< Key, T >::begin ()`

Returns

Iterator at the first element of the collection.

E.66.3.5 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMap< Key, T >::const_iterator BiometricEvaluation::Memory::OrderedMap< Key, T >::begin () const`

Returns

Iterator at the first element of the collection.

E.66.3.6 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMap< Key, T >::iterator BiometricEvaluation::Memory::OrderedMap< Key, T >::end ()`

Returns

Iterator beyond the last element of the collection.

E.66.3.7 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMap< Key, T >::const_iterator BiometricEvaluation::Memory::OrderedMap< Key, T >::end () const`

Returns

Iterator beyond the last element of the collection.

E.66.3.8 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMap< Key, T >::size_type BiometricEvaluation::Memory::OrderedMap< Key, T >::size () const`

Returns

Number of elements in the collection.

E.66.3.9 `template<class Key, class T > bool BiometricEvaluation::Memory::OrderedMap< Key, T >::keyExists (const Key & key) const`

Determine if a value exists in the container.

Parameters

<i>key</i>	Key to search the container for.
------------	----------------------------------

Returns

Whether or not key exists in this container.

Complexity is O(1).

E.66.3.10 `template<class Key, class T > const BiometricEvaluation::Memory::OrderedMapIterator< Key, T > BiometricEvaluation::Memory::OrderedMap< Key, T >::find (const Key & key) const`

Obtain an iterator to a particular key.

Complexity is O(n).

E.66.3.11 `template<class Key, class T > T & BiometricEvaluation::Memory::OrderedMap< Key, T >::operator[] (const Key & key)`

Subscripting operator.

Parameters

<i>key</i>	Key used to index into the map.
------------	---------------------------------


Returns

Value for key, which may be a new value.

E.67 BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T > Class Template Reference

```
#include <be_memory_orderedmap.h>
```

Inheritance diagram for BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >:

**Public Types**

- typedef std::iterator_traits
< [OrderedMapConstIterator](#) >
::reference **reference**
- typedef const
std::iterator_traits
< [OrderedMapConstIterator](#) >
::reference **const_reference**
- typedef std::iterator_traits
< [OrderedMapConstIterator](#) >
::pointer **pointer**
- typedef const
std::iterator_traits
< [OrderedMapConstIterator](#) >
::pointer **const_pointer**
- typedef std::iterator_traits
< [OrderedMapConstIterator](#) >
::value_type **value_type**
- typedef std::iterator_traits
< [OrderedMapConstIterator](#) >
::difference_type **difference_type**

Public Member Functions

- [OrderedMapConstIterator](#) ()
- [OrderedMapConstIterator](#) (const [OrderedMapIterator](#)< Key, T > &iterator)
- [~OrderedMapConstIterator](#) ()
- const_reference [operator*](#) () const
- const_pointer [operator->](#) () const
- [OrderedMapConstIterator](#) & [operator++](#) ()

- `OrderedMapConstIterator` & `operator++` (int dummy)
- `OrderedMapConstIterator` & `operator--` ()
- `OrderedMapConstIterator` & `operator--` (int dummy)
- `bool operator==` (const `OrderedMapConstIterator` &rhs) const
Test for iterator equality.
- `bool operator!=` (const `OrderedMapConstIterator` &rhs) const
Test for iterator equality.

Friends

- class `OrderedMap< Key, T >`

E.67.1 Detailed Description

`template<class Key, class T>class BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >`

Const Iterator for OrderedMaps.

E.67.2 Constructor & Destructor Documentation

E.67.2.1 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >::OrderedMapConstIterator ()`

Constructor

E.67.2.2 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >::OrderedMapConstIterator (const OrderedMapIterator< Key, T > & iterator)`

Iterator to ConstIterator converter

E.67.2.3 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >::~~OrderedMapConstIterator ()`

Destructor

E.67.3 Member Function Documentation

E.67.3.1 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >::const_reference BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >::operator* () const`

Returns

Reference to the current iterated pair.

E.67.3.2 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >::const_pointer BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >::operator-> () const`

Returns

Pointer to the current iterated pair.

E.67.3.3 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T > & BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >::operator++ ()`

Move to the next pair

E.67.3.4 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T > & BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >::operator++ (int dummy)`

Move to the next pair

E.67.3.5 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T > & BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >::operator-- ()`

Move to the previous pair.

E.67.3.6 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T > & BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >::operator-- (int dummy)`

Move to the previous pair.

E.67.3.7 `template<class Key , class T > bool BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >::operator==(const OrderedMapConstIterator< Key, T > & rhs) const`

Test for iterator equality.

Parameters

<i>rhs</i>	Object on the right-hand side of the expression.
------------	--

Returns

Whether or not this iterator is equivalent to *rhs*.

E.67.3.8 `template<class Key , class T > bool BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >::operator!= (const OrderedMapConstIterator< Key, T > & rhs) const`

Test for iterator equality.

Parameters

<i>rhs</i>	Object on the right-hand side of the expression.
------------	--


Returns

Whether or not this iterator is not equivalent to rhs.

E.68 BiometricEvaluation::Memory::OrderedMapIterator< Key, T > Class Template Reference

```
#include <be_memory_orderedmap.h>
```

Inheritance diagram for BiometricEvaluation::Memory::OrderedMapIterator< Key, T >:



Public Types

- typedef std::iterator_traits< [OrderedMapIterator](#) >::reference **reference**
- typedef std::iterator_traits< [OrderedMapIterator](#) >::pointer **pointer**
- typedef std::iterator_traits< [OrderedMapIterator](#) >::value_type **value_type**
- typedef std::iterator_traits< [OrderedMapIterator](#) >::difference_type **difference_type**

Public Member Functions

- [OrderedMapIterator](#) ()
- [~OrderedMapIterator](#) ()
- reference [operator*](#) () const

- pointer `operator-> ()` const
- `OrderedMapIterator` & `operator++ ()`
- `OrderedMapIterator` & `operator++ (int dummy)`
- `OrderedMapIterator` & `operator-- ()`
- `OrderedMapIterator` & `operator-- (int dummy)`
- bool `operator==` (const `OrderedMapIterator` &rhs) const
Test for iterator equality.
- bool `operator!=` (const `OrderedMapIterator` &rhs) const
Test for iterator equality.

Friends

- class `OrderedMap< Key, T >`
- class `OrderedMapConstIterator< Key, T >`

E.68.1 Detailed Description

`template<class Key, class T>class BiometricEvaluation::Memory::OrderedMapIterator< Key, T >`

Iterator for OrderedMaps.

E.68.2 Constructor & Destructor Documentation

E.68.2.1 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapIterator< Key, T >::OrderedMapIterator ()`

Constructor

E.68.2.2 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapIterator< Key, T >::~~OrderedMapIterator ()`

Destructor

E.68.3 Member Function Documentation

E.68.3.1 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapIterator< Key, T >::reference BiometricEvaluation::Memory::OrderedMapIterator< Key, T >::operator* () const`

Returns

Reference to the current iterated pair.

E.68.3.2 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapIterator< Key, T >::pointer BiometricEvaluation::Memory::OrderedMapIterator< Key, T >::operator-> () const`

Returns

Pointer to the current iterated pair.

E.68.3.3 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapIterator< Key, T > & BiometricEvaluation::Memory::OrderedMapIterator< Key, T >::operator++ ()`

Move to the next pair

E.68.3.4 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapIterator< Key, T > & BiometricEvaluation::Memory::OrderedMapIterator< Key, T >::operator++ (int dummy)`

Move to the next pair

E.68.3.5 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapIterator< Key, T > & BiometricEvaluation::Memory::OrderedMapIterator< Key, T >::operator-- ()`

Move to the previous pair.

E.68.3.6 `template<class Key , class T > BiometricEvaluation::Memory::OrderedMapIterator< Key, T > & BiometricEvaluation::Memory::OrderedMapIterator< Key, T >::operator-- (int dummy)`

Move to the previous pair.

E.68.3.7 `template<class Key , class T > bool BiometricEvaluation::Memory::OrderedMapIterator< Key, T >::operator== (const OrderedMapIterator< Key, T > & rhs) const`

Test for iterator equality.

Parameters

<i>rhs</i>	Object on the right-hand side of the expression.
------------	--

Returns

Whether or not this iterator is equivalent to rhs.

E.68.3.8 `template<class Key , class T > bool BiometricEvaluation::Memory::OrderedMapIterator< Key, T >::operator!= (const OrderedMapIterator< Key, T > & rhs) const`

Test for iterator equality.

Parameters

<i>rhs</i>	Object on the right-hand side of the expression.
------------	--

Returns


Whether or not this iterator is not equivalent to rhs.

E.69 BiometricEvaluation::Error::ParameterError Class Reference

An invalid parameter was passed to a constructor or method.

```
#include <be_error_exception.h>
```

Inheritance diagram for BiometricEvaluation::Error::ParameterError:

**Public Member Functions**

- [ParameterError](#) ()
- [ParameterError](#) (string info)

E.69.1 Detailed Description

An invalid parameter was passed to a constructor or method.

E.69.2 Constructor & Destructor Documentation**E.69.2.1 BiometricEvaluation::Error::ParameterError::ParameterError ()**

Construct a [ParameterError](#) object with the default information string.

E.69.2.2 BiometricEvaluation::Error::ParameterError::ParameterError (string info)

Construct a [ParameterError](#) object with an information string appended to the default information string.

E.70 BiometricEvaluation::Finger::PatternClassification Class Reference

Pattern classification codes.

```
#include <be_finger.h>
```

Public Types

- enum **Kind** {
 PlainArch = 0, **TentedArch**, **RadialLoop**, **UlnarLoop**,
 PlainWhorl, **CentralPocketLoop**, **DoubleLoop**, **AccidentalWhorl**,
 Whorl, **RightSlantLoop**, **LeftSlantLoop**, **Scar**,
 Amputation, **Unknown** }

E.70.1 Detailed Description

Pattern classification codes.

E.71 BiometricEvaluation::Feature::AN2K7Minutiae::PatternClassification Class Reference

Pattern classification codes.

```
#include <be_feature_an2k7minutiae.h>
```

Classes

- struct [Entry](#)

Public Types

- typedef struct [Entry](#) **Entry**

E.71.1 Detailed Description


Pattern classification codes.

E.72 BiometricEvaluation::Image::PNG Class Reference

A PNG-encoded image.

```
#include <be_image_png.h>
```

Inheritance diagram for BiometricEvaluation::Image::PNG:



Public Member Functions

- **PNG** (const uint8_t *data, const uint64_t size) throw (Error::DataError, Error::StrategyError)
- **Memory::AutoArray**< uint8_t > **getRawData** () const throw (Error::DataError)
Accessor for the raw image data. The data returned should not be compressed or encoded.
- **Memory::AutoArray**< uint8_t > **getRawGrayscaleData** (uint8_t depth=8) const throw (Error::DataError, Error::ParameterError)
Accessor for decompressed data in grayscale.

Static Public Member Functions

- static bool **isPNG** (const uint8_t *data)

Additional Inherited Members

E.72.1 Detailed Description

A PNG-encoded image.

E.72.2 Member Function Documentation

E.72.2.1 **Memory::AutoArray**<uint8_t> **BiometricEvaluation::Image::PNG::getRawData** () const throw (Error::DataError) [virtual]

Accessor for the raw image data. The data returned should not be compressed or encoded.

Returns

Raw image data.

Exceptions

Error::DataError	Error decompressing image data.
-------------------------	---------------------------------

Implements **BiometricEvaluation::Image::Image**.

E.72.2.2 **Memory::AutoArray**<uint8_t> **BiometricEvaluation::Image::PNG::getRawGrayscaleData** (uint8_t *depth* = 8) const throw (Error::DataError, Error::ParameterError) [virtual]

Accessor for decompressed data in grayscale.

Parameters

<i>depth</i>	The desired bit depth of the resulting raw image. This value may either be 8 or 1.
--------------	--

Returns

[Raw](#) image buffer.

Exceptions

Error::DataError	Error decompressing image data.
Error::ParameterError	Invalid value for depth.

Note

This method does not save a cached copy of the decompressed image because the bit depth of the image can be changed between calls.

This method always returns an image that uses 8 bits to represent a single pixel. depth adjusts the number of pixels used to determine the color of the pixel in the 8 bit container, currently 1 (2 gray levels) or 8 (256 gray levels).

Implements [BiometricEvaluation::Image::Image](#).

E.72.2.3 static bool BiometricEvaluation::Image::PNG::isPNG (const uint8_t* *data*) [static]

Whether or not data is a [PNG](#) image.

Parameters

in	<i>data</i>	The buffer to check.
----	-------------	----------------------

Returns

true if data appears to be a [PNG](#) image, false otherwise

E.73 BiometricEvaluation::Finger::Position Class Reference

[Finger](#) position codes.

```
#include <be_finger.h>
```

Public Types

- enum **Kind** {
Unknown = 0, **RightThumb** = 1, **RightIndex** = 2, **RightMiddle** = 3,
RightRing = 4, **RightLittle** = 5, **LeftThumb** = 6, **LeftIndex** = 7,
LeftMiddle = 8, **LeftRing** = 9, **LeftLittle** = 10, **PlainRightThumb** = 11,
PlainLeftThumb = 12, **PlainRightFourFingers** = 13, **PlainLeftFourFingers** = 14, **LeftRightThumbs** = 15,
EJI = 19 }

E.73.1 Detailed Description

[Finger](#) position codes.


These codes match those in ANSI/NIST. Other minutiae formats may have to map codes into this set.

E.74 BiometricEvaluation::Process::POSIXThreadManager Class Reference

[Manager](#) implementation that starts Workers in POSIX threads.

```
#include <be_process_posixthreadmanager.h>
```

Inheritance diagram for BiometricEvaluation::Process::POSIXThreadManager:



Public Member Functions

- [POSIXThreadManager](#) ()
- `tr1::shared_ptr< WorkerController > addWorker (tr1::shared_ptr< Worker > worker)`
Adds a [Worker](#) to be managed by this [Manager](#).
- `void startWorkers (bool wait=true, bool communicate=false) throw (Error::ObjectExists, Error::StrategyError)`
Begin [Worker](#)'s work.
- `void startWorker (tr1::shared_ptr< WorkerController > worker, bool wait=true, bool communicate=false) throw (Error::ObjectExists, Error::StrategyError)`
Start a [Worker](#).
- `int32_t stopWorker (tr1::shared_ptr< WorkerController > workerController) throw (Error::ObjectDoesNotExist, Error::StrategyError)`
Ask [Worker](#) to exit.
- `~POSIXThreadManager ()`
~POSIXThreadManager destructor.

Additional Inherited Members

E.74.1 Detailed Description

[Manager](#) implementation that starts Workers in POSIX threads.

E.74.2 Constructor & Destructor Documentation

E.74.2.1 BiometricEvaluation::Process::POSIXThreadManager::POSIXThreadManager ()

[POSIXThreadManager](#) constructor.

E.74.3 Member Function Documentation

E.74.3.1 `tr1::shared_ptr<WorkerController> BiometricEvaluation::Process::POSIXThreadManager::addWorker (tr1::shared_ptr< Worker > worker) [virtual]`

Adds a [Worker](#) to be managed by this [Manager](#).

Parameters

<i>worker</i>	A Worker instance to run.
---------------	---

Returns

`shared_ptr` to `worker`.

Implements [BiometricEvaluation::Process::Manager](#).

E.74.3.2 `void BiometricEvaluation::Process::POSIXThreadManager::startWorkers (bool wait = true, bool communicate = false) throw (Error::ObjectExists, Error::StrategyError) [virtual]`

Begin [Worker](#)'s work.

Parameters

<i>in</i>	<i>wait</i>	Whether or not to wait for all Workers to return before returning.
<i>in</i>	<i>communicate</i>	Whether or not to enable communication among the Workers and Managers.

Exceptions

Error::ObjectExists	At least one Worker is already working.
Error::StrategyError	Problem starting the Workers.

Implements [BiometricEvaluation::Process::Manager](#).

E.74.3.3 `void BiometricEvaluation::Process::POSIXThreadManager::startWorker (tr1::shared_ptr< WorkerController > worker, bool wait = true, bool communicate = false) throw (Error::ObjectExists, Error::StrategyError) [virtual]`

Start a [Worker](#).

Parameters

<i>worker</i>	Pointer to a WorkerController that is being managed by this Manager instance.
<i>wait</i>	Whether or not to wait for this Worker to exit before returning control to the caller.
<i>communicate</i>	Whether or not to enable communication among the Workers and Managers.

Exceptions

<i>Error::ObjectExists</i>	worker is already working.
<i>Error::StrategyError</i>	worker is not managed by this Manager instance.

Implements [BiometricEvaluation::Process::Manager](#).

E.74.3.4 `int32_t BiometricEvaluation::Process::POSIXThreadManager::stopWorker (tr1::shared_ptr< WorkerController > workerController) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Ask [Worker](#) to exit.

Parameters

<i>worker-Controller</i>	Pointer to the WorkerController that should be stopped.
--------------------------	---

Returns

Exit status of worker.

Exceptions

<i>Error::ObjectDoesNotExist</i>	worker is not working.
<i>Error::StrategyError</i>	Problem sending the signal.


Implements [BiometricEvaluation::Process::Manager](#).

E.75 BiometricEvaluation::Process::POSIXThreadWorkerController Class Reference

Decorated [Worker](#) returned from a [Process::POSIXThreadManager](#).

```
#include <be_process_posixthreadmanager.h>
```

Inheritance diagram for BiometricEvaluation::Process::POSIXThreadWorkerController:

**Public Member Functions**

- void [reset](#) () throw (Error::ObjectExists)

Reuse the [Worker](#).

- bool [isWorking](#) () const
Obtain whether or not [Worker](#) is working.
- [~POSIXThreadWorkerController](#) ()
[POSIXThreadWorkerController](#) destructor.

Friends

- class [POSIXThreadManager](#)

Additional Inherited Members

E.75.1 Detailed Description

Decorated [Worker](#) returned from a [Process::POSIXThreadManager](#).

E.75.2 Member Function Documentation

E.75.2.1 void [BiometricEvaluation::Process::POSIXThreadWorkerController::reset](#) () throw
 ([Error::ObjectExists](#)) [virtual]

Reuse the [Worker](#).

Exceptions

Error::ObjectExists	The previously started Worker is still running.
-------------------------------------	---

Reimplemented from [BiometricEvaluation::Process::WorkerController](#).

E.75.2.2 bool [BiometricEvaluation::Process::POSIXThreadWorkerController::isWorking](#) () const
 [virtual]

Obtain whether or not [Worker](#) is working.

Returns

Whether or not the [Worker](#) is working.

Implements [BiometricEvaluation::Process::WorkerController](#).

E.76 BiometricEvaluation::Finger::AN2KViewVariableResolution::PrintPosition-Coordinate Struct Reference

Offsets to the bounding boxes for the EJI, full finger views, or EJI segments.

```
#include <be_finger_an2kview_varres.h>
```

Public Member Functions

- [PrintPositionCoordinate](#) (FingerImageCode::Kind &[fingerView](#), FingerImageCode::Kind &[segment](#), Image::CoordinateSet &[coordinates](#))

Construct a [PrintPositionCoordinate](#).

Public Attributes

- FingerImageCode::Kind [fingerView](#)
- FingerImageCode::Kind [segment](#)
- Image::CoordinateSet [coordinates](#)

E.76.1 Detailed Description

Offsets to the bounding boxes for the EJI, full finger views, or EJI segments.

E.76.2 Constructor & Destructor Documentation

- E.76.2.1** [BiometricEvaluation::Finger::AN2KViewVariableResolution::PrintPositionCoordinate::PrintPositionCoordinate](#) (FingerImageCode::Kind & *fingerView*, FingerImageCode::Kind & *segment*, Image::CoordinateSet & *coordinates*)

Construct a [PrintPositionCoordinate](#).

Parameters

<i>fingerView</i>	The full finger view being referred to.
<i>segment</i>	Location of a segment within fingerView. If segment is NA, the image referred to is the entire image or tip.
<i>coordinates</i>	Two coordinates creating a bounding rectangle (top left vertex, lower right vertex).

E.76.3 Member Data Documentation

- E.76.3.1** [FingerImageCode::Kind BiometricEvaluation::Finger::AN2KViewVariableResolution::PrintPositionCoordinate::fingerView](#)

Full finger view being bounded

- E.76.3.2** [FingerImageCode::Kind BiometricEvaluation::Finger::AN2KViewVariableResolution::PrintPositionCoordinate::segment](#)

Segment within full finger view bound

- E.76.3.3** [Image::CoordinateSet BiometricEvaluation::Finger::AN2KViewVariableResolution::PrintPositionCoordinate::coordinates](#)


Two coordinates forming bounding box

E.77 BiometricEvaluation::IO::Properties Class Reference

Maintain key/value pairs of strings, with each property matched to one value.

```
#include <be_io_properties.h>
```

Inheritance diagram for BiometricEvaluation::IO::Properties:



Public Types

- typedef
PropertiesMap::const_iterator [const_iterator](#)

Public Member Functions

- [Properties](#) (uint8_t mode=IO::READWRITE)
Construct a new [Properties](#) object.
- [Properties](#) (const uint8_t *buffer, const size_t size, uint8_t mode=IO::READWRITE) throw (Error::StrategyError)
Construct a new [Properties](#) object from the contents of a buffer.
- virtual void [setProperty](#) (const string &property, const string &value) throw (Error::StrategyError)
Set a property with a value.
- virtual void [setPropertyFromInteger](#) (const string &property, int64_t value) throw (Error::StrategyError)
Set a property with an integer value.
- virtual void [setPropertyFromDouble](#) (const string &property, double value) throw (Error::StrategyError)
Set a property with a double value.
- virtual void [removeProperty](#) (const string &property) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Remove a property.
- virtual string [getProperty](#) (const string &property) const throw (Error::ObjectDoesNotExist)
Retrieve a property value as a string object.
- virtual int64_t [getPropertyAsInteger](#) (const string &property) const throw (Error::ObjectDoesNotExist, Error::ConversionError)
Retrieve a property value as an integer value.
- virtual double [getPropertyAsDouble](#) (const string &property) const throw (Error::ObjectDoesNotExist)
Retrieve a property value as a double value.
- [const_iterator begin](#) () const
Obtain iterator to the first property.
- [const_iterator end](#) () const

- virtual [~Properties](#) ()
Obtain iterator to one past the last property.

Protected Member Functions

- uint8_t [getMode](#) () const
Obtain the mode of the [Properties](#) object.
- void [initWithBuffer](#) (const [Memory::uint8Array](#) &buffer) throw (Error::StrategyError)
Initialize the PropertiesMap with the contents of a properly formatted buffer.
- void [initWithBuffer](#) (const uint8_t *const buffer, size_t size) throw (Error::StrategyError)
Initialize the PropertiesMap with the contents of a properly formatted buffer.

E.77.1 Detailed Description

Maintain key/value pairs of strings, with each property matched to one value.

E.77.2 Member Typedef Documentation

E.77.2.1 typedef PropertiesMap::const_iterator BiometricEvaluation::IO::Properties::const_iterator

Convenience const iterator over a [Properties](#)

E.77.3 Constructor & Destructor Documentation

E.77.3.1 BiometricEvaluation::IO::Properties::Properties (uint8_t mode = IO::READWRITE)

Construct a new [Properties](#) object.

Parameters

in	<i>mode</i>	The read/write mode of the object.
----	-------------	------------------------------------

E.77.3.2 BiometricEvaluation::IO::Properties::Properties (const uint8_t * buffer, const size_t size, uint8_t mode = IO::READWRITE) throw (Error::StrategyError)

Construct a new [Properties](#) object from the contents of a buffer.

The format of the buffer can be seen in [PropertiesFile](#).

Parameters

in	<i>buffer</i>	A buffer that contains the contents of a Property file.
in	<i>size</i>	The size of buffer.
in	<i>mode</i>	The read/write mode of the object.

Exceptions

<i>Error::StrategyError</i>	A line in the properties file is malformed.
---	---

E.77.3.3 virtual BiometricEvaluation::IO::Properties::~~Properties () [virtual]

Destructor

E.77.4 Member Function Documentation

E.77.4.1 virtual void BiometricEvaluation::IO::Properties::setProperty (const string & *property*, const string & *value*) throw (Error::StrategyError) [virtual]

Set a property with a value.

Both the property and value will have leading and trailing whitespace removed. If the property already exists in the set, its value will be replaced with the new value; otherwise, the property will be created.

Parameters

in	<i>property</i>	The name of the property to set.
in	<i>value</i>	The value associated with the property.

Exceptions

<i>Error::StrategyError</i>	The Properties object is read-only.
---	---

E.77.4.2 virtual void BiometricEvaluation::IO::Properties::setPropertyFromInteger (const string & *property*, int64_t *value*) throw (Error::StrategyError) [virtual]

Set a property with an integer value.

The property will have leading and trailing whitespace removed. If the property already exists in the set, its value will be replaced with the new value; otherwise the property will be created.

Parameters

in	<i>property</i>	The name of the property to set.
in	<i>value</i>	The value associated with the property.

Exceptions

<i>Error::StrategyError</i>	The Properties object is read-only.
---	---

E.77.4.3 virtual void BiometricEvaluation::IO::Properties::setPropertyFromDouble (const string & *property*, double *value*) throw (Error::StrategyError) [virtual]

Set a property with a double value.

The property will have leading and trailing whitespace removed. If the property already exists in the set, its value will be replaced with the new value; otherwise the property will be created.

Parameters

in	<i>property</i>	The name of the property to set.
in	<i>value</i>	The value associated with the property.

Exceptions

<i>Error::StrategyError</i>	The <i>Properties</i> object is read-only.
---	--

E.77.4.4 virtual void BiometricEvaluation::IO::Properties::removeProperty (const string & *property*) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Remove a property.

Parameters

in	<i>property</i>	The name of the property to set.
----	-----------------	----------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	The named property does not exist.
<i>Error::StrategyError</i>	The <i>Properties</i> object is read-only.

E.77.4.5 virtual string BiometricEvaluation::IO::Properties::getProperty (const string & *property*) const throw (Error::ObjectDoesNotExist) [virtual]

Retrieve a property value as a string object.

Parameters

in	<i>property</i>	The name of the property to get.
----	-----------------	----------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	The named property does not exist.
--	------------------------------------

E.77.4.6 virtual int64_t BiometricEvaluation::IO::Properties::getPropertyAsInteger (const string & *property*) const throw (Error::ObjectDoesNotExist, Error::ConversionError) [virtual]

Retrieve a property value as an integer value.

Integer value strings for properties can represent either decimal or hexadecimal values, which must be preceded

with either "0x" or "0X".

Parameters

<i>in</i>	<i>property</i>	The name of the property to get.
-----------	-----------------	----------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	The named property does not exist.
<i>Error::ConversionError</i>	The property value cannot be converted, usually due to non-numeric characters in the string.

E.77.4.7 `virtual double BiometricEvaluation::IO::Properties::getPropertyAsDouble (const string & property) const throw (Error::ObjectDoesNotExist) [virtual]`

Retrieve a property value as a double value.

Parameters

<i>in</i>	<i>property</i>	The name of the property to get.
-----------	-----------------	----------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	The named property does not exist.
--	------------------------------------

E.77.4.8 `const_iterator BiometricEvaluation::IO::Properties::begin () const`

Obtain iterator to the first property.

Returns

Iterator to first property.

E.77.4.9 `const_iterator BiometricEvaluation::IO::Properties::end () const`

Obtain iterator to one past the last property.

Returns

Iterator one past the last property.

E.77.4.10 `uint8_t BiometricEvaluation::IO::Properties::getMode () const [protected]`

Obtain the mode of the [Properties](#) object.

Returns

Mode (IO::READONLY or IO::READWRITE)

E.77.4.11 `void BiometricEvaluation::IO::Properties::initWithBuffer (const Memory::uint8Array & buffer)
throw (Error::StrategyError) [protected]`

Initialize the PropertiesMap with the contents of a properly formatted buffer.

This method ensures that the PropertiesMap contains only the properties found within the buffer.

Parameters

<i>buffer</i>	Contents of a properties file.
---------------	--------------------------------

Exceptions

<i>Error::StrategyError</i>	A line of the buffer is malformed.
---	------------------------------------

E.77.4.12 `void BiometricEvaluation::IO::Properties::initWithBuffer (const uint8_t *const buffer, size_t size)
throw (Error::StrategyError) [protected]`

Initialize the PropertiesMap with the contents of a properly formatted buffer.

This method ensures that the PropertiesMap contains only the properties found within the buffer.

Parameters

<i>buffer</i>	Contents of a properties file.
<i>size</i>	Size of the buffer.

Exceptions


<i>Error::StrategyError</i>	A line of the buffer is malformed.
---	------------------------------------

E.78 BiometricEvaluation::IO::PropertiesFile Class Reference

A [Properties](#) object persisted in an file on disk.

```
#include <be_io_propertiesfile.h>
```

Inheritance diagram for BiometricEvaluation::IO::PropertiesFile:



Public Member Functions

- [PropertiesFile](#) (const string &filename, uint8_t mode=IO::READWRITE) throw (Error::FileError, Error::StrategyError)
Construct a new [Properties](#) object from an existing or to be created properties file. The constructor will create the file when it does not exist.
- void [sync](#) () throw (Error::FileError, Error::StrategyError)
Write the properties to the underlying file, synchronizing the in-memory and on-disk versions.
- void [changeName](#) (const string &filename) throw (Error::StrategyError)
Change the name of the [Properties](#), which means changing the name of the underlying file that stores the properties. The empty string ("") can be used to indicate no backing file.
- [~PropertiesFile](#) ()

Additional Inherited Members

E.78.1 Detailed Description

A [Properties](#) object persisted in an file on disk.

An example file might look like this:

```
*      Name = John Smith
*      Age = 32
*      Favorite Hex Number = 0xffff
*
```

For property keys and values, leading and trailing whitespace is removed, therefore the call

```
props->setProperty("  My property  ", "  A Value  ");
```

results in an entry in the property file as

```
*      My property = A value
*
```

Therefore, the property names "Foo", " Foo", "Foo " are equivalent.

E.78.2 Constructor & Destructor Documentation

E.78.2.1 [BiometricEvaluation::IO::PropertiesFile::PropertiesFile](#) (const string & filename, uint8_t mode = IO::READWRITE) throw (Error::FileError, Error::StrategyError)

Construct a new [Properties](#) object from an existing or to be created properties file. The constructor will create the file when it does not exist.

Parameters

in	<i>filename</i>	The name of the file to store the properties.
in	<i>mode</i>	The read/write mode of the object.

Exceptions

<i>Error::StrategyError</i>	A line in the properties file is malformed.
<i>Error::FileError</i>	An error occurred when using the underlying storage system.

E.78.2.2 BiometricEvaluation::IO::PropertiesFile::~~PropertiesFile ()

Destructor

E.78.3 Member Function Documentation**E.78.3.1 void BiometricEvaluation::IO::PropertiesFile::sync () throw (Error::FileError, Error::StrategyError)**

Write the properties to the underlying file, synchronizing the in-memory and on-disk versions.

Exceptions

<i>Error::FileError</i>	An error occurred when using the underlying storage system.
<i>Error::StrategyError</i>	The object was constructed with NULL as the file name, or is read-only.

E.78.3.2 void BiometricEvaluation::IO::PropertiesFile::changeName (const string & filename) throw (Error::StrategyError)

Change the name of the [Properties](#), which means changing the name of the underlying file that stores the properties. The empty string ("") can be used to indicate no backing file.

Note

No check is made that the file is writeable at this time.

Parameters

in	<i>filename</i>	The name of the properties file.
----	-----------------	----------------------------------

Exceptions


<i>Error::StrategyError</i>	The object is read-only.
---	--------------------------

E.79 BiometricEvaluation::Image::Raw Class Reference

An image with no encoding or compression.

```
#include <be_image_raw.h>
```

Inheritance diagram for BiometricEvaluation::Image::Raw:



Public Member Functions

- **Raw** (const uint8_t *data, const uint64_t size, const [Size](#) dimensions, const unsigned int depth, const [Resolution](#) resolution)
- [Memory::AutoArray](#)< uint8_t > **getData** () const
- [Memory::AutoArray](#)< uint8_t > **getRawData** () const throw (Error::DataError)
Accessor for the raw image data. The data returned should not be compressed or encoded.
- [Memory::AutoArray](#)< uint8_t > **getRawGrayscaleData** (uint8_t depth=8) const throw (Error::DataError, Error::ParameterError)
Accessor for decompressed data in grayscale.

Additional Inherited Members

E.79.1 Detailed Description

An image with no encoding or compression.

E.79.2 Member Function Documentation

E.79.2.1 [Memory::AutoArray](#)<uint8_t> **BiometricEvaluation::Image::Raw::getRawData** () const throw (Error::DataError) [virtual]

Accessor for the raw image data. The data returned should not be compressed or encoded.

Returns

[Raw](#) image data.

Exceptions

Error::DataError	Error decompressing image data.
----------------------------------	---------------------------------

Implements [BiometricEvaluation::Image::Image](#).

E.79.2.2 [Memory::AutoArray](#)<uint8_t> **BiometricEvaluation::Image::Raw::getRawGrayscaleData** (uint8_t depth = 8) const throw (Error::DataError, Error::ParameterError) [virtual]

Accessor for decompressed data in grayscale.

Parameters

<i>depth</i>	The desired bit depth of the resulting raw image. This value may either be 8 or 1.
--------------	--

Returns

[Raw](#) image buffer.

Exceptions

Error::DataError	Error decompressing image data.
Error::ParameterError	Invalid value for depth.

Note

This method does not save a cached copy of the decompressed image because the bit depth of the image can be changed between calls.

This method always returns an image that uses 8 bits to represent a single pixel. *depth* adjusts the number of pixels used to determine the color of the pixel in the 8 bit container, currently 1 (2 gray levels) or 8 (256 gray levels).


Implements [BiometricEvaluation::Image::Image](#).

E.80 BiometricEvaluation::IO::RecordStore Class Reference

A class to represent a data storage mechanism.

```
#include <be_io_recordstore.h>
```

Inheritance diagram for BiometricEvaluation::IO::RecordStore:

**Public Member Functions**

- [RecordStore](#) (const string &name, const string &description, const string &type, const string &parentDir) throw (Error::ObjectExists, Error::StrategyError)
- [RecordStore](#) (const string &name, const string &parentDir, uint8_t mode=READWRITE) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- string [getName](#) () const
- string [getDescription](#) () const
- unsigned int [getCount](#) () const
- virtual void [changeName](#) (const string &name) throw (Error::ObjectExists, Error::StrategyError)
- virtual void [changeDescription](#) (const string &description) throw (Error::StrategyError)
- virtual uint64_t [getSpaceUsed](#) () const throw (Error::StrategyError)
- *Obtain real storage utilization.*
- virtual void [sync](#) () const throw (Error::StrategyError)

- virtual void [insert](#) (const string &key, const void *const data, const uint64_t size)=0 throw (Error::ObjectExists, Error::StrategyError)
- virtual void [insert](#) (const string &key, const [Memory::uint8Array](#) &data) throw (Error::ObjectExists, Error::StrategyError)
- virtual void [remove](#) (const string &key)=0 throw (Error::ObjectDoesNotExist, Error::StrategyError)
- virtual uint64_t [read](#) (const string &key, void *const data) const =0 throw (Error::ObjectDoesNotExist, Error::StrategyError)
- virtual uint64_t [read](#) (const string &key, [Memory::uint8Array](#) &data) const throw (Error::ObjectDoesNotExist, Error::StrategyError)

Read a complete record from a store.

- virtual void [replace](#) (const string &key, const void *const data, const uint64_t size)=0 throw (Error::ObjectDoesNotExist, Error::StrategyError)
- virtual void [replace](#) (const string &key, const [Memory::uint8Array](#) &data) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- virtual uint64_t [length](#) (const string &key) const =0 throw (Error::ObjectDoesNotExist, Error::StrategyError)
- virtual void [flush](#) (const string &key) const =0 throw (Error::ObjectDoesNotExist, Error::StrategyError)
- virtual uint64_t [sequence](#) (string &key, void *const data=NULL, int cursor=[BE_RECSTORE_SEQ_NEXT](#))=0 throw (Error::ObjectDoesNotExist, Error::StrategyError)

Sequence through a [RecordStore](#), returning the key/data pairs.

- virtual uint64_t [sequence](#) (string &key, [Memory::uint8Array](#) &data, int cursor=[BE_RECSTORE_SEQ_NEXT](#)) throw (Error::ObjectDoesNotExist, Error::StrategyError)

Sequence through a [RecordStore](#), returning the key/data pairs.

- virtual void [setCursorAtKey](#) (string &key)=0 throw (Error::ObjectDoesNotExist, Error::StrategyError)
- virtual bool [containsKey](#) (const string &key) const

Determines whether the [RecordStore](#) contains an element with the specified key.

Static Public Member Functions

- static tr1::shared_ptr
< [RecordStore](#) > [openRecordStore](#) (const string &name, const string &parentDir, uint8_t mode=READWRITE) throw (Error::ObjectDoesNotExist, Error::StrategyError)

Open an existing [RecordStore](#) and return a managed pointer to the the object representing that store.

- static tr1::shared_ptr
< [RecordStore](#) > [createRecordStore](#) (const string &name, const string &description, const string &type, const string &destDir) throw (Error::ObjectExists, Error::StrategyError)

Create a new [RecordStore](#) and return a managed pointer to the the object representing that store.

- static void [removeRecordStore](#) (const string &name, const string &parentDir) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- static void [mergeRecordStores](#) (const string &mergedName, const string &mergedDescription, const string &parentDir, const string &type, const vector< string > &path) throw (Error::ObjectExists, Error::StrategyError)

Create a new [RecordStore](#) that contains the contents of several other [RecordStores](#).

Static Public Attributes

- static const string [INVALIDKEYCHARS](#)
- static const char [KEY_SEGMENT_SEPARATOR](#) = '&'
- static const uint64_t [KEY_SEGMENT_START](#) = 1
- static const string [CONTROLFILENAME](#)
- static const string [NAMEPROPERTY](#)
- static const string [DESCRIPTIONPROPERTY](#)
- static const string [COUNTPROPERTY](#)
- static const string [TYPEPROPERTY](#)
- static const string [BERKELEYDBTYPE](#)
- static const string [ARCHIVETYPE](#)
- static const string [FILETYPE](#)
- static const string [SQLITETYPE](#)
- static const string [COMPRESSEDTYPE](#)
- static const string [LISTTYPE](#)
- static const string [DEFAULTTYPE](#)
- static const string [RSREADONLYERROR](#)
- static const int [BE_RECSTORE_SEQ_START](#) = 1
- static const int [BE_RECSTORE_SEQ_NEXT](#) = 2

Protected Member Functions

- uint8_t **getMode** () const
- string **getDirectory** () const
- string **getParentDirectory** () const
- string **canonicalName** (const string &name) const
- int **getCursor** () const
- void **setCursor** (int cursor)
- bool **validateKeyString** (const string &key) const
- void **setProperty** (const tr1::shared_ptr< [IO::Properties](#) > properties) throw (Error::StrategyError)
Replace existing [Properties](#) in [RecordStore](#) Control File.
- tr1::shared_ptr< [IO::Properties](#) > **getProperties** () const
Obtain a copy of the [Properties](#) object.

Static Protected Member Functions

- static string **genKeySegName** (const string &key, const uint64_t segnum)
Generate key segment names.

E.80.1 Detailed Description

A class to represent a data storage mechanism.

A [RecordStore](#) is an abstraction that associates keys with a specific record. Implementations of this abstraction can store the records in any format supported by the operating system, such as files or databases, rooted in the file system.

Certain characters are prohibited in the key string. See [IO::RecordStore::INVALIDKEYCHARS](#). A key string cannot begin with the space character.

See Also

[IO::ArchiveRecordStore](#), [IO::DBRecordStore](#), [IO::FileRecordStore](#).

E.80.2 Constructor & Destructor Documentation

E.80.2.1 BiometricEvaluation::IO::RecordStore::RecordStore (const string & *name*, const string & *description*, const string & *type*, const string & *parentDir*) throw (Error::ObjectExists, Error::StrategyError)

Constructor to create a new [RecordStore](#).

Parameters

in	<i>name</i>	The name of the RecordStore to be created.
in	<i>description</i>	The text used to describe the store.
in	<i>type</i>	The type of RecordStore .
in	<i>parentDir</i>	Where, in the file system, the store is to be rooted. This directory must exist.

Exceptions

Error::ObjectExists	The store was previously created, or the directory where it would be created exists.
Error::StrategyError	An error occurred when using the underlying storage system, or the the name malformed.

E.80.2.2 BiometricEvaluation::IO::RecordStore::RecordStore (const string & *name*, const string & *parentDir*, uint8_t *mode* = READWRITE) throw (Error::ObjectDoesNotExist, Error::StrategyError)

Constructor to open an existing [RecordStore](#).

Parameters

in	<i>name</i>	The name of the store to be opened.
in	<i>parentDir</i>	Where, in the file system, the store is rooted.
in	<i>mode</i>	The type of access a client of this RecordStore has.

Exceptions

Error::ObjectDoesNotExist	The RecordStore does not exist.
Error::StrategyError	An error occurred when using the underlying storage system, or the name is malformed.

E.80.3 Member Function Documentation

E.80.3.1 string BiometricEvaluation::IO::RecordStore::getName () const

Return the name of the [RecordStore](#).

Returns

The [RecordStore](#)'s name.

E.80.3.2 `string BiometricEvaluation::IO::RecordStore::getDescription () const`

Obtain a textual description of the [RecordStore](#).

Returns

The [RecordStore](#)'s description.

E.80.3.3 `unsigned int BiometricEvaluation::IO::RecordStore::getCount () const`

Obtain the number of items in the [RecordStore](#).

Returns

The number of items in the [RecordStore](#).

E.80.3.4 `virtual void BiometricEvaluation::IO::RecordStore::changeName (const string & name) throw (Error::ObjectExists, Error::StrategyError) [virtual]`

Change the name of the [RecordStore](#).

Parameters

<i>in</i>	<i>name</i>	The new name for the RecordStore .
-----------	-------------	--

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying storage system, or the name is malformed.
---	---

Reimplemented in [BiometricEvaluation::IO::CompressedRecordStore](#), [BiometricEvaluation::IO::ArchiveRecordStore](#), [BiometricEvaluation::IO::DBRecordStore](#), [BiometricEvaluation::IO::ListRecordStore](#), [BiometricEvaluation::IO::FileRecordStore](#), and [BiometricEvaluation::IO::SQLiteRecordStore](#).

E.80.3.5 `virtual void BiometricEvaluation::IO::RecordStore::changeDescription (const string & description) throw (Error::StrategyError) [virtual]`

Change the description of the [RecordStore](#).

Parameters

<i>in</i>	<i>description</i>	The new description.
-----------	--------------------	----------------------

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.
---	---

Reimplemented in [BiometricEvaluation::IO::SQLiteRecordStore](#).

E.80.3.6 `virtual uint64_t BiometricEvaluation::IO::RecordStore::getSpaceUsed () const throw (Error::StrategyError) [virtual]`

Obtain real storage utilization.

The amount of disk space used, for example. This is the actual space allocated by the underlying storage mechanism, in bytes.

Returns

The amount of backing storage used by the [RecordStore](#).

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.
---	---

Reimplemented in [BiometricEvaluation::IO::ListRecordStore](#), [BiometricEvaluation::IO::CompressedRecordStore](#), [BiometricEvaluation::IO::ArchiveRecordStore](#), [BiometricEvaluation::IO::DBRecordStore](#), [BiometricEvaluation::IO::FileRecordStore](#), and [BiometricEvaluation::IO::SQLiteRecordStore](#).

E.80.3.7 `virtual void BiometricEvaluation::IO::RecordStore::sync () const throw (Error::StrategyError) [virtual]`

Synchronize the entire record store to persistent storage.

Exceptions

<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.
---	---

Reimplemented in [BiometricEvaluation::IO::CompressedRecordStore](#), [BiometricEvaluation::IO::ArchiveRecordStore](#), [BiometricEvaluation::IO::ListRecordStore](#), and [BiometricEvaluation::IO::DBRecordStore](#).

E.80.3.8 `virtual void BiometricEvaluation::IO::RecordStore::insert (const string & key, const void *const data, const uint64_t size) throw (Error::ObjectExists, Error::StrategyError) [pure virtual]`

Insert a record into the store.

Parameters

in	<i>key</i>	The key of the record to be inserted.
in	<i>data</i>	The data for the record.
in	<i>size</i>	The size, in bytes, of the record.

Exceptions

<i>Error::ObjectExists</i>	A record with the given key is already present.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implemented in [BiometricEvaluation::IO::CompressedRecordStore](#), [BiometricEvaluation::IO::ArchiveRecordStore](#), [BiometricEvaluation::IO::DBRecordStore](#), [BiometricEvaluation::IO::FileRecordStore](#), [BiometricEvaluation::IO::ListRecordStore](#), and [BiometricEvaluation::IO::SQLiteRecordStore](#).

E.80.3.9 `virtual void BiometricEvaluation::IO::RecordStore::insert (const string & key, const Memory::uint8Array & data) throw (Error::ObjectExists, Error::StrategyError) [virtual]`

Insert a record into the store.

Parameters

in	<i>key</i>	The key of the record to be inserted.
in	<i>data</i>	The data for the record.

Exceptions

<i>Error::ObjectExists</i>	A record with the given key is already present.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

E.80.3.10 `virtual void BiometricEvaluation::IO::RecordStore::remove (const string & key) throw (Error::ObjectDoesNotExist, Error::StrategyError) [pure virtual]`

Remove a record from the store.

Parameters

in	<i>key</i>	The key of the record to be removed.
----	------------	--------------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implemented in [BiometricEvaluation::IO::CompressedRecordStore](#), [BiometricEvaluation::IO::ArchiveRecordStore](#), [BiometricEvaluation::IO::DBRecordStore](#), [BiometricEvaluation::IO::FileRecordStore](#), [BiometricEvaluation::IO::ListRecordStore](#), and [BiometricEvaluation::IO::SQLiteRecordStore](#).

E.80.3.11 `virtual uint64_t BiometricEvaluation::IO::RecordStore::read (const string & key, void *const data) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [pure virtual]`

Read a complete record from a store. Applications are responsible for allocating storage for the record's data.

Parameters

in	<i>key</i>	The key of the record to be read.
in	<i>data</i>	Pointer to where the data is to be written.

Returns

The size of the record.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implemented in [BiometricEvaluation::IO::CompressedRecordStore](#), [BiometricEvaluation::IO::ArchiveRecordStore](#), [BiometricEvaluation::IO::DBRecordStore](#), [BiometricEvaluation::IO::FileRecordStore](#), [BiometricEvaluation::IO::ListRecordStore](#), and [BiometricEvaluation::IO::SQLiteRecordStore](#).

E.80.3.12 `virtual uint64_t BiometricEvaluation::IO::RecordStore::read (const string & key, Memory::uint8Array & data) const throw (Error::ObjectDoesNotExist, Error::StrategyError)` [virtual]

Read a complete record from a store.

The AutoArray will be resized to match the size of the data.

Parameters

in	<i>key</i>	The key of the record to be read.
in	<i>data</i>	Pointer to where the data is to be written.

Returns

The size of the record.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

E.80.3.13 `virtual void BiometricEvaluation::IO::RecordStore::replace (const string & key, const void *const data, const uint64_t size) throw (Error::ObjectDoesNotExist, Error::StrategyError)` [pure virtual]

Replace a complete record in a store.

Parameters

in	<i>key</i>	The key of the record to be replaced.
in	<i>data</i>	The data for the record.
in	<i>size</i>	The size of data.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implemented in [BiometricEvaluation::IO::CompressedRecordStore](#), [BiometricEvaluation::IO::ArchiveRecordStore](#), [BiometricEvaluation::IO::DBRecordStore](#), [BiometricEvaluation::IO::FileRecordStore](#), [BiometricEvaluation::IO::ListRecordStore](#), and [BiometricEvaluation::IO::SQLiteRecordStore](#).

E.80.3.14 `virtual void BiometricEvaluation::IO::RecordStore::replace (const string & key, const Memory::uint8Array & data) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Replace a complete record in a [RecordStore](#).

Parameters

in	<i>key</i>	The key of the record to be replaced.
in	<i>data</i>	The data for the record.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

E.80.3.15 `virtual uint64_t BiometricEvaluation::IO::RecordStore::length (const string & key) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [pure virtual]`

Return the length of a record.

Parameters

in	<i>key</i>	The key of the record.
----	------------	------------------------

Returns

The record length.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implemented in [BiometricEvaluation::IO::CompressedRecordStore](#), [BiometricEvaluation::IO::ArchiveRecordStore](#), [BiometricEvaluation::IO::DBRecordStore](#), [BiometricEvaluation::IO::FileRecordStore](#), [BiometricEvaluation::IO::ListRecordStore](#), and [BiometricEvaluation::IO::SQLiteRecordStore](#).

E.80.3.16 `virtual void BiometricEvaluation::IO::RecordStore::flush (const string & key) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [pure virtual]`

Commit the record's data to storage.

Parameters

in	<i>key</i>	The key of the record to be flushed.
----	------------	--------------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implemented in [BiometricEvaluation::IO::CompressedRecordStore](#), [BiometricEvaluation::IO::ArchiveRecordStore](#), [BiometricEvaluation::IO::DBRecordStore](#), [BiometricEvaluation::IO::FileRecordStore](#), [BiometricEvaluation::IO::ListRecordStore](#), and [BiometricEvaluation::IO::SQLiteRecordStore](#).

E.80.3.17 `virtual uint64_t BiometricEvaluation::IO::RecordStore::sequence (string & key, void *const data = NULL, int cursor = BE_RECSTORE_SEQ_NEXT) throw (Error::ObjectDoesNotExist, Error::StrategyError) [pure virtual]`

Sequence through a [RecordStore](#), returning the key/data pairs.

Sequencing means to start at some point in the store and return the record, then repeatedly calling the sequencor to return the next record. The starting point is typically the first record, and is set to that when the [RecordStore](#) object is created. The starting point can be reset by calling this method with the cursor parameter set to BE_RECSTORE_SEQ_START.

Parameters

out	<i>key</i>	The key of the currently sequenced record.
in	<i>data</i>	Pointer to where the data is to be written. Applications can set data to NULL to indicate only the key is wanted.
in	<i>cursor</i>	The location within the sequence of the key/data pair to return.

Returns

The length of the record currently in sequence.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implemented in [BiometricEvaluation::IO::CompressedRecordStore](#), [BiometricEvaluation::IO::ArchiveRecordStore](#), [BiometricEvaluation::IO::DBRecordStore](#), [BiometricEvaluation::IO::ListRecordStore](#), [BiometricEvaluation::IO::FileRecordStore](#), and [BiometricEvaluation::IO::SQLiteRecordStore](#).

E.80.3.18 `virtual uint64_t BiometricEvaluation::IO::RecordStore::sequence (string & key, Memory::uint8Array & data, int cursor = BE_RECSTORE_SEQ_NEXT) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Sequence through a [RecordStore](#), returning the key/data pairs.

Sequencing means to start at some point in the store and return the record, then repeatedly calling the `sequence()` to return the next record. The starting point is typically the first record, and is set to that when the [RecordStore](#) object is created. The starting point can be reset by calling this method with the `cursor` parameter set to `BE_RECSTORE_SEQ_START`.

Parameters

out	<i>key</i>	The key of the currently sequenced record.
in	<i>data</i>	Pointer to where the data is to be written.
in	<i>cursor</i>	The location within the sequence of the key/data pair to return.

Returns

The length of the record currently in sequence.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

E.80.3.19 `virtual void BiometricEvaluation::IO::RecordStore::setCursorAtKey (string & key) throw (Error::ObjectDoesNotExist, Error::StrategyError) [pure virtual]`

Set the sequence cursor to an arbitrary position within the [RecordStore](#), starting at `key`. `key` will be the first record returned from the next call to `sequence()`.

Parameters

in	<i>key</i>	The key of the record which will be returned by the first subsequent call to <code>sequence()</code> .
----	------------	--

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implemented in [BiometricEvaluation::IO::CompressedRecordStore](#), [BiometricEvaluation::IO::ArchiveRecordStore](#), [BiometricEvaluation::IO::DBRecordStore](#), [BiometricEvaluation::IO::ListRecordStore](#), [BiometricEvaluation::IO::FileRecordStore](#), and [BiometricEvaluation::IO::SQLiteRecordStore](#).

E.80.3.20 `static tr1::shared_ptr<RecordStore> BiometricEvaluation::IO::RecordStore::openRecordStore (const string & name, const string & parentDir, uint8_t mode = READWRITE) throw (Error::ObjectDoesNotExist, Error::StrategyError) [static]`

Open an existing [RecordStore](#) and return a managed pointer to the the object representing that store.

Applications can open existing record stores without the need to know what type of [RecordStore](#) it is.

The allocated object will be automatically freed when the returned pointer goes out of scope. Applications should not delete the object.

Parameters

in	<i>name</i>	The name of the store to be opened.
in	<i>parentDir</i>	Where, in the file system, the store is rooted.
in	<i>mode</i>	The type of access a client of this RecordStore has.

Returns

An object representing the existing store.

Exceptions

<i>Error::ObjectDoesNotExist</i>	The RecordStore does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system, or the name is malformed.

E.80.3.21 `static tr1::shared_ptr<RecordStore> BiometricEvaluation::IO::RecordStore::createRecordStore (const string & name, const string & description, const string & type, const string & destDir) throw (Error::ObjectExists, Error::StrategyError) [static]`

Create a new [RecordStore](#) and return a managed pointer to the the object representing that store.

The allocated object will be automatically freed when the returned pointer goes out of scope. Applications should not delete the object.

Parameters

in	<i>name</i>	The name of the store to be created.
in	<i>description</i>	The description of the store to be created.

in	<i>type</i>	The type of the store to be created.
in	<i>destDir</i>	Where, in the file system, the store will be created.

Returns

An `auto_ptr` to the object representing the created store.

Exceptions

<i>Error::ObjectDoesNotExist</i>	The RecordStore does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system, or the name is malformed.

E.80.3.22 `static void BiometricEvaluation::IO::RecordStore::removeRecordStore (const string & name, const string & parentDir) throw (Error::ObjectDoesNotExist, Error::StrategyError) [static]`

Remove a [RecordStore](#) by deleting all persistent data associated with the store.

Parameters

in	<i>name</i>	The name of the existing RecordStore .
in	<i>parentDir</i>	Where, in the file system, the store is rooted.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record with the given key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

E.80.3.23 `static void BiometricEvaluation::IO::RecordStore::mergeRecordStores (const string & mergedName, const string & mergedDescription, const string & parentDir, const string & type, const vector< string > & path) throw (Error::ObjectExists, Error::StrategyError) [static]`

Create a new [RecordStore](#) that contains the contents of several other RecordStores.

Parameters

in	<i>mergedName</i>	The name of the new RecordStore that will be created.
in	<i>merged-Description</i>	The text used to describe the RecordStore .
in	<i>parentDir</i>	Where the new RecordStore should be rooted.
in	<i>type</i>	The type of RecordStore that mergedName should be.
in	<i>path</i>	Vector of string paths to RecordStores to open. These point to the RecordStores that will be merged.

Exceptions

<i>Error::ObjectExists</i>	A RecordStore with mergedNamed in parentDir already exists.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

E.80.3.24 `virtual bool BiometricEvaluation::IO::RecordStore::containsKey (const string & key) const`
`[virtual]`

Determines whether the [RecordStore](#) contains an element with the specified key.

Parameters

<i>key</i>	The key to locate.
------------	--------------------

Returns

True if the [RecordStore](#) contains an element with the key, false otherwise.

E.80.3.25 `static string BiometricEvaluation::IO::RecordStore::genKeySegName (const string & key, const uint64_t segnum)` `[static], [protected]`

Generate key segment names.

Parameters

<i>key</i>	Base key name.
<i>segnum</i>	Segment number for key (zero based).

Returns

Key segment name.

E.80.3.26 `void BiometricEvaluation::IO::RecordStore::setProperties (const tr1::shared_ptr< IO::Properties > properties) throw (Error::StrategyError)` `[protected]`

Replace existing [Properties](#) in [RecordStore](#) Control File.

Existing properties will be updated. [RecordStore](#) core properties will be ignored.

Parameters

<i>in</i>	<i>properties</i>	Shared pointer to Properties object.
-----------	-------------------	--

Exceptions

<i>Error::StrategyError</i>	RecordStore was opened READONLY.
-----------------------------	--

E.80.3.27 `tr1::shared_ptr<IO::Properties> BiometricEvaluation::IO::RecordStore::getProperties () const`
`[protected]`

Obtain a copy of the [Properties](#) object.

[RecordStore](#) core properties will be excluded.

Returns

Shared pointer to [Properties](#) object that may be modified.

E.80.4 Member Data Documentation

E.80.4.1 `const string BiometricEvaluation::IO::RecordStore::INVALIDKEYCHARS` `[static]`

The set of prohibited characters in a key: '/', '\', '*', '&'

E.80.4.2 `const char BiometricEvaluation::IO::RecordStore::KEY_SEGMENT_SEPARATOR = '&'` `[static]`

Character used to separate key segments

E.80.4.3 `const uint64_t BiometricEvaluation::IO::RecordStore::KEY_SEGMENT_START = 1` `[static]`

First segment number of a segmented record

E.80.4.4 `const string BiometricEvaluation::IO::RecordStore::CONTROLFILENAME` `[static]`

The name of the control file, a properties list

E.80.4.5 `const string BiometricEvaluation::IO::RecordStore::NAMEPROPERTY` `[static]`

Property key for name of the [RecordStore](#)

E.80.4.6 `const string BiometricEvaluation::IO::RecordStore::DESCRIPTIONPROPERTY` `[static]`

Property key for description of the [RecordStore](#)

E.80.4.7 `const string BiometricEvaluation::IO::RecordStore::COUNTPROPERTY` `[static]`

Property key for the number of store items

E.80.4.8 `const string BiometricEvaluation::IO::RecordStore::TYPEPROPERTY` `[static]`

Property key for the type of [RecordStore](#)

E.80.4.9 `const string BiometricEvaluation::IO::RecordStore::BERKELEYDBTYPE` [static]

[DBRecordStore](#) type

E.80.4.10 `const string BiometricEvaluation::IO::RecordStore::ARCHIVETYPE` [static]

[ArchiveRecordStore](#) type

E.80.4.11 `const string BiometricEvaluation::IO::RecordStore::FILETYPE` [static]

[FileRecordStore](#) type

E.80.4.12 `const string BiometricEvaluation::IO::RecordStore::SQLITETYPE` [static]

[SQLiteRecordStore](#) type

E.80.4.13 `const string BiometricEvaluation::IO::RecordStore::COMPRESSEDTYPE` [static]

[CompressedRecordStore](#) type

E.80.4.14 `const string BiometricEvaluation::IO::RecordStore::LISTTYPE` [static]

[ListRecordStore](#) type

E.80.4.15 `const string BiometricEvaluation::IO::RecordStore::DEFAULTTYPE` [static]

Default [RecordStore](#)

E.80.4.16 `const string BiometricEvaluation::IO::RecordStore::RSREADONLYERROR` [static]

Message for READONLY [RecordStore](#) modification

E.80.4.17 `const int BiometricEvaluation::IO::RecordStore::BE_RECSTORE_SEQ_START = 1` [static]

Tell [sequence\(\)](#) to sequence from beginning

E.80.4.18 `const int BiometricEvaluation::IO::RecordStore::BE_RECSTORE_SEQ_NEXT = 2` [static]

Tell sequence to sequence from current position

E.81 BiometricEvaluation::View::AN2KView::RecordType Class Reference

The type of AN2K record.

```
#include <be_view_an2kview.h>
```

Public Types

- enum **Kind** {
Type_1 = 1, **Type_2** = 2, **Type_3** = 3, **Type_4** = 4,
Type_5 = 5, **Type_6** = 6, **Type_7** = 7, **Type_8** = 8,
Type_9 = 9, **Type_10** = 10, **Type_11** = 11, **Type_12** = 12,
Type_13 = 13, **Type_14** = 14, **Type_15** = 15, **Type_16** = 16,
Type_17 = 17, **Type_99** = 99 }

E.81.1 Detailed Description

The type of AN2K record.

E.82 BiometricEvaluation::Image::Resolution Struct Reference

A structure to represent the resolution of an image.

```
#include <be_image.h>
```

Public Types

- enum **Kind** { **NA** = 0, **PPI** = 1, **PPMM** = 2, **PPCM** = 3 }
Possible representations of the units in a [Resolution](#) struct.

Public Member Functions

- Resolution** (const double **xRes**=0.0, const double **yRes**=0.0, const **Kind** **units**=**PPI**)
Create a [Resolution](#) struct.

Public Attributes

- double **xRes**
- double **yRes**
- Kind** **units**

E.82.1 Detailed Description

A structure to represent the resolution of an image.

E.82.2 Member Enumeration Documentation

E.82.2.1 enum BiometricEvaluation::Image::Resolution::Kind

Possible representations of the units in a [Resolution](#) struct.

Enumerator*NA* Not-applicable: unknown, or otherwise*PPI* Pixels per inch*PPMM* Pixels per millimeter*PPCM* Pixels per centimeter**E.82.3 Constructor & Destructor Documentation**

E.82.3.1 `BiometricEvaluation::Image::Resolution::Resolution (const double xRes = 0.0, const double yRes = 0.0, const Kind units = PPI)`

Create a [Resolution](#) struct.

Parameters

in	<i>xRes</i>	Resolution along the X-axis
in	<i>yRes</i>	Resolution along the Y-axis
in	<i>units</i>	Units in which xRes and yRes are represented

E.82.4 Member Data Documentation

E.82.4.1 `double BiometricEvaluation::Image::Resolution::xRes`

[Resolution](#) along the X-axis

E.82.4.2 `double BiometricEvaluation::Image::Resolution::yRes`

[Resolution](#) along the Y-axis

E.82.4.3 `Kind BiometricEvaluation::Image::Resolution::units`

Units in which xRes and yRes are represented

E.83 BiometricEvaluation::Feature::RidgeCountExtractionMethod Class Reference

Enumerate the types of extraction methods for ridge counts.

```
#include <be_feature_minutiae.h>
```

Public Types

- enum **Kind** { **NonSpecific** = 0, **FourNeighbor** = 1, **EightNeighbor** = 2, **Other** = 3 }

E.83.1 Detailed Description

Enumerate the types of extraction methods for ridge counts.

E.84 BiometricEvaluation::Feature::RidgeCountItem Struct Reference

Representation of ridge count data, which is the number of ridges between any two minutia data points, each represented by its index number.

```
#include <be_feature_minutiae.h>
```

Public Member Functions

- [RidgeCountItem](#) (RidgeCountExtractionMethod::Kind extraction_method, int index_one, int index_two, int count=0)

Create a [RidgeCountItem](#) struct.

Public Attributes

- RidgeCountExtractionMethod::Kind **extraction_method**
- int **index_one**
- int **index_two**
- int **count**

E.84.1 Detailed Description

Representation of ridge count data, which is the number of ridges between any two minutia data points, each represented by its index number.

E.85 BiometricEvaluation::Error::SignalManager Class Reference

A [SignalManager](#) object is used to handle signals that come from the operating system.

```
#include <be_error_signal_manager.h>
```

Public Member Functions

- [SignalManager](#) () throw (Error::StrategyError)
- [SignalManager](#) (const sigset_t signalSet) throw (Error::ParameterError)
- void [setSignalSet](#) (const sigset_t signalSet) throw (Error::ParameterError)
- void [clearSignalSet](#) ()
- void [setDefaultSignalSet](#) ()
- bool [sigHandled](#) ()
- void [start](#) () throw (Error::StrategyError)
- void [stop](#) () throw (Error::StrategyError)

- void [setSigHandled\(\)](#)
- void [clearSigHandled\(\)](#)

Static Public Attributes

- static bool [_canSigJump](#)
- static sigjmp_buf [_sigJumpBuf](#)

E.85.1 Detailed Description

A [SignalManager](#) object is used to handle signals that come from the operating system.

Applications typically do not invoke most methods of a [SignalManager](#), except the [setSignalSet\(\)](#), [setDefaultSignalSet\(\)](#), and [sigHandled\(\)](#). An application wishing to just catch memory errors can simply construct a [SignalManager](#) object, and invoke [sigHandled\(\)](#) at the end of the signal block to detect whether a signal was handled.

The `BEGIN_SIGNAL_BLOCK` macro sets up the jump block and tells the [SignalManager](#) object to start handling signals. Applications can call either [setSignalSet\(\)](#) or [setDefaultSignalSet\(\)](#) before invoking these macros to indicate which signals are to be handled.

The `END_SIGNAL_BLOCK()` macro clears the signal set, so from that point forward application code signals will be handled in the system's default manner until another signal block is created.

A [SignalManager](#) is passive (i.e. no signal handlers are installed) until that [start\(\)](#) method is called, and becomes passive when [stop\(\)](#) is invoked. The signals that are to be handled by the object are maintained as state, and the set of signals can be changed at any time, but are not in effect until [start\(\)](#) is called.

Attention

The [start\(\)](#), [stop\(\)](#), [setSigHandled\(\)](#) and [clearSigHandled\(\)](#) methods are not meant to be used directly by applications, which should use the `BEGIN_SIGNAL_BLOCK()/END_SIGNAL_BLOCK()` macro pair.

E.85.2 Constructor & Destructor Documentation

E.85.2.1 BiometricEvaluation::Error::SignalManager::SignalManager () throw (Error::StrategyError)

Construct a new [SignalManager](#) object with the default signal handling: SIGSEGV and SIGBUS.

Exceptions

Error::StrategyError	Could not register the signal handler.
--------------------------------------	--

E.85.2.2 BiometricEvaluation::Error::SignalManager::SignalManager (const sigset_t *signalSet*) throw (Error::ParameterError)

Construct a new [SignalManager](#) object with the specified signal handling, no defaults.

Parameters

<i>signalSet</i>	(in) The signal set; see sigaction(2), sigemptyset(3) and sigaddset(3).
------------------	---

Exceptions

<i>Error::ParameterError</i>	One of the signals in signalSet cannot be handled (SIGKILL, SIGSTOP).
--	---

E.85.3 Member Function Documentation

E.85.3.1 void BiometricEvaluation::Error::SignalManager::setSignalSet (const sigset_t *signalSet*) throw (Error::ParameterError)

Set the signals this object will manage.

Parameters

<i>signalSet</i>	(in) The signal set; see sigaction(2), sigemptyset(3) and sigaddset(3).
------------------	---

Exceptions

<i>Error::ParameterError</i>	One of the signals in signalSet cannot be handled (SIGKILL, SIGSTOP).
--	---

E.85.3.2 void BiometricEvaluation::Error::SignalManager::clearSignalSet ()

Clear all signal handling.

E.85.3.3 void BiometricEvaluation::Error::SignalManager::setDefaultSignalSet ()

Set the default signals this object will manage: SIGSEGV and SIGBUS.

E.85.3.4 bool BiometricEvaluation::Error::SignalManager::sigHandled ()

Indicate whether a signal was handled.

Returns

true if a signal was handled, false otherwise.

E.85.3.5 void BiometricEvaluation::Error::SignalManager::start () throw (Error::StrategyError)

Start handling signals of the current signal set.

Exceptions

<i>Error::StrategyError</i>	Could not register the signal handler.
---	--

Note

If an application invokes [start\(\)](#) without setting up a signal jump block, behavior is undefined, and can result in an infinite loop if further processing causes a signal to be raised.

E.85.3.6 void BiometricEvaluation::Error::SignalManager::stop () throw (Error::StrategyError)

Stop handling signals of the current signal set.

Exceptions

Error::StrategyError	Could not register the signal handler.
--------------------------------------	--

E.85.3.7 void BiometricEvaluation::Error::SignalManager::setSigHandled ()

Set a flag to indicate a signal was handled.

E.85.3.8 void BiometricEvaluation::Error::SignalManager::clearSigHandled ()

Clear the indication that a signal was handled.

E.85.4 Member Data Documentation**E.85.4.1 bool BiometricEvaluation::Error::SignalManager::_canSigJump [static]**

Flag indicating can jump after handling a signal.

Note

Should not be directly used by applications.

E.85.4.2 sigjmp_buf BiometricEvaluation::Error::SignalManager::_sigJumpBuf [static]

The jump buffer used by the signal handler.

Note

Should not be directly used by applications.

E.86 BiometricEvaluation::Image::Size Struct Reference

A structure to represent the size of an image, in pixels.

```
#include <be_image.h>
```

Public Member Functions

- [Size](#) (const uint32_t *xSize*=0, const uint32_t *ySize*=0)

Create a [Size](#) struct.

Public Attributes

- uint32_t *xSize*
- uint32_t *ySize*

E.86.1 Detailed Description

A structure to represent the size of an image, in pixels.

E.86.2 Constructor & Destructor Documentation

E.86.2.1 BiometricEvaluation::Image::Size::Size (const uint32_t *xSize* = 0, const uint32_t *ySize* = 0)

Create a [Size](#) struct.

Parameters

in	<i>xSize</i>	Number of pixels on the X-axis
in	<i>ySize</i>	Number of pixels on the Y-axis

E.86.3 Member Data Documentation

E.86.3.1 uint32_t BiometricEvaluation::Image::Size::xSize

Number of pixels on the X-axis

E.86.3.2 uint32_t BiometricEvaluation::Image::Size::ySize


Number of pixels on the Y-axis

E.87 BiometricEvaluation::IO::SQLiteRecordStore Class Reference

A [RecordStore](#) implementation using a SQLite database as the underlying record storage system.

```
#include <be_io_sqliterecstore.h>
```

Inheritance diagram for BiometricEvaluation::IO::SQLiteRecordStore:



Public Member Functions

- **SQLiteRecordStore** (const string &name, const string &description, const string &parentDir) throw (Error::ObjectExists, Error::StrategyError)
- **SQLiteRecordStore** (const string &name, const string &parentDir, uint8_t mode=READWRITE) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void **changeName** (const string &name) throw (Error::ObjectExists, Error::StrategyError)
- void **changeDescription** (const string &description) throw (Error::StrategyError)
- uint64_t **getSpaceUsed** () const throw (Error::StrategyError)
Obtain real storage utilization.
- void **insert** (const string &key, const void *const data, const uint64_t size) throw (Error::ObjectExists, Error::StrategyError)
- void **remove** (const string &key) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t **read** (const string &key, void *const data) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void **replace** (const string &key, const void *const data, const uint64_t size) throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t **length** (const string &key) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- void **flush** (const string &key) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
- uint64_t **sequence** (string &key, void *const data=NULL, int cursor=BE_RECSTORE_SEQ_NEXT) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Sequence through a [RecordStore](#), returning the key/data pairs.
- void **setCursorAtKey** (string &key) throw (Error::ObjectDoesNotExist, Error::StrategyError)

Protected Member Functions

- void **sqliteError** (int32_t errorNumber) const throw (Error::StrategyError)
Convert an SQLite error into a StrategyError.
- void **createStructure** () throw (Error::StrategyError)
Create the tables needed to store key->value pairs in SQLite.
- bool **validateKeyValueTable** (const string &table) throw (Error::StrategyError)
Confirm that a key->value table exists with the proper schema.
- void **createKeyValueTable** (const string &table) throw (Error::StrategyError)
Create a tables needed to store key->value pairs in SQLite.
- bool **validateSchema** () throw (Error::StrategyError)
Confirm that the schema of the opened SQLite database is compatible.
- uint64_t **readSegments** (const string &key, void *const data) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
Select a row from the [RecordStore](#).
- void **cleanup** () throw (Error::StrategyError)
Perform SQLite cleanup routines.

Additional Inherited Members

E.87.1 Detailed Description

A [RecordStore](#) implementation using a SQLite database as the underlying record storage system.

E.87.2 Member Function Documentation

E.87.2.1 void BiometricEvaluation::IO::SQLiteRecordStore::changeName (const string & *name*) throw (Error::ObjectExists, Error::StrategyError) [virtual]

Change the name of the [RecordStore](#).

Parameters

in	<i>name</i>	The new name for the RecordStore .
----	-------------	--

Exceptions

Error::StrategyError	An error occurred when using the underlying storage system, or the name is malformed.
--------------------------------------	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.87.2.2 void BiometricEvaluation::IO::SQLiteRecordStore::changeDescription (const string & *description*) throw (Error::StrategyError) [virtual]

Change the description of the [RecordStore](#).

Parameters

in	<i>description</i>	The new description.
----	--------------------	----------------------

Exceptions

Error::StrategyError	An error occurred when using the underlying storage system.
--------------------------------------	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.87.2.3 uint64_t BiometricEvaluation::IO::SQLiteRecordStore::getSpaceUsed () const throw (Error::StrategyError) [virtual]

Obtain real storage utilization.

The amount of disk space used, for example. This is the actual space allocated by the underlying storage mechanism, in bytes.

Returns

The amount of backing storage used by the [RecordStore](#).

Exceptions

Error::StrategyError	An error occurred when using the underlying storage system.
--------------------------------------	---

Reimplemented from [BiometricEvaluation::IO::RecordStore](#).

E.87.2.4 `void BiometricEvaluation::IO::SQLiteRecordStore::insert (const string & key, const void *const data, const uint64_t size) throw (Error::ObjectExists, Error::StrategyError) [virtual]`

Insert a record into the store.

Parameters

in	<i>key</i>	The key of the record to be inserted.
in	<i>data</i>	The data for the record.
in	<i>size</i>	The size, in bytes, of the record.

Exceptions

Error::ObjectExists	A record with the given key is already present.
Error::StrategyError	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.87.2.5 `void BiometricEvaluation::IO::SQLiteRecordStore::remove (const string & key) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Remove a record from the store.

Parameters

in	<i>key</i>	The key of the record to be removed.
----	------------	--------------------------------------

Exceptions

Error::ObjectDoesNotExist	A record for the key does not exist.
Error::StrategyError	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.87.2.6 `uint64_t BiometricEvaluation::IO::SQLiteRecordStore::read (const string & key, void *const data) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Read a complete record from a store. Applications are responsible for allocating storage for the record's data.

Parameters

in	<i>key</i>	The key of the record to be read.
in	<i>data</i>	Pointer to where the data is to be written.

Returns

The size of the record.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.87.2.7 `void BiometricEvaluation::IO::SQLiteRecordStore::replace (const string & key, const void *const data, const uint64_t size) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Replace a complete record in a store.

Parameters

in	<i>key</i>	The key of the record to be replaced.
in	<i>data</i>	The data for the record.
in	<i>size</i>	The size of data.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.87.2.8 `uint64_t BiometricEvaluation::IO::SQLiteRecordStore::length (const string & key) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Return the length of a record.

Parameters

in	<i>key</i>	The key of the record.
----	------------	------------------------

Returns

The record length.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.87.2.9 void BiometricEvaluation::IO::SQLiteRecordStore::flush (const string & key) const throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Commit the record's data to storage.

Parameters

in	key	The key of the record to be flushed.
----	-----	--------------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.87.2.10 uint64_t BiometricEvaluation::IO::SQLiteRecordStore::sequence (string & key, void *const data = NULL, int cursor = BE_RECSTORE_SEQ_NEXT) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Sequence through a [RecordStore](#), returning the key/data pairs.

Sequencing means to start at some point in the store and return the record, then repeatedly calling the sequencor to return the next record. The starting point is typically the first record, and is set to that when the [RecordStore](#) object is created. The starting point can be reset by calling this method with the cursor parameter set to BE_RECSTORE_SEQ_START.

Parameters

out	key	The key of the currently sequenced record.
in	data	Pointer to where the data is to be written. Applications can set data to NULL to indicate only the key is wanted.
in	cursor	The location within the sequence of the key/data pair to return.

Returns

The length of the record currently in sequence.

Exceptions

<i>Error::ObjectDoesNotExist</i>	A record for the key does not exist.
<i>Error::StrategyError</i>	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.87.2.11 `void BiometricEvaluation::IO::SQLiteRecordStore::setCursorAtKey (string & key) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]`

Set the sequence cursor to an arbitrary position within the [RecordStore](#), starting at key. Key will be the first record returned from the next call to [sequence\(\)](#).

Parameters

<i>in</i>	<i>key</i>	The key of the record which will be returned by the first subsequent call to sequence() .
-----------	------------	---

Exceptions

Error::ObjectDoesNotExist	A record for the key does not exist.
Error::StrategyError	An error occurred when using the underlying storage system.

Implements [BiometricEvaluation::IO::RecordStore](#).

E.87.2.12 `void BiometricEvaluation::IO::SQLiteRecordStore::sqliteError (int32_t errorNumber) const throw (Error::StrategyError) [protected]`

Convert an SQLite error into a StrategyError.

Exceptions

Error::StrategyError	Always thrown with the textual description of the last error condition.
--------------------------------------	---

E.87.2.13 `void BiometricEvaluation::IO::SQLiteRecordStore::createStructure () throw (Error::StrategyError) [protected]`

Create the tables needed to store key->value pairs in SQLite.

Exceptions

Error::StrategyError	Error executing SQL commands.
--------------------------------------	---

E.87.2.14 `bool BiometricEvaluation::IO::SQLiteRecordStore::validateKeyValueTable (const string & table) throw (Error::StrategyError) [protected]`

Confirm that a key->value table exists with the proper schema.

Parameters

<i>table</i>	Name of the table to check.
--------------	-----------------------------

Returns

Whether or not the table exists with the proper schema.

Exceptions

Error::StrategyError	Error compiling SQL.
--------------------------------------	----------------------

E.87.2.15 void BiometricEvaluation::IO::SQLiteRecordStore::createKeyValueTable (const string & *table*)
throw (Error::StrategyError) [protected]

Create a tables needed to store key->value pairs in SQLite.

Parameters

<i>table</i>	Name of the table to create.
--------------	------------------------------

Exceptions

Error::StrategyError	Error executing SQL commands.
--------------------------------------	-------------------------------

E.87.2.16 bool BiometricEvaluation::IO::SQLiteRecordStore::validateSchema () throw
(Error::StrategyError) [protected]

Confirm that the schema of the opened SQLite database is compatible.

Returns

Whether or not the schema of the opened SQLite database is compatible with this object.

Exceptions

Error::StrategyError	Error compiling SQL.
--------------------------------------	----------------------

E.87.2.17 uint64_t BiometricEvaluation::IO::SQLiteRecordStore::readSegments (const string & *key*,
void *const *data*) const throw (Error::ObjectDoesNotExist, Error::StrategyError)
[protected]

Select a row from the [RecordStore](#).

Parameters

<i>key</i>	Key of the row to select.
<i>data</i>	If not NULL, deep copy the record for key into data.

Exceptions

<i>Error::ObjectDoesNotExist</i>	Key does not exist in RecordStore .
<i>Error::StrategyError</i>	Error executing SQL commands.

Returns

Size of key's record.

E.87.2.18 `void BiometricEvaluation::IO::SQLiteRecordStore::cleanup () throw (Error::StrategyError)`
`[protected]`

Perform SQLite cleanup routines.

- Finalize the sequencer statement
- Close the SQLite database handle

Exceptions

<i>Error::StrategyError</i>	Bad return code from SQLite during cleanup.
---	---

E.88 BiometricEvaluation::Process::Statistics Class Reference

The [Statistics](#) class provides an interface for gathering process statistics, such as memory usage, system time, etc.

```
#include <be_process_statistics.h>
```

Public Member Functions

- [Statistics](#) ()
- [Statistics](#) ([IO::LogCabinet](#) *const logCabinet) throw (Error::NotImplemented, Error::ObjectExists, Error::StrategyError)
- void [getCPUTimes](#) (uint64_t *usertime, uint64_t *systemtime) throw (Error::StrategyError, Error::NotImplemented)
- void [getMemorySizes](#) (uint64_t *vmrss, uint64_t *vmsize, uint64_t *vmpeak, uint64_t *vmdata, uint64_t *vmstack) throw (Error::StrategyError, Error::NotImplemented)
- uint32_t [getNumThreads](#) () throw (Error::StrategyError, Error::NotImplemented)
- void [logStats](#) () throw (Error::ObjectDoesNotExist, Error::StrategyError, Error::NotImplemented)
Create a snapshot of the current process statistics in the LogSheet created in the LogCabinet.
- void [startAutoLogging](#) (uint64_t interval) throw (Error::ObjectDoesNotExist, Error::ObjectExists, Error::StrategyError, Error::NotImplemented)
Start logging process statistics automatically, in intervals of microseconds. The first log entry will occur soon after the call to this method as the delay interval is invoked after the first entry.
- void [stopAutoLogging](#) () throw (Error::ObjectDoesNotExist, Error::StrategyError)

Stop the automatic logging of process statistics.

- void [callStatistics_logStats](#) ()

E.88.1 Detailed Description

The [Statistics](#) class provides an interface for gathering process statistics, such as memory usage, system time, etc.

The information gathered by objects of this class are for the current process, and can optionally be logged to a LogSheet object contained within the provided LogCabinet.

Note

The resolution of a returned value for many methods may not match the resolution allowed by the interface. For example, the operating system may allow for second resolution whereas the interface allows microsecond resolution.

E.88.2 Constructor & Destructor Documentation

E.88.2.1 BiometricEvaluation::Process::Statistics::Statistics ()

Constructor with no parameters.

E.88.2.2 BiometricEvaluation::Process::Statistics::Statistics (IO::LogCabinet *const *logCabinet*) throw (Error::NotImplemented, Error::ObjectExists, Error::StrategyError)

Construct a [Statistics](#) object with the associated LogCabinet.

Parameters

<i>in</i>	<i>logCabinet</i>	The LogCabinet object where this object will create a LogSheet to contain the statistic information for the process.
-----------	-------------------	--

Exceptions

Error::NotImplemented	Logging is not supported on this OS. This exception can be thrown when any portion of the statistics gathering cannot be completed.
Error::ObjectExists	The LogSheet already exists. This exception should rarely, if ever, occur.
Error::StrategyError	Failure to create the LogSheet in the cabinet.

E.88.3 Member Function Documentation

E.88.3.1 void BiometricEvaluation::Process::Statistics::getCPUTimes (uint64_t * *usertime*, uint64_t * *systemtime*) throw (Error::StrategyError, Error::NotImplemented)

Obtain the total user and system times for the process, in microseconds. Any of the out parameters can be NULL, indicating non-interest in that statistic.

Note

This method may not be implemented in all operating systems.

Parameters

out	<i>usertime</i>	Pointer where to store the total user time.
out	<i>systemtime</i>	Pointer where to store the total system time.

Exceptions

<i>Error::StrategyError</i>	An error occurred when obtaining the process statistics from the operating system. The exception information string contains the error reason.
<i>Error::NotImplemented</i>	This method is not implemented on this OS.

E.88.3.2 void BiometricEvaluation::Process::Statistics::getMemorySizes (uint64_t * *vmrss*, uint64_t * *vmsize*, uint64_t * *vmpeak*, uint64_t * *vmdata*, uint64_t * *vmstack*) throw (Error::StrategyError, Error::NotImplemented)

Obtain the current memory set sizes for the process, in kilobytes. Any of the out parameters can be NULL, indicating non-interest in that statistic.

Note

This method may not be implemented in all operating systems.

Parameters

out	<i>vmrss</i>	Pointer where to store the current resident set size.
out	<i>vmsize</i>	Pointer where to store the current total virtual memory size.
out	<i>vmpeak</i>	Pointer where to store the peak total virtual memory size.
out	<i>vmdata</i>	Pointer where to store the current virtual memory data segment size.
out	<i>vmstack</i>	Pointer where to store the current virtual memory stack segment size.

Exceptions

<i>Error::StrategyError</i>	An error occurred when obtaining the process statistics from the operating system. The exception information string contains the error reason.
<i>Error::NotImplemented</i>	This method is not implemented on this OS.

E.88.3.3 uint32_t BiometricEvaluation::Process::Statistics::getNumThreads () throw (Error::StrategyError, Error::NotImplemented)

Obtain the number of threads composing this process.

Note

This method may not be implemented in all operating systems.

Exceptions

<i>Error::StrategyError</i>	An error occurred when obtaining the process info from the operating system. The exception information string contains the error reason.
<i>Error::NotImplemented</i>	This method is not implemented on this OS.

E.88.3.4 void BiometricEvaluation::Process::Statistics::logStats () throw (Error::ObjectDoesNotExist, Error::StrategyError, Error::NotImplemented)

Create a snapshot of the current process statistics in the LogSheet created in the LogCabinet.

Exceptions

<i>Error::ObjectDoesNotExist</i>	The LogSheet does not exist; this object was not created with LogCabinet object.
<i>Error::StrategyError</i>	An error occurred when writing to the LogSheet.
<i>Error::NotImplemented</i>	The statistics gathering is not implemented for this operating system.

E.88.3.5 void BiometricEvaluation::Process::Statistics::startAutoLogging (uint64_t interval) throw (Error::ObjectDoesNotExist, Error::ObjectExists, Error::StrategyError, Error::NotImplemented)

Start logging process statistics automatically, in intervals of microseconds. The first log entry will occur soon after the call to this method as the delay interval is invoked after the first entry.

Note

It is unrealistic to expect that log entries can be made at a rate of one per microsecond. If [`stopAutoLogging\(\)`](#) is called very soon after the start, a log entry may not be made.

Parameters

in	<i>interval</i>	The gap between logging snapshots, in microseconds.
----	-----------------	---

Exceptions

<i>Error::ObjectDoesNotExist</i>	The LogSheet does not exist; this object was not created with LogCabinet object.
<i>Error::ObjectExists</i>	Autologging is currently invoked.
<i>Error::StrategyError</i>	An error occurred when writing to the LogSheet.
<i>Error::NotImplemented</i>	The statistics gathering is not implemented for this operating system.

E.88.3.6 void BiometricEvaluation::Process::Statistics::stopAutoLogging () throw (Error::ObjectDoesNotExist, Error::StrategyError)

Stop the automatic logging of process statistics.

Exceptions

<i>Error::ObjectDoesNotExist</i>	Not currently autologging.
<i>Error::StrategyError</i>	An error occurred when stopping, most likely because the logging thread died.

E.88.3.7 void BiometricEvaluation::Process::Statistics::callStatistics_logStats ()


Helper function in C++ space that has access to this object, and is called from C space by the logging thread. Applications should not call this function.

E.89 BiometricEvaluation::Error::StrategyError Class Reference

A [StrategyError](#) object is thrown when the underlying implementation of this interface encounters an error.

```
#include <be_error_exception.h>
```

Inheritance diagram for BiometricEvaluation::Error::StrategyError:



Public Member Functions

- [StrategyError](#) ()
- [StrategyError](#) (string info)

E.89.1 Detailed Description

A [StrategyError](#) object is thrown when the underlying implementation of this interface encounters an error.

E.89.2 Constructor & Destructor Documentation

E.89.2.1 BiometricEvaluation::Error::StrategyError::StrategyError ()

Construct a [StrategyError](#) object with the default information string.

E.89.2.2 BiometricEvaluation::Error::StrategyError::StrategyError (string info)

Construct a [StrategyError](#) object with an information string appended to the default information string.

E.90 BiometricEvaluation::Time::Timer Class Reference

This class can be used by applications to report the amount of time a block of code takes to execute.

```
#include <be_time_timer.h>
```

Public Member Functions

- [Timer](#) ()
- void [start](#) () throw (Error::StrategyError)
- void [stop](#) () throw (Error::StrategyError)
- uint64_t [elapsed](#) () throw (Error::StrategyError)

E.90.1 Detailed Description

This class can be used by applications to report the amount of time a block of code takes to execute.

Applications wrap the block of code in the [Timer::start\(\)](#) and [Timer::stop\(\)](#) calls, then use [Timer::elapsed\(\)](#) to obtain the calculated time of the operation.

Warning

Timers are not threadsafe and should only be used to time operations within the same thread.

E.90.2 Constructor & Destructor Documentation

E.90.2.1 BiometricEvaluation::Time::Timer::Timer ()

Constructor for the [Timer](#) object.

E.90.3 Member Function Documentation

E.90.3.1 void BiometricEvaluation::Time::Timer::start () throw (Error::StrategyError)

Start tracking time.

Exceptions

Error::StrategyError	This object is currently timing an operation or an error occurred when obtaining timing information.
--------------------------------------	--

E.90.3.2 void BiometricEvaluation::Time::Timer::stop () throw (Error::StrategyError)

Stop tracking time.

Exceptions

<i>Error::StrategyError</i>	This object is not currently timing an operation or an error occurred when obtaining timing information.
---	--

E.90.3.3 uint64_t BiometricEvaluation::Time::Timer::elapsed () throw (Error::StrategyError)

Get the elapsed time in microseconds between calls to this object's [start\(\)](#) and [stop\(\)](#) methods.

Returns

The number of microseconds between calls to this object's [start\(\)](#) and [stop\(\)](#) methods.

Exceptions


<i>Error::StrategyError</i>	This object is currently timing an operation or an error occurred when obtaining timing information.
---	--

E.91 BiometricEvaluation::View::View Class Reference

A class to represent single biometric element view.

```
#include <be_view_view.h>
```

Inheritance diagram for BiometricEvaluation::View::View:



Public Member Functions

- virtual tr1::shared_ptr
< [Image::Image](#) > [getImage](#) () const =0
Obtain the image used for the finger view.
- virtual [Image::Size](#) [getImageSize](#) () const =0
Obtain the image size.
- virtual [Image::Resolution](#) [getImageResolution](#) () const =0
Obtain the image resolution.
- virtual uint32_t [getImageDepth](#) () const =0
Obtain the image depth.

- virtual `Image::CompressionAlgorithm::Kind` `getCompressionAlgorithm () const =0`
Obtain the compression algorithm used on the image.
- virtual `Image::Resolution` `getScanResolution () const =0`
Obtain the image scan resolution.

E.91.1 Detailed Description

A class to represent single biometric element view.

Included in a view is the biometric image and any derived information, such as minutiae points.

E.91.2 Member Function Documentation

E.91.2.1 `virtual tr1::shared_ptr<Image::Image> BiometricEvaluation::View::View::getImage () const` `[pure virtual]`

Obtain the image used for the finger view.

Not all finger views will have an image, however the derived information, such as minutiae, may be present.

Implemented in `BiometricEvaluation::View::AN2KView`, and `BiometricEvaluation::Finger::INCITSView`.

E.91.2.2 `virtual Image::Size BiometricEvaluation::View::View::getImageSize () const` `[pure virtual]`

Obtain the image size.

This value is as present in the biometric record, and not in the image data itself. Normally, this value and the actual image size must be equal, but applications can check for inconsistencies. In the case of raw images, however, the value obtained with this method must be accepted as correct.

Implemented in `BiometricEvaluation::View::AN2KView`, and `BiometricEvaluation::Finger::INCITSView`.

E.91.2.3 `virtual Image::Resolution BiometricEvaluation::View::View::getImageResolution () const` `[pure virtual]`

Obtain the image resolution.

`Image` resolution is taken from the biometric record, and not from the image data. In some cases, the resolution may be the components of the pixel ratio, and applications must check the `Image::Resolution::units` field for value NA.

Implemented in `BiometricEvaluation::View::AN2KView`, and `BiometricEvaluation::Finger::INCITSView`.

E.91.2.4 `virtual uint32_t BiometricEvaluation::View::View::getImageDepth () const` `[pure virtual]`

Obtain the image depth.

This value is as present in the biometric record, and not in the image data itself. Normally, this value and the actual image depth must be equal, but applications can check for inconsistencies. In the case of raw images, however, the value obtained with this method must be accepted as correct.

Implemented in [BiometricEvaluation::View::AN2KView](#), and [BiometricEvaluation::Finger::INCITSView](#).

E.91.2.5 `virtual Image::CompressionAlgorithm::Kind BiometricEvaluation::View::View::getCompressionAlgorithm () const [pure virtual]`

Obtain the compression algorithm used on the image.

This value is as present in the biometric record, and not obtained from the image data itself.

Implemented in [BiometricEvaluation::View::AN2KView](#), and [BiometricEvaluation::Finger::INCITSView](#).

E.91.2.6 `virtual Image::Resolution BiometricEvaluation::View::View::getScanResolution () const [pure virtual]`

Obtain the image scan resolution.

This value is as present in the biometric record, and not in the image data itself. Normally, this value and the actual image resolution must be equal, but applications can check for inconsistencies.

Implemented in [BiometricEvaluation::View::AN2KView](#), and [BiometricEvaluation::Finger::INCITSView](#).

E.92 BiometricEvaluation::Time::Watchdog Class Reference

A [Watchdog](#) object can be used by applications to limit the amount of processing time taken by a block of code.

```
#include <be_time_watchdog.h>
```

Public Member Functions

- [Watchdog](#) (const uint8_t type) throw (Error::NotImplemented, Error::ParameterError)
- void [setInterval](#) (uint64_t interval)
- void [start](#) () throw (Error::StrategyError)
- void [stop](#) () throw (Error::StrategyError)
- bool [expired](#) ()
- void [setCanSigJump](#) ()
- void [clearCanSigJump](#) ()
- void [setExpired](#) ()
- void [clearExpired](#) ()

Static Public Attributes

- static const uint8_t [PROCESSTIME](#) = 0
- static const uint8_t [REALTIME](#) = 1
- static bool [_canSigJump](#)
- static sigjmp_buf [_sigJumpBuf](#)

E.92.1 Detailed Description

A [Watchdog](#) object can be used by applications to limit the amount of processing time taken by a block of code.

A [Watchdog](#) object is used to set a timer that, upon expiration, will force a jump to a location within the process. An application can detect whether the timer expired at that point in the code. [Watchdog](#) builds on the POSIX `setitimer(2)` call. [Timer](#) intervals are in terms of process virtual time or real time, based on how the object is constructed.

Most applications will not directly invoke the methods of the `WatchDog` class, instead using the `BEGIN_WATCHDOG_BLOCK()` and `END_WATCHDOG_BLOCK()` macros. Applications should not install there own signal handlers, but use the `SignalManager` class instead.

The `BEGIN_WATCHDOG_BLOCK` macro sets up the jump block and tells the [Watchdog](#) object to start handling the alarm signal. Applications must call [setInterval\(\)](#) before invoking the `BEGIN_WATCHDOG_BLOCK()` macro.

The `END_WATCHDOG_BLOCK()` macro disables the watchdog timer, but doesn't affect the current interval value. Applications can set the interval once and use the `BEGIN/END` block macros repeatedly. Failure to call [setInterval\(\)](#) results in an effectively disabled timer, as does setting the interval to 0.

Note

[Process](#) virtual timing may not be available on all systems. In those cases, an application compilation error will occur because `PROCESSTIME` will not be defined.

Attention

On many systems, the `sleep(3)` call is implemented using alarm signals, the same technique used by the [Watchdog](#) class. Therefore, applications should not call `sleep(3)` inside the [Watchdog](#) block; behavior is undefined in that case, but usually results in cancellation of the [Watchdog](#) timer.

The [setCanSigJump\(\)](#), [clearCanSigJump\(\)](#), [setExpired\(\)](#) and [clearExpired\(\)](#) methods are not meant to be used directly by applications, which should use the `BEGIN_WATCHDOG_BLOCK()/END_WATCHDOG_BLOCK()` macro pair.

See Also

[Error::SignalManager](#)

E.92.2 Constructor & Destructor Documentation

E.92.2.1 BiometricEvaluation::Time::Watchdog::Watchdog (const uint8_t type) throw (Error::NotImplemented, Error::ParameterError)

Construct a new [Watchdog](#) object.

Parameters

<code>in</code>	<i>type</i>	The type of timer, <code>ProcessTime</code> or <code>RealTime</code> .
-----------------	-------------	--

Exceptions

<i>Error::NotImplemented</i>	The type of watchdog requested is not implemented.
<i>Error::ParameterError</i>	The type is invalid.

Warning

[*Watchdog::PROCESSTIME*](#) is not supported under Cygwin.

E.92.3 Member Function Documentation**E.92.3.1 void BiometricEvaluation::Time::Watchdog::setInterval (uint64_t *interval*)**

Set the interval for the timer, but don't start the timer. Setting a value of 0 will essentially disable the timer. [*Timer*](#) intervals are in microseconds, however actual intervals are dependent on the resolution of the system clock, and may not be at microsecond resolution.

Parameters

in	<i>interval</i>	The timer interval, in microseconds.
----	-----------------	--------------------------------------

E.92.3.2 void BiometricEvaluation::Time::Watchdog::start () throw (Error::StrategyError)

Start a watchdog timer.

Exceptions

<i>Error::StrategyError</i>	Could not register the signal handler, or could not create the timer.
---	---

E.92.3.3 void BiometricEvaluation::Time::Watchdog::stop () throw (Error::StrategyError)

Stop a watchdog timer.

Exceptions

<i>Error::StrategyError</i>	Could not clear the timer.
---	----------------------------

E.92.3.4 bool BiometricEvaluation::Time::Watchdog::expired ()

Indicate whether the watchdog timer expired.

Returns

true if the timer expired, false otherwise.

E.92.3.5 void BiometricEvaluation::Time::Watchdog::setCanSigJump ()

Indicate that the signal handler can jump into the application code after handling the signal.

E.92.3.6 void BiometricEvaluation::Time::Watchdog::clearCanSigJump ()

Clears the flag for the [Watchdog](#) object to indicate that the signal jump block is no longer valid.

E.92.3.7 void BiometricEvaluation::Time::Watchdog::setExpired ()

Set a flag to indicate the timer expired.

E.92.3.8 void BiometricEvaluation::Time::Watchdog::clearExpired ()

Clear the flag indicating the timer expired.

E.92.4 Member Data Documentation**E.92.4.1 const uint8_t BiometricEvaluation::Time::Watchdog::PROCESSTIME = 0 [static]**

A [Watchdog](#) based on process time.

E.92.4.2 const uint8_t BiometricEvaluation::Time::Watchdog::REALTIME = 1 [static]

A [Watchdog](#) based on real (wall clock) time.

E.93 BiometricEvaluation::Process::Worker Class Reference

An abstraction of an instance that performs work on given data.

```
#include <be_process_worker.h>
```

Public Member Functions

- virtual int32_t [workerMain](#) ()=0
The method that will get called to start execution by a ProcessManager.
- tr1::shared_ptr< void > [getParameter](#) (const string &name)
Obtain a parameter passed to this [Worker](#).
- double [getParameterAsDouble](#) (const string &name)
Obtain a parameter passed to this [Worker](#) as a double.
- int64_t [getParameterAsInteger](#) (const string &name)
Obtain a parameter passed to this [Worker](#) as an integer.
- string [getParameterAsString](#) (const string &name)
Obtain a parameter passed to this [Worker](#) as a string.

- void [setParameter](#) (const string &name, tr1::shared_ptr< void > argument)
Pass a parameter to this [Worker](#).
- void [stop](#) ()
Tell this [Worker](#) to return ASAP.
- void [closeWorkerPipeEnds](#) () throw (Error::StrategyError)
Perform initialization for communication from [Worker](#) to [Manager](#).
- void [closeManagerPipeEnds](#) () throw (Error::StrategyError)
Perform initialization for communication from [Manager](#) to [Worker](#).
- int [getSendingPipe](#) () const throw (Error::ObjectDoesNotExist, Error::StrategyError)
Obtain the pipe used to send messages to this [Worker](#).
- int [getReceivingPipe](#) () const throw (Error::ObjectDoesNotExist, Error::StrategyError)
Obtain the pipe used to receive messages to this [Worker](#).
- void [sendMessageToManager](#) (const [Memory::uint8Array](#) &message) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Send a message to the [Manager](#).
- void [receiveMessageFromManager](#) ([Memory::uint8Array](#) &message) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Receive a message from the [Manager](#).
- void [_initCommunication](#) () throw (Error::StrategyError)
Perform general communication initialization from Constructor.
- virtual [~Worker](#) ()
[Worker](#) destructor.

Protected Member Functions

- [Worker](#) ()
[Worker](#) constructor.
- bool [stopRequested](#) () const
Determine if the parent has requested this child to exit.
- bool [waitForMessage](#) (int numSeconds=-1) const
Block while waiting for a message from the [Manager](#).

E.93.1 Detailed Description

An abstraction of an instance that performs work on given data.

E.93.2 Member Function Documentation

E.93.2.1 virtual int32_t BiometricEvaluation::Process::Worker::workerMain () [pure virtual]

The method that will get called to start execution by a ProcessManager.

Returns

Status code.

Note

If an object of this class is added to a [Process::ForkManager](#) object, the implementation of [Process::Worker::workerMain\(\)](#) should release all resources prior to returning.

E.93.2.2 `tr1::shared_ptr<void> BiometricEvaluation::Process::Worker::getParameter (const string & name)`

Obtain a parameter passed to this [Worker](#).

Parameters

<i>name</i>	The parameter name to retrieve.
-------------	---------------------------------

Returns

`shared_ptr` to the parameter argument.

Attention

If name does not exist, a new `shared_ptr` will be set for name.

E.93.2.3 `double BiometricEvaluation::Process::Worker::getParameterAsDouble (const string & name)`

Obtain a parameter passed to this [Worker](#) as a double.

Parameters

<i>name</i>	The parameter name to retrieve.
-------------	---------------------------------

Returns

Parameter as a double.

Attention

If name does not exist, a new `shared_ptr<double>` will be set for name.

E.93.2.4 `int64_t BiometricEvaluation::Process::Worker::getParameterAsInteger (const string & name)`

Obtain a parameter passed to this [Worker](#) as an integer.

Parameters

<i>name</i>	The parameter name to retrieve.
-------------	---------------------------------

Returns

Parameter as an integer.

Attention

If name does not exist, a new `shared_ptr<int64_t>` will be set for name.

E.93.2.5 `string BiometricEvaluation::Process::Worker::getParameterAsString (const string & name)`

Obtain a parameter passed to this [Worker](#) as a string.

Parameters

<i>name</i>	The parameter name to retrieve.
-------------	---------------------------------

Returns

Parameter as a string.

Attention

If name does not exist, a new `shared_ptr<string>` will be set for name.

E.93.2.6 `void BiometricEvaluation::Process::Worker::setParameter (const string & name, tr1::shared_ptr<void > argument)`

Pass a parameter to this [Worker](#).

Parameters

<i>name</i>	A unique identifier for this parameter
<i>argument</i>	A <code>shared_ptr</code> to the object to store.

E.93.2.7 `void BiometricEvaluation::Process::Worker::stop ()`

Tell this [Worker](#) to return ASAP.

Attention

This method should not be overridden.

E.93.2.8 `void BiometricEvaluation::Process::Worker::closeWorkerPipeEnds () throw (Error::StrategyError)`

Perform initialization for communication from [Worker](#) to [Manager](#).

Note

Behavior is undefined if called by a non-Manager.

Exceptions

<i>Error::StrategyError</i>	Communications not enabled.
---	-----------------------------

E.93.2.9 void BiometricEvaluation::Process::Worker::closeManagerPipeEnds () throw (Error::StrategyError)

Perform initialization for communication from [Manager](#) to [Worker](#).

Note

Behavior is undefined if called by a non-Worker.

Exceptions

<i>Error::StrategyError</i>	Communications not enabled.
---	-----------------------------

E.93.2.10 int BiometricEvaluation::Process::Worker::getSendingPipe () const throw (Error::ObjectDoesNotExist, Error::StrategyError)

Obtain the pipe used to send messages to this [Worker](#).

Returns

Sending pipe.

Exceptions

<i>Error::ObjectDoesNotExist</i>	Worker exiting soon, communication disabled.
<i>Error::StrategyError</i>	Communications not enabled.

E.93.2.11 int BiometricEvaluation::Process::Worker::getReceivingPipe () const throw (Error::ObjectDoesNotExist, Error::StrategyError)

Obtain the pipe used to receive messages to this [Worker](#).

Returns

Receiving pipe.

Exceptions

<i>Error::ObjectDoesNotExist</i>	Worker exiting soon, communication disabled.
<i>Error::StrategyError</i>	Communications not enabled.

E.93.2.12 void BiometricEvaluation::Process::Worker::sendMessageToManager (const Memory::uint8Array & *message*) throw (Error::ObjectDoesNotExist, Error::StrategyError)

Send a message to the [Manager](#).

Parameters

in	<i>message</i>	Message to send.
----	----------------	------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	Widowed pipe.
<i>Error::StrategyError</i>	Communications not enabled.

E.93.2.13 void BiometricEvaluation::Process::Worker::receiveMessageFromManager (Memory::uint8Array & *message*) throw (Error::ObjectDoesNotExist, Error::StrategyError)

Receive a message from the [Manager](#).

Parameters

out	<i>message</i>	Buffer to store the received message.
-----	----------------	---------------------------------------

Exceptions

<i>Error::ObjectDoesNotExist</i>	Widowed pipe.
<i>Error::StrategyError</i>	Communications not enabled.

See Also

[waitForMessage](#)

E.93.2.14 void BiometricEvaluation::Process::Worker::_initCommunication () throw (Error::StrategyError)

Perform general communication initialization from Constructor.

Exceptions

<i>Error::StrategyError</i>	Error in initialization.
---	--

E.93.2.15 `bool BiometricEvaluation::Process::Worker::stopRequested () const` [protected]

Determine if the parent has requested this child to exit.

Returns

Whether or not this child should exit.

Attention

This method should not be overridden.

E.93.2.16 `bool BiometricEvaluation::Process::Worker::waitForMessage (int numSeconds = -1) const`
[protected]

Block while waiting for a message from the [Manager](#).

Parameters

<i>numSeconds</i>	Number of seconds to wait for a message, or any value < 0 to wait forever.
-------------------	--

Returns


true once a message is ready to be read or false if an error occurred.

E.94 BiometricEvaluation::Process::WorkerController Class Reference

Wrapper of a [Worker](#) returned from a [Process::Manager](#).

```
#include <be_process_workercontroller.h>
```

Inheritance diagram for BiometricEvaluation::Process::WorkerController:



Public Member Functions

- [WorkerController](#) (tr1::shared_ptr< [Worker](#) > worker)
- virtual void [sendMessageToWorker](#) (const [Memory::uint8Array](#) &message) throw (Error::ObjectDoesNotExist, Error::StrategyError)
Send a message to the [Worker](#) contained within this [WorkerController](#).
- virtual void [setParameter](#) (const string &name, tr1::shared_ptr< void > argument)
Set the parameter to be passed to the [Worker](#).
- virtual void [setParameterFromDouble](#) (const string &name, double argument)

- Set a double parameter to be passed to the [Worker](#).*

 - virtual void [setParameterFromInteger](#) (const string &name, int64_t argument)

Set an integer parameter to be passed to the [Worker](#).

 - virtual void [setParameterFromString](#) (const string &name, const string &argument)

Set a string parameter to be passed to the [Worker](#).

 - virtual void [reset](#) () throw (Error::ObjectExists)

Reuse the [Worker](#).

 - virtual bool [isWorking](#) () const =0

Obtain whether or not [Worker](#) is working.

 - tr1::shared_ptr< [Worker](#) > [getWorker](#) () const

Obtain the [Worker](#) instance being wrapped.

 - virtual ~[WorkerController](#) ()

[WorkerController](#) destructor.

Protected Attributes

- tr1::shared_ptr< [Worker](#) > [_worker](#)

E.94.1 Detailed Description

Wrapper of a [Worker](#) returned from a [Process::Manager](#).

E.94.2 Constructor & Destructor Documentation

- E.94.2.1 [BiometricEvaluation::Process::WorkerController::WorkerController](#) (tr1::shared_ptr< [Worker](#) > *worker*)

[WorkerController](#) constructor.

Parameters

<i>worker</i>	The Worker instance to wrap.
---------------	--

E.94.3 Member Function Documentation

- E.94.3.1 virtual void [BiometricEvaluation::Process::WorkerController::sendMessageToWorker](#) (const [Memory::uint8Array](#) & *message*) throw (Error::ObjectDoesNotExist, Error::StrategyError) [virtual]

Send a message to the [Worker](#) contained within this [WorkerController](#).

Parameters

<i>message</i>	Message to send to the Worker .
----------------	---

Exceptions

<i>Error::ObjectDoesNotExist</i>	Worker receive pipe is closed (Worker object likely destroyed).
<i>Error::StrategyError</i>	Message sending failed.

E.94.3.2 `virtual void BiometricEvaluation::Process::WorkerController::setParameter (const string & name, tr1::shared_ptr< void > argument) [virtual]`

Set the parameter to be passed to the [Worker](#).

Parameters

in	<i>name</i>	The name representing the argument in the Worker .
in	<i>argument</i>	The argument to be passed to the Worker .

Note

Subsequent calls to [setParameter\(\)](#) with the same name will overwrite any exiting argument.

E.94.3.3 `virtual void BiometricEvaluation::Process::WorkerController::setParameterFromDouble (const string & name, double argument) [virtual]`

Set a double parameter to be passed to the [Worker](#).

Parameters

in	<i>name</i>	The name representing the argument in the Worker .
in	<i>argument</i>	The double to be passed to the Worker .

Note

Subsequent calls to [setParameter*\(\)](#) with the same name will overwrite any exiting argument.

E.94.3.4 `virtual void BiometricEvaluation::Process::WorkerController::setParameterFromInteger (const string & name, int64_t argument) [virtual]`

Set an integer parameter to be passed to the [Worker](#).

Parameters

in	<i>name</i>	The name representing the argument in the Worker .
in	<i>argument</i>	The integer to be passed to the Worker .

Note

Subsequent calls to [setParameter*\(\)](#) with the same name will overwrite any exiting argument.

E.94.3.5 `virtual void BiometricEvaluation::Process::WorkerController::setParameterFromString (const string & name, const string & argument) [virtual]`

Set a string parameter to be passed to the [Worker](#).

Parameters

in	<i>name</i>	The name representing the argument in the Worker .
in	<i>argument</i>	The string to be passed to the Worker .

Note

Subsequent calls to `setParameter*()` with the same name will overwrite any exiting argument.

E.94.3.6 `virtual void BiometricEvaluation::Process::WorkerController::reset () throw (Error::ObjectExists) [virtual]`

Reuse the [Worker](#).

Exceptions

Error::ObjectExists	The previously started Worker is still running.
-------------------------------------	---

Reimplemented in [BiometricEvaluation::Process::ForkWorkerController](#), and [BiometricEvaluation::Process::PO-
SIXThreadWorkerController](#).

E.94.3.7 `virtual bool BiometricEvaluation::Process::WorkerController::isWorking () const [pure
virtual]`

Obtain whether or not [Worker](#) is working.

Returns

Whether or not the [Worker](#) is working.

Implemented in [BiometricEvaluation::Process::ForkWorkerController](#), and [BiometricEvaluation::Process::PO-
SIXThreadWorkerController](#).

E.94.3.8 `tr1::shared_ptr<Worker> BiometricEvaluation::Process::WorkerController::getWorker () const`

Obtain the [Worker](#) instance being wrapped.

Returns

[Worker](#) instance.

E.94.4 Member Data Documentation

E.94.4.1 `tr1::shared_ptr<Worker> BiometricEvaluation::Process::WorkerController::_worker`
`[protected]`


The [Worker](#) instance that is running in this child

E.95 BiometricEvaluation::Image::WSQ Class Reference

A WSQ-encoded image.

```
#include <be_image_wsq.h>
```

Inheritance diagram for BiometricEvaluation::Image::WSQ:



Public Member Functions

- **WSQ** (const uint8_t *data, const uint64_t size) throw (Error::DataError, Error::StrategyError)
- [Memory::AutoArray](#)< uint8_t > [getRawData](#) () const throw (Error::DataError)
Accessor for the raw image data. The data returned should not be compressed or encoded.
- [Memory::AutoArray](#)< uint8_t > [getRawGrayscaleData](#) (uint8_t depth=8) const throw (Error::DataError, Error::ParameterError)
Accessor for decompressed data in grayscale.

Static Public Member Functions

- static bool [isWSQ](#) (const uint8_t *data)

Additional Inherited Members

E.95.1 Detailed Description

A WSQ-encoded image.

E.95.2 Member Function Documentation

E.95.2.1 `Memory::AutoArray<uint8_t> BiometricEvaluation::Image::WSQ::getRawData () const throw (Error::DataError) [virtual]`

Accessor for the raw image data. The data returned should not be compressed or encoded.

Returns

[Raw](#) image data.

Exceptions

Error::DataError	Error decompressing image data.
----------------------------------	---------------------------------

Implements [BiometricEvaluation::Image::Image](#).

E.95.2.2 `Memory::AutoArray<uint8_t> BiometricEvaluation::Image::WSQ::getRawGrayscaleData (uint8_t depth = 8) const throw (Error::DataError, Error::ParameterError) [virtual]`

Accessor for decompressed data in grayscale.

Parameters

<i>depth</i>	The desired bit depth of the resulting raw image. This value may either be 8 or 1.
--------------	--

Returns

[Raw](#) image buffer.

Exceptions

Error::DataError	Error decompressing image data.
Error::ParameterError	Invalid value for depth.

Note

This method does not save a cached copy of the decompressed image because the bit depth of the image can be changed between calls.

This method always returns an image that uses 8 bits to represent a single pixel. *depth* adjusts the number of pixels used to determine the color of the pixel in the 8 bit container, currently 1 (2 gray levels) or 8 (256 gray levels).

Implements [BiometricEvaluation::Image::Image](#).

E.95.2.3 `static bool BiometricEvaluation::Image::WSQ::isWSQ (const uint8_t * data) [static]`

Whether or not data is a [WSQ](#) image.

Parameters

<i>in</i>	<i>data</i>	The buffer to check.
-----------	-------------	----------------------

Returns

true if data appears to be a [WSQ](#) image, false otherwise

Appendix F

Example Documentation

F.1 `/Users/wsalamon/Work/p4-nigos/projects/EVALUATION/Main/common/src/include/be-io_listrecstore.h`

RecordStore that reads a list of keys from a text file, and retrieves the data from another RecordStore. List-RecordStores must be hand-crafted by first setting the 'Source Record Store', 'Type', and 'Count' properties in the .rscontrol.prop file. 'Source Record Store' is the complete path of the RecordStore containing the actual data records. Type must be 'List'. Count should match the number of entries in the file created next. Other properties are as in a "normal" RecordStore; see example below.

Second, create a file called 'KeyList.txt' in the RecordStore directory containing a list of keys, one per line.

ListRecordStores can also be created and modified with versions of rstool(1) from 2013 or later.

Example .rscontrol.prop file: Count = 10 Description = Search records for SDK TESTSDK Name = TestLRS
Type = List Source Record Store = /Users/wsalamon/sandbox/SD29.rs

Note

List RecordStores can only be opened read-only.

Index

- ~ArchiveRecordStore 196
 - BiometricEvaluation::IO::ArchiveRecordStore, 133_theLogFile
- ~AutoArray
 - BiometricEvaluation::IO::LogSheet, 256
- ~Compressor
 - BiometricEvaluation::Memory::AutoArray, 142
 - _worker
 - BiometricEvaluation::Process::WorkerController, 352
- ~ListRecordStore
 - BiometricEvaluation::IO::ListRecordStore, 242
 - _workers
 - BiometricEvaluation::Process::Manager, 262
- ~LogSheet
 - BiometricEvaluation::IO::LogSheet, 252
- ~OrderedMap
 - BiometricEvaluation::Memory::OrderedMap, 275
- ~OrderedMapConstIterator
 - BiometricEvaluation::Memory::OrderedMapConstIterator, 279
- ~OrderedMapIterator
 - BiometricEvaluation::Memory::OrderedMapIterator, 282
- ~Properties
 - BiometricEvaluation::IO::Properties, 295
- ~PropertiesFile
 - BiometricEvaluation::IO::PropertiesFile, 300
- _autoSync
 - BiometricEvaluation::IO::LogSheet, 256
- _canSigJump
 - BiometricEvaluation::Error::SignalManager, 323
- _cursor
 - BiometricEvaluation::IO::LogSheet, 256
- _entryNumber
 - BiometricEvaluation::IO::LogSheet, 256
- _initCommunication
 - BiometricEvaluation::Process::Worker, 348
- _pendingExit
 - BiometricEvaluation::Process::Manager, 262
- _raw_data
 - BiometricEvaluation::Image::Image, 213
- _sequenceFile
 - BiometricEvaluation::IO::LogSheet, 256
- _sigJumpBuf
 - BiometricEvaluation::Error::SignalManager, 323
- _stop
 - BiometricEvaluation::Process::ForkWorkerController, 352
- AN2K7Minutiae
 - BiometricEvaluation::Feature::AN2K7Minutiae, 91
- AN2KMinutiaeDataRecord
 - BiometricEvaluation::Finger::AN2KMinutiaeDataRecord, 94, 95
- AN2KRecord
 - BiometricEvaluation::DataInterchange::AN2KRecord, 98
- AN2KView
 - BiometricEvaluation::Finger::AN2KView, 103, 104
 - BiometricEvaluation::View::AN2KView, 109
- AN2KViewCapture
 - BiometricEvaluation::Finger::AN2KViewCapture, 113, 114
- AN2KViewFixedResolution
 - BiometricEvaluation::Finger::AN2KViewFixedResolution, 117
- AN2KViewLatent
 - BiometricEvaluation::Finger::AN2KViewLatent, 118, 119
- AN2KViewVariableResolution
 - BiometricEvaluation::Finger::AN2KViewVariableResolution, 121
 - BiometricEvaluation::View::AN2KViewVariableResolution, 124
- ANSI2004View
 - BiometricEvaluation::Finger::ANSI2004View, 128
- ANSI2007View
 - BiometricEvaluation::Finger::ANSI2007View, 130
- ARCHIVETYPE
 - BiometricEvaluation::IO::RecordStore, 317
- ASCIIBitmapTo8Bit
 - BiometricEvaluation::Image::NetPBM, 269
- ASCIIPixmapToBinaryPixmap

- BiometricEvaluation::Image::NetPBM, 269
- addMinutiaeDataRecord
 - BiometricEvaluation::Finger::AN2KView, 106
- addWorker
 - BiometricEvaluation::Process::ForkManager, 191
 - BiometricEvaluation::Process::Manager, 258
 - BiometricEvaluation::Process::POSIXThreadManager, 289
- Amputated
 - BiometricEvaluation::Finger::AN2KViewCapture-
::AmputatedBandaged, 89
- ArchiveRecordStore
 - BiometricEvaluation::IO::ArchiveRecordStore, 133
- Assisted
 - BiometricEvaluation::View::AN2KView::Device-
MonitoringMode, 177
- at
 - BiometricEvaluation::Memory::AutoArray, 143
- AutoArray
 - BiometricEvaluation::Memory::AutoArray, 141, 142
- BACKING_STORE
 - BiometricEvaluation::IO::CompressedRecordStore, 155
- BERKELEYDBTYPE
 - BiometricEvaluation::IO::RecordStore, 316
- Bandaged
 - BiometricEvaluation::Finger::AN2KViewCapture-
::AmputatedBandaged, 89
- begin
 - BiometricEvaluation::IO::Properties, 297
 - BiometricEvaluation::Memory::AutoArray, 144
 - BiometricEvaluation::Memory::OrderedMap, 276
- BinaryBitmapTo8Bit
 - BiometricEvaluation::Image::NetPBM, 269
- BiometricEvaluation::Finger::AN2KViewCapture::Amputated
 - Bandaged
 - Amputated, 89
 - Bandaged, 89
 - NA, 89
- BiometricEvaluation::Image::Resolution
 - NA, 319
 - PPCM, 319
 - PPI, 319
 - PPMM, 319
- BiometricEvaluation::View::AN2KView::DeviceMonitoring-
Mode
 - Assisted, 177
 - Controlled, 177
 - NA, 177
 - Observed, 177
 - Unattended, 177
 - Unknown, 177
- BiometricEvaluation::DataInterchange::AN2KRecord, 96
 - AN2KRecord, 98
 - CharacterSet, 98
 - DomainName, 98
 - getDate, 99
 - getDestinationAgency, 99
 - getDirectoryOfCharacterSets, 102
 - getDomainName, 101
 - getFingerCaptureCount, 100
 - getFingerCaptures, 101
 - getFingerLatentCount, 100
 - getFingerLatents, 100
 - getGreenwichMeanTime, 101
 - getMinutiaeDataRecordSet, 101
 - getNativeScanningResolution, 100
 - getNominalTransmittingResolution, 100
 - getOriginatingAgency, 100
 - getPriority, 101
 - getTransactionControlNumber, 100
 - getVersionNumber, 99
 - recordLocations, 99
- BiometricEvaluation::DataInterchange::AN2KRecord-
::CharacterSet, 148
 - CharacterSet, 148
 - commonName, 148
 - identifier, 148
 - version, 149
- BiometricEvaluation::DataInterchange::AN2KRecord-
::DomainName, 177
 - DomainName, 177
 - identifier, 178
 - version, 178
- BiometricEvaluation::Error, 65
 - errorStr, 66
- BiometricEvaluation::Error::ConversionError, 166
 - ConversionError, 167
- BiometricEvaluation::Error::DataError, 169
 - DataError, 169
- BiometricEvaluation::Error::Exception, 179
 - Exception, 180
 - getInfo, 181
- BiometricEvaluation::Error::FileError, 181
 - FileError, 181
- BiometricEvaluation::Error::MemoryError, 262
 - MemoryError, 263
- BiometricEvaluation::Error::NotImplemented, 270
 - NotImplemented, 270, 271
- BiometricEvaluation::Error::ObjectDoesNotExist, 271

- ObjectDoesNotExist, 271
- BiometricEvaluation::Error::ObjectExists, 271
 - ObjectExists, 272
- BiometricEvaluation::Error::ObjectIsClosed, 272
 - ObjectIsClosed, 273
- BiometricEvaluation::Error::ObjectIsOpen, 273
 - ObjectIsOpen, 273
- BiometricEvaluation::Error::ParameterError, 284
 - ParameterError, 284
- BiometricEvaluation::Error::SignalManager, 320
 - _canSigJump, 323
 - _sigJumpBuf, 323
 - clearSigHandled, 323
 - clearSignalSet, 322
 - setDefaultSignalSet, 322
 - setSigHandled, 323
 - setSignalSet, 322
 - sigHandled, 322
 - SignalManager, 321
 - start, 322
 - stop, 323
- BiometricEvaluation::Error::StrategyError, 336
 - StrategyError, 336
- BiometricEvaluation::Feature::AN2K7Minutiae, 89
 - AN2K7Minutiae, 91
 - convertCoordinate, 93
 - convertEncodingMethod, 92
 - convertPatternClassification, 92
 - getOriginatingFingerprintReadingSystem, 93
 - getPatternClassificationSet, 93
- BiometricEvaluation::Feature::AN2K7Minutiae::Encoding-Method, 178
- BiometricEvaluation::Feature::AN2K7Minutiae::Fingerprint-ReadingSystem, 188
 - equipment, 189
 - method, 188
 - name, 188
- BiometricEvaluation::Feature::AN2K7Minutiae::Pattern-Classification, 285
- BiometricEvaluation::Feature::AN2K7Minutiae::PatternBiometricEvaluation::Entry, 178
 - code, 179
 - Entry, 178
 - standard, 179
- BiometricEvaluation::Feature::CorePoint, 168
- BiometricEvaluation::Feature::DeltaPoint, 176
- BiometricEvaluation::Feature::INCITSMinutiae, 213
 - INCITSMinutiae, 216
 - setCorePointSet, 216
 - setDeltaPointSet, 216
 - setMinutiaPoints, 216
 - setRidgeCountItems, 216
- BiometricEvaluation::Feature::MinutiaPoint, 265
- BiometricEvaluation::Feature::Minutiae, 263
- BiometricEvaluation::Feature::MinutiaeFormat, 264
- BiometricEvaluation::Feature::MinutiaeType, 264
- BiometricEvaluation::Feature::RidgeCountExtraction-Method, 319
- BiometricEvaluation::Feature::RidgeCountItem, 320
- BiometricEvaluation::Finger, 66
 - operator<<, 68
- BiometricEvaluation::Finger::AN2KMinutiaeDataRecord, 94
 - AN2KMinutiaeDataRecord, 94, 95
 - getAN2K7Minutiae, 95
 - getImpressionType, 95
 - getRegisteredVendorBlock, 95
- BiometricEvaluation::Finger::AN2KView, 102
 - AN2KView, 103, 104
 - addMinutiaeDataRecord, 106
 - convertFingerImageCode, 105
 - convertPosition, 104
 - getImpressionType, 105
 - getMinutiaeDataRecordSet, 105
 - getPositions, 105
 - populateFGP, 105
 - setImpressionType, 106
 - setPositions, 106
- BiometricEvaluation::Finger::AN2KViewCapture, 111
 - AN2KViewCapture, 113, 114
 - convertAlternateFingerSegmentPosition, 114
 - convertAmputatedBandaged, 114
 - convertFingerSegmentPosition, 114
 - extractNISTQuality, 115
 - getAlternateFingerSegmentPositionSet, 116
 - getAmputatedBandaged, 115
 - getFingerSegmentPositionSet, 115
 - getFingerprintQualityMetric, 116
 - getNISTQualityMetric, 115
 - getSegmentationQualityMetric, 115
- BiometricEvaluation::Finger::AN2KViewCapture::Amputated-Bandaged, 89
 - Kind, 89
- BiometricEvaluation::Finger::AN2KViewCapture::Finger-SegmentPosition, 189
 - coordinates, 190
 - fingerPosition, 189
 - FingerSegmentPosition, 189
- BiometricEvaluation::Finger::AN2KViewFixedResolution, 116
 - AN2KViewFixedResolution, 117
- BiometricEvaluation::Finger::AN2KViewLatent, 118

- AN2KViewLatent, 118, 119
- getLatentQualityMetric, 119
- BiometricEvaluation::Finger::AN2KViewVariableResolution, 119
- AN2KViewVariableResolution, 121
- convertPrintPositionCoordinate, 122
- getImpressionType, 122
- getPositionDescriptors, 122
- getPositions, 121
- getPrintPositionCoordinates, 122
- parsePositionDescriptors, 122
- BiometricEvaluation::Finger::AN2KViewVariableResolution::PrintPositionCoordinate, 291
- coordinates, 292
- fingerView, 292
- PrintPositionCoordinate, 292
- segment, 292
- BiometricEvaluation::Finger::ANSI2004View, 127
- ANSI2004View, 128
- readCoreDeltaData, 128
- BiometricEvaluation::Finger::ANSI2007View, 129
- ANSI2007View, 130
- readCoreDeltaData, 131
- BiometricEvaluation::Finger::FingerImageCode, 188
- BiometricEvaluation::Finger::INCITSView, 217
- convertImpression, 220
- convertPosition, 220
- getCaptureEquipmentID, 221
- getCompressionAlgorithm, 222
- getFIRData, 223
- getFMRData, 223
- getImage, 222
- getImageDepth, 222
- getImageResolution, 222
- getImageSize, 222
- getImpressionType, 221
- getPosition, 221
- getQuality, 221
- getScanResolution, 223
- INCITSView, 219, 220
- isAppendixFCompliant, 221
- readCoreDeltaData, 227
- readExtendedDataBlock, 227
- readFMRHeader, 226
- readFVMR, 226
- readMinutiaeDataPoints, 226
- readRidgeCountData, 227
- setAppendixFCompliance, 225
- setCBEFFProductIDs, 224
- setCaptureEquipmentID, 224
- setImageData, 225
- setImageResolution, 225
- setImageSize, 225
- setImpressionType, 224
- setMinutiaeData, 223
- setPosition, 223
- setQuality, 224
- setScanResolution, 225
- setViewNumber, 224
- BiometricEvaluation::Finger::ISO2005View, 232
- ISO2005View, 234
- readCoreDeltaData, 234
- BiometricEvaluation::Finger::Impression, 213
- BiometricEvaluation::Finger::PatternClassification, 284
- BiometricEvaluation::Finger::Position, 287
- BiometricEvaluation::Framework, 68
- getCompileDate, 69
- getCompileTime, 69
- getCompiler, 69
- getCompilerVersion, 69
- getMajorVersion, 68
- getMinorVersion, 69
- BiometricEvaluation::IO, 71
- ManifestMap, 72
- PropertiesMap, 72
- BiometricEvaluation::IO::ArchiveRecordStore, 131
- ~ArchiveRecordStore, 133
- ArchiveRecordStore, 133
- changeName, 137
- flush, 136
- getArchiveName, 139
- getManifestName, 139
- getSpaceUsed, 134
- insert, 134
- length, 136
- needsVacuum, 138
- read, 135
- remove, 134
- replace, 135
- sequence, 136
- setCursorAtKey, 137
- sync, 134
- vacuum, 138
- BiometricEvaluation::IO::CompressedRecordStore, 149
- changeName, 155
- CompressedRecordStore, 150, 151
- flush, 154
- getSpaceUsed, 151
- insert, 152
- length, 153
- read, 152
- remove, 152

- replace, 153
- sequence, 154
- setCursorAtKey, 155
- sync, 151
- BiometricEvaluation::IO::Compressor, 156
 - ~Compressor, 158
 - compress, 159–161
 - Compressor, 158
 - createCompressor, 166
 - decompress, 162–164
 - GZIPTYPE, 166
 - getOption, 165
 - getOptionAsInteger, 165
 - Kind, 158
 - kindToString, 158
 - removeOption, 166
 - setOption, 164, 165
 - stringToKind, 159
- BiometricEvaluation::IO::DBRecordStore, 170
 - changeName, 175
 - DBRecordStore, 171
 - flush, 174
 - getSpaceUsed, 171
 - insert, 172
 - length, 173
 - read, 173
 - remove, 172
 - replace, 173
 - sequence, 174
 - setCursorAtKey, 175
 - sync, 172
- BiometricEvaluation::IO::FileRecordStore, 182
 - changeName, 187
 - FileRecordStore, 183
 - flush, 186
 - getSpaceUsed, 184
 - insert, 184
 - length, 185
 - read, 185
 - remove, 184
 - replace, 185
 - sequence, 186
 - setCursorAtKey, 187
- BiometricEvaluation::IO::GZip, 197
 - CHUNK_SIZE, 205
 - compress, 199–201
 - decompress, 201–204
 - MEMORY_LEVEL, 204
 - WINDOW_BITS, 204
- BiometricEvaluation::IO::ListRecordStore, 241
 - ~ListRecordStore, 242
 - changeName, 245
 - flush, 244
 - getSpaceUsed, 246
 - insert, 242
 - length, 243
 - ListRecordStore, 242
 - read, 243
 - remove, 242
 - replace, 243
 - sequence, 244
 - setCursorAtKey, 245
 - sync, 244
- BiometricEvaluation::IO::LogCabinet, 247
 - getCount, 249
 - getDescription, 248
 - getName, 248
 - LogCabinet, 247
 - newLogSheet, 248
 - remove, 249
- BiometricEvaluation::IO::LogSheet, 249
 - ~LogSheet, 252
 - _autoSync, 256
 - _cursor, 256
 - _entryNumber, 256
 - _sequenceFile, 256
 - _theLogFile, 256
 - CommentDelimiter, 255
 - DescriptionTag, 256
 - EntryDelimiter, 255
 - getCurrentEntry, 253
 - getCurrentEntryNumber, 253
 - LogSheet, 251, 252
 - mergeLogSheets, 255
 - newEntry, 253
 - operator=, 255
 - resetCurrentEntry, 253
 - sequence, 254
 - setAutoSync, 254
 - sync, 253
 - trim, 254
 - updateCursor, 255
 - write, 252
 - writeComment, 252
- BiometricEvaluation::IO::ManifestEntry, 262
 - offset, 262
 - size, 262
- BiometricEvaluation::IO::Properties, 293
 - ~Properties, 295
 - begin, 297
 - const_iterator, 294
 - end, 297

- getMode, 297
- getProperty, 296
- getPropertyAsDouble, 297
- getPropertyAsInteger, 296
- initWithBuffer, 298
- Properties, 294
- removeProperty, 296
- setProperty, 295
- setPropertyFromDouble, 295
- setPropertyFromInteger, 295
- BiometricEvaluation::IO::PropertiesFile, 298
 - ~PropertiesFile, 300
 - changeName, 300
 - PropertiesFile, 299
 - sync, 300
- BiometricEvaluation::IO::RecordStore, 302
 - ARCHIVETYPE, 317
 - BERKELEYDBTYPE, 316
 - COMPRESSEDTYPE, 317
 - COUNTPROPERTY, 316
 - changeDescription, 306
 - changeName, 306
 - containsKey, 315
 - createRecordStore, 313
 - DEFAULTTYPE, 317
 - FILETYPE, 317
 - flush, 311
 - genKeySegName, 315
 - getCount, 306
 - getDescription, 306
 - getName, 305
 - getProperties, 315
 - getSpaceUsed, 307
 - insert, 307, 308
 - LISTTYPE, 317
 - length, 310
 - mergeRecordStores, 314
 - NAMEPROPERTY, 316
 - openRecordStore, 313
 - read, 308, 309
 - RecordStore, 305
 - remove, 308
 - removeRecordStore, 314
 - replace, 309, 310
 - SQLITETYPE, 317
 - sequence, 311, 312
 - setCursorAtKey, 312
 - setProperties, 315
 - sync, 307
 - TYPEPROPERTY, 316
- BiometricEvaluation::IO::SQLiteRecordStore, 324
 - changeDescription, 326
 - changeName, 326
 - cleanup, 332
 - createKeyValueTable, 331
 - createStructure, 330
 - flush, 329
 - getSpaceUsed, 326
 - insert, 327
 - length, 328
 - read, 327
 - readSegments, 331
 - remove, 327
 - replace, 328
 - sequence, 329
 - setCursorAtKey, 330
 - sqliteError, 330
 - validateKeyValueTable, 330
 - validateSchema, 331
- BiometricEvaluation::IO::Utility, 73
 - constructAndCheckPath, 76
 - copyDirectoryContents, 74
 - createTemporaryFile, 79
 - fileExists, 75
 - getFileSize, 75
 - isReadable, 78
 - isWritable, 78
 - makePath, 76
 - readFile, 77
 - removeDirectory, 74
 - setAsideName, 75
 - validateRootName, 76
 - writeFile, 77, 78
- BiometricEvaluation::Image, 69
 - distance, 71
 - operator<=, 71
- BiometricEvaluation::Image::CompressionAlgorithm, 156
- BiometricEvaluation::Image::Coordinate, 167
 - Coordinate, 168
 - x, 168
 - xDistance, 168
 - y, 168
 - yDistance, 168
- BiometricEvaluation::Image::Image, 205
 - _raw_data, 213
 - bitsPerComponent, 213
 - getCompressionAlgorithm, 207, 211, 212
 - getData, 208
 - getDepth, 209
 - getDimensions, 209
 - getRawData, 208

- getRawGrayscaleData, 208
- getResolution, 208
- Image, 207
- openImage, 210
- setDepth, 212
- setDimensions, 212
- setResolution, 212
- valueInColorspace, 209
- BiometricEvaluation::Image::JPEG, 235
 - getRawData, 236
 - getRawGrayscaleData, 235
 - isJPEG, 236
- BiometricEvaluation::Image::JPEG2000, 237
 - getRawData, 238
 - getRawGrayscaleData, 238
 - isJPEG2000, 239
 - JPEG2000, 237
- BiometricEvaluation::Image::JPEGL, 239
 - getRawData, 240
 - getRawGrayscaleData, 240
 - isJPEGL, 241
- BiometricEvaluation::Image::NetPBM, 265
 - ASCIIBitmapTo8Bit, 269
 - ASCIIPixmapToBinaryPixmap, 269
 - BinaryBitmapTo8Bit, 269
 - getNextValue, 268
 - getRawData, 266
 - getRawGrayscaleData, 267
 - isNetPBM, 267
 - skipComment, 268
 - skipLine, 268
- BiometricEvaluation::Image::PNG, 285
 - getRawData, 286
 - getRawGrayscaleData, 286
 - isPNG, 287
- BiometricEvaluation::Image::Raw, 300
 - getRawData, 301
 - getRawGrayscaleData, 301
- BiometricEvaluation::Image::Resolution, 318
 - Kind, 318
 - Resolution, 319
 - units, 319
 - xRes, 319
 - yRes, 319
- BiometricEvaluation::Image::Size, 323
 - Size, 324
 - xSize, 324
 - ySize, 324
- BiometricEvaluation::Image::WSQ, 353
 - getRawData, 353
 - getRawGrayscaleData, 354
 - isWSQ, 354
- BiometricEvaluation::Memory, 80
- BiometricEvaluation::Memory::AutoArray
 - ~AutoArray, 142
 - at, 143
 - AutoArray, 141, 142
 - begin, 144
 - const_iterator, 141
 - const_reference, 141
 - copy, 145, 146
 - end, 144
 - iterator, 141
 - operator const T *, 142
 - operator T *, 142
 - operator=, 146
 - reference, 141
 - resize, 145
 - size, 145
 - size_type, 141
 - swap, 146
 - value_type, 141
- BiometricEvaluation::Memory::AutoArray< T >, 139
- BiometricEvaluation::Memory::AutoBuffer
 - value_type, 147
- BiometricEvaluation::Memory::AutoBuffer< T >, 147
- BiometricEvaluation::Memory::IndexedBuffer, 228
 - getIndex, 229
 - getSize, 229
 - IndexedBuffer, 229
 - scan, 231
 - scanBeU16Val, 230
 - scanBeU32Val, 231
 - scanU16Val, 230
 - scanU32Val, 231
 - scanU64Val, 231
 - scanU8Val, 230
 - setIndex, 229
- BiometricEvaluation::Memory::OrderedMap
 - ~OrderedMap, 275
 - begin, 276
 - end, 276
 - erase, 275, 276
 - find, 277
 - keyExists, 277
 - OrderedMap, 275
 - push_back, 275
 - size, 277
- BiometricEvaluation::Memory::OrderedMap< Key, T >, 274
- BiometricEvaluation::Memory::OrderedMapConstIterator
 - ~OrderedMapConstIterator, 279

- operator*, 279
- operator++, 280
- operator->, 279
- operator--, 280
- operator==, 280
- OrderedMapConstIterator, 279
- BiometricEvaluation::Memory::OrderedMapConstIterator< Key, T >, 278
- BiometricEvaluation::Memory::OrderedMapIterator
 - ~OrderedMapIterator, 282
 - operator*, 282
 - operator++, 283
 - operator->, 282
 - operator--, 283
 - operator==, 283
 - OrderedMapIterator, 282
- BiometricEvaluation::Memory::OrderedMapIterator< Key, T >, 281
- BiometricEvaluation::Process, 81
 - ParameterList, 81
- BiometricEvaluation::Process::ForkManager, 190
 - addWorker, 191
 - broadcastSignal, 193
 - FORKMANAGERS, 194
 - ForkManager, 191
 - getIsWorkingStatus, 193
 - responsibleFor, 193
 - setNotWorking, 193
 - startWorker, 192
 - startWorkers, 191
 - stopWorker, 192
- BiometricEvaluation::Process::ForkWorkerController, 194
 - _stop, 196
 - ForkManager::addWorker, 197
 - ForkManager::startWorker, 196
 - ForkManager::startWorkers, 196
 - ForkManager::stopWorker, 197
 - getPID, 195
 - isWorking, 195
 - reset, 195
- BiometricEvaluation::Process::Manager, 256
 - _pendingExit, 262
 - _workers, 262
 - addWorker, 258
 - broadcastMessage, 261
 - getNextMessage, 261
 - getNumActiveWorkers, 258
 - getNumCompletedWorkers, 258
 - getTotalWorkers, 259
 - reset, 260
- startWorker, 259
- startWorkers, 259
- stopWorker, 260
- waitForMessage, 260
- BiometricEvaluation::Process::POSIXThreadManager, 288
 - addWorker, 289
 - POSIXThreadManager, 288
 - startWorker, 289
 - startWorkers, 289
 - stopWorker, 290
- BiometricEvaluation::Process::POSIXThreadWorkerController, 290
 - isWorking, 291
 - reset, 291
- BiometricEvaluation::Process::Statistics, 332
 - callStatistics_logStats, 336
 - getCPUTimes, 333
 - getMemorySizes, 334
 - getNumThreads, 334
 - logStats, 335
 - startAutoLogging, 335
 - Statistics, 333
 - stopAutoLogging, 335
- BiometricEvaluation::Process::Worker, 343
 - _initCommunication, 348
 - closeManagerPipeEnds, 347
 - closeWorkerPipeEnds, 346
 - getParameter, 345
 - getParameterAsDouble, 345
 - getParameterAsInteger, 345
 - getParameterAsString, 346
 - getReceivingPipe, 347
 - getSendingPipe, 347
 - receiveMessageFromManager, 348
 - sendMessageToManager, 348
 - setParameter, 346
 - stop, 346
 - stopRequested, 349
 - waitForMessage, 349
 - workerMain, 344
- BiometricEvaluation::Process::WorkerController, 349
 - _worker, 352
 - getWorker, 352
 - isWorking, 352
 - reset, 352
 - sendMessageToWorker, 350
 - setParameter, 351
 - setParameterFromDouble, 351
 - setParameterFromInteger, 351
 - setParameterFromString, 351

- WorkerController, 350
- BiometricEvaluation::System, 81
 - getCPUCount, 82
 - getLoadAverage, 82
 - getRealMemorySize, 82
- BiometricEvaluation::Text, 83
 - digest, 83, 84
 - dirname, 85
 - filename, 85
 - split, 84
- BiometricEvaluation::Time, 85
- BiometricEvaluation::Time::Timer, 337
 - elapsed, 338
 - start, 337
 - stop, 337
 - Timer, 337
- BiometricEvaluation::Time::Watchdog, 340
 - clearCanSigJump, 343
 - clearExpired, 343
 - expired, 342
 - PROCESSTIME, 343
 - REALTIME, 343
 - setCanSigJump, 342
 - setExpired, 343
 - setInterval, 342
 - start, 342
 - stop, 342
 - Watchdog, 341
- BiometricEvaluation::View, 86
 - operator<<, 87
- BiometricEvaluation::View::AN2KView, 106
 - AN2KView, 109
 - convertCompressionAlgorithm, 109
 - convertDeviceMonitoringMode, 109
 - getAN2KRecord, 111
 - getCompressionAlgorithm, 110
 - getImage, 110
 - getImageDepth, 110
 - getImageResolution, 110
 - getImageSize, 110
 - getMinutiaeDataRecordSet, 111
 - getRecordType, 111
 - getScanResolution, 111
- BiometricEvaluation::View::AN2KView::DeviceMonitoring-Mode, 176
- BiometricEvaluation::View::AN2KView::Kind, 177
- BiometricEvaluation::View::AN2KView::RecordType, 317
- BiometricEvaluation::View::AN2KViewVariableResolution, 123
 - AN2KViewVariableResolution, 124
 - extractQuality, 125
 - getCaptureDate, 125
 - getComment, 125
 - getQualityMetric, 126
 - getSourceAgency, 125
 - getUserDefinedField, 125
 - parseUserDefinedField, 126
- BiometricEvaluation::View::AN2KViewVariableResolution::AN2KQualityMetric, 96
- BiometricEvaluation::View::View, 338
 - getCompressionAlgorithm, 340
 - getImage, 339
 - getImageDepth, 339
 - getImageResolution, 339
 - getImageSize, 339
 - getScanResolution, 340
- bitsPerComponent
 - BiometricEvaluation::Image::Image, 213
- broadcastMessage
 - BiometricEvaluation::Process::Manager, 261
- broadcastSignal
 - BiometricEvaluation::Process::ForkManager, 193
- CHUNK_SIZE
 - BiometricEvaluation::IO::GZip, 205
- COMPRESSEDTYPE
 - BiometricEvaluation::IO::RecordStore, 317
- COMPRESSION_LEVEL
 - BiometricEvaluation::IO::GZip, 204
- CONTROLFILENAME
 - BiometricEvaluation::IO::RecordStore, 316
- COUNTPROPERTY
 - BiometricEvaluation::IO::RecordStore, 316
- callStatistics_logStats
 - BiometricEvaluation::Process::Statistics, 336
- changeDescription
 - BiometricEvaluation::IO::RecordStore, 306
 - BiometricEvaluation::IO::SQLiteRecordStore, 326
- changeName
 - BiometricEvaluation::IO::ArchiveRecordStore, 137
 - BiometricEvaluation::IO::CompressedRecordStore, 155
 - BiometricEvaluation::IO::DBRecordStore, 175
 - BiometricEvaluation::IO::FileRecordStore, 187
 - BiometricEvaluation::IO::ListRecordStore, 245
 - BiometricEvaluation::IO::PropertiesFile, 300
 - BiometricEvaluation::IO::RecordStore, 306
 - BiometricEvaluation::IO::SQLiteRecordStore, 326
- CharacterSet
 - BiometricEvaluation::DataInterchange::AN2KRecord, 98

- BiometricEvaluation::DataInterchange::AN2KRecord-
::CharacterSet, 148
- cleanup
 - BiometricEvaluation::IO::SQLiteRecordStore, 332
- clearCanSigJump
 - BiometricEvaluation::Time::Watchdog, 343
- clearExpired
 - BiometricEvaluation::Time::Watchdog, 343
- clearSigHandled
 - BiometricEvaluation::Error::SignalManager, 323
- clearSignalSet
 - BiometricEvaluation::Error::SignalManager, 322
- closeManagerPipeEnds
 - BiometricEvaluation::Process::Worker, 347
- closeWorkerPipeEnds
 - BiometricEvaluation::Process::Worker, 346
- code
 - BiometricEvaluation::Feature::AN2K7Minutiae:-
PatternClassification::Entry, 179
- CommentDelimiter
 - BiometricEvaluation::IO::LogSheet, 255
- commonName
 - BiometricEvaluation::DataInterchange::AN2KRecord-
::CharacterSet, 148
- compress
 - BiometricEvaluation::IO::Compressor, 159–161
 - BiometricEvaluation::IO::GZip, 199–201
- CompressedRecordStore
 - BiometricEvaluation::IO::CompressedRecordStore,
150, 151
- Compressor
 - BiometricEvaluation::IO::Compressor, 158
- const_iterator
 - BiometricEvaluation::IO::Properties, 294
 - BiometricEvaluation::Memory::AutoArray, 141
- const_reference
 - BiometricEvaluation::Memory::AutoArray, 141
- constructAndCheckPath
 - BiometricEvaluation::IO::Utility, 76
- containsKey
 - BiometricEvaluation::IO::RecordStore, 315
- Controlled
 - BiometricEvaluation::View::AN2KView::Device-
MonitoringMode, 177
- ConversionError
 - BiometricEvaluation::Error::ConversionError, 167
- convertAlternateFingerSegmentPosition
 - BiometricEvaluation::Finger::AN2KViewCapture,
114
- convertAmputatedBandaged
 - BiometricEvaluation::Finger::AN2KViewCapture, DataError
- convertCompressionAlgorithm
 - BiometricEvaluation::View::AN2KView, 109
- convertCoordinate
 - BiometricEvaluation::Feature::AN2K7Minutiae, 93
- convertDeviceMonitoringMode
 - BiometricEvaluation::View::AN2KView, 109
- convertEncodingMethod
 - BiometricEvaluation::Feature::AN2K7Minutiae, 92
- convertFingerImageCode
 - BiometricEvaluation::Finger::AN2KView, 105
- convertFingerSegmentPosition
 - BiometricEvaluation::Finger::AN2KViewCapture,
114
- convertImpression
 - BiometricEvaluation::Finger::INCITSView, 220
- convertPatternClassification
 - BiometricEvaluation::Feature::AN2K7Minutiae, 92
- convertPosition
 - BiometricEvaluation::Finger::AN2KView, 104
 - BiometricEvaluation::Finger::INCITSView, 220
- convertPrintPositionCoordinate
 - BiometricEvaluation::Finger::AN2KView Variable-
Resolution, 122
- Coordinate
 - BiometricEvaluation::Image::Coordinate, 168
- coordinates
 - BiometricEvaluation::Finger::AN2KViewCapture-
::FingerSegmentPosition, 190
 - BiometricEvaluation::Finger::AN2KView Variable-
Resolution::PrintPositionCoordinate, 292
- copy
 - BiometricEvaluation::Memory::AutoArray, 145,
146
- copyDirectoryContents
 - BiometricEvaluation::IO::Utility, 74
- createCompressor
 - BiometricEvaluation::IO::Compressor, 166
- createKeyValueTable
 - BiometricEvaluation::IO::SQLiteRecordStore, 331
- createRecordStore
 - BiometricEvaluation::IO::RecordStore, 313
- createStructure
 - BiometricEvaluation::IO::SQLiteRecordStore, 330
- createTemporaryFile
 - BiometricEvaluation::IO::Utility, 79
- DBRecordStore
 - BiometricEvaluation::IO::DBRecordStore, 171
- DEFAULTTYPE
 - BiometricEvaluation::IO::RecordStore, 317

- BiometricEvaluation::Error::DataError, 169
- decompress
 - BiometricEvaluation::IO::Compressor, 162–164
 - BiometricEvaluation::IO::GZip, 201–204
- DescriptionTag
 - BiometricEvaluation::IO::LogSheet, 256
- digest
 - BiometricEvaluation::Text, 83, 84
- dirname
 - BiometricEvaluation::Text, 85
- distance
 - BiometricEvaluation::Image, 71
- DomainName
 - BiometricEvaluation::DataInterchange::AN2KRecord, 98
 - BiometricEvaluation::DataInterchange::AN2KRecord-
::DomainName, 177
- elapsed
 - BiometricEvaluation::Time::Timer, 338
- end
 - BiometricEvaluation::IO::Properties, 297
 - BiometricEvaluation::Memory::AutoArray, 144
 - BiometricEvaluation::Memory::OrderedMap, 276
- Entry
 - BiometricEvaluation::Feature::AN2K7Minutiae::-
PatternClassification::Entry, 178
- EntryDelimiter
 - BiometricEvaluation::IO::LogSheet, 255
- equipment
 - BiometricEvaluation::Feature::AN2K7Minutiae::-
FingerprintReadingSystem, 189
- erase
 - BiometricEvaluation::Memory::OrderedMap, 275, 276
- errorStr
 - BiometricEvaluation::Error, 66
- Exception
 - BiometricEvaluation::Error::Exception, 180
- expired
 - BiometricEvaluation::Time::Watchdog, 342
- extractNISTQuality
 - BiometricEvaluation::Finger::AN2KViewCapture, 115
- extractQuality
 - BiometricEvaluation::View::AN2KViewVariable-
Resolution, 125
- FILETYPE
 - BiometricEvaluation::IO::RecordStore, 317
- FORKMANAGERS
 - BiometricEvaluation::Process::ForkManager, 194
- FileError
 - BiometricEvaluation::Error::FileError, 181
- fileExists
 - BiometricEvaluation::IO::Utility, 75
- FileRecordStore
 - BiometricEvaluation::IO::FileRecordStore, 183
- filename
 - BiometricEvaluation::Text, 85
- find
 - BiometricEvaluation::Memory::OrderedMap, 277
- fingerPosition
 - BiometricEvaluation::Finger::AN2KViewCapture-
::FingerSegmentPosition, 189
- FingerSegmentPosition
 - BiometricEvaluation::Finger::AN2KViewCapture-
::FingerSegmentPosition, 189
- fingerView
 - BiometricEvaluation::Finger::AN2KViewVariable-
Resolution::PrintPositionCoordinate, 292
- flush
 - BiometricEvaluation::IO::ArchiveRecordStore, 136
 - BiometricEvaluation::IO::CompressedRecordStore, 154
 - BiometricEvaluation::IO::DBRecordStore, 174
 - BiometricEvaluation::IO::FileRecordStore, 186
 - BiometricEvaluation::IO::ListRecordStore, 244
 - BiometricEvaluation::IO::RecordStore, 311
 - BiometricEvaluation::IO::SQLiteRecordStore, 329
- ForkManager
 - BiometricEvaluation::Process::ForkManager, 191
- ForkManager::addWorker
 - BiometricEvaluation::Process::ForkWorkerController, 197
- ForkManager::startWorker
 - BiometricEvaluation::Process::ForkWorkerController, 196
- ForkManager::startWorkers
 - BiometricEvaluation::Process::ForkWorkerController, 196
- ForkManager::stopWorker
 - BiometricEvaluation::Process::ForkWorkerController, 197
- GZIPTYPE
 - BiometricEvaluation::IO::Compressor, 166
- genKeySegName
 - BiometricEvaluation::IO::RecordStore, 315
- getAN2K7Minutiae
 - BiometricEvaluation::Finger::AN2KMinutiaeData-
Record, 95
- getAN2KRecord
 - BiometricEvaluation::View::AN2KView, 111

- getAlternateFingerSegmentPositionSet
 - BiometricEvaluation::Finger::AN2KViewCapture, 116
- getAmputatedBandaged
 - BiometricEvaluation::Finger::AN2KViewCapture, 115
- getArchiveName
 - BiometricEvaluation::IO::ArchiveRecordStore, 139
- getCPUCount
 - BiometricEvaluation::System, 82
- getCPUTimes
 - BiometricEvaluation::Process::Statistics, 333
- getCaptureDate
 - BiometricEvaluation::View::AN2KViewVariable-Resolution, 125
- getCaptureEquipmentID
 - BiometricEvaluation::Finger::INCITSView, 221
- getComment
 - BiometricEvaluation::View::AN2KViewVariable-Resolution, 125
- getCompileDate
 - BiometricEvaluation::Framework, 69
- getCompileTime
 - BiometricEvaluation::Framework, 69
- getCompiler
 - BiometricEvaluation::Framework, 69
- getCompilerVersion
 - BiometricEvaluation::Framework, 69
- getCompressionAlgorithm
 - BiometricEvaluation::Finger::INCITSView, 222
 - BiometricEvaluation::Image::Image, 207, 211, 212
 - BiometricEvaluation::View::AN2KView, 110
 - BiometricEvaluation::View::View, 340
- getCount
 - BiometricEvaluation::IO::LogCabinet, 249
 - BiometricEvaluation::IO::RecordStore, 306
- getCurrentEntry
 - BiometricEvaluation::IO::LogSheet, 253
- getCurrentEntryNumber
 - BiometricEvaluation::IO::LogSheet, 253
- getData
 - BiometricEvaluation::Image::Image, 208
- getDate
 - BiometricEvaluation::DataInterchange::AN2KRecord, 99
- getDepth
 - BiometricEvaluation::Image::Image, 209
- getDescription
 - BiometricEvaluation::IO::LogCabinet, 248
 - BiometricEvaluation::IO::RecordStore, 306
- getDestinationAgency
 - BiometricEvaluation::DataInterchange::AN2KRecord, 99
- getDimensions
 - BiometricEvaluation::Image::Image, 209
- getDirectoryOfCharacterSets
 - BiometricEvaluation::DataInterchange::AN2KRecord, 102
- getDomainName
 - BiometricEvaluation::DataInterchange::AN2KRecord, 101
- getFIRData
 - BiometricEvaluation::Finger::INCITSView, 223
- getFMRData
 - BiometricEvaluation::Finger::INCITSView, 223
- getFileSize
 - BiometricEvaluation::IO::Utility, 75
- getFingerCaptureCount
 - BiometricEvaluation::DataInterchange::AN2KRecord, 100
- getFingerCaptures
 - BiometricEvaluation::DataInterchange::AN2KRecord, 101
- getFingerLatentCount
 - BiometricEvaluation::DataInterchange::AN2KRecord, 100
- getFingerLatents
 - BiometricEvaluation::DataInterchange::AN2KRecord, 100
- getFingerSegmentPositionSet
 - BiometricEvaluation::Finger::AN2KViewCapture, 115
- getFingerprintQualityMetric
 - BiometricEvaluation::Finger::AN2KViewCapture, 116
- getGreenwichMeanTime
 - BiometricEvaluation::DataInterchange::AN2KRecord, 101
- getImage
 - BiometricEvaluation::Finger::INCITSView, 222
 - BiometricEvaluation::View::AN2KView, 110
 - BiometricEvaluation::View::View, 339
- getImageDepth
 - BiometricEvaluation::Finger::INCITSView, 222
 - BiometricEvaluation::View::AN2KView, 110
 - BiometricEvaluation::View::View, 339
- getImageResolution
 - BiometricEvaluation::Finger::INCITSView, 222
 - BiometricEvaluation::View::AN2KView, 110
 - BiometricEvaluation::View::View, 339
- getImageSize
 - BiometricEvaluation::Finger::INCITSView, 222

- BiometricEvaluation::View::AN2KView, 110
- BiometricEvaluation::View::View, 339
- getImpressionType
 - BiometricEvaluation::Finger::AN2KMinutiaeData-Record, 95
 - BiometricEvaluation::Finger::AN2KView, 105
 - BiometricEvaluation::Finger::AN2KViewVariable-Resolution, 122
 - BiometricEvaluation::Finger::INCITSView, 221
- getIndex
 - BiometricEvaluation::Memory::IndexedBuffer, 229
- getInfo
 - BiometricEvaluation::Error::Exception, 181
- getIsWorkingStatus
 - BiometricEvaluation::Process::ForkManager, 193
- getLatentQualityMetric
 - BiometricEvaluation::Finger::AN2KViewLatent, 119
- getLoadAverage
 - BiometricEvaluation::System, 82
- getMajorVersion
 - BiometricEvaluation::Framework, 68
- getManifestName
 - BiometricEvaluation::IO::ArchiveRecordStore, 139
- getMemorySizes
 - BiometricEvaluation::Process::Statistics, 334
- getMinorVersion
 - BiometricEvaluation::Framework, 69
- getMinutiaeDataRecordSet
 - BiometricEvaluation::DataInterchange::AN2KRecord, 101
 - BiometricEvaluation::Finger::AN2KView, 105
 - BiometricEvaluation::View::AN2KView, 111
- getMode
 - BiometricEvaluation::IO::Properties, 297
- getNISTQualityMetric
 - BiometricEvaluation::Finger::AN2KViewCapture, 115
- getName
 - BiometricEvaluation::IO::LogCabinet, 248
 - BiometricEvaluation::IO::RecordStore, 305
- getNativeScanningResolution
 - BiometricEvaluation::DataInterchange::AN2KRecord, 100
- getNextMessage
 - BiometricEvaluation::Process::Manager, 261
- getNextValue
 - BiometricEvaluation::Image::NetPBM, 268
- getNominalTransmittingResolution
 - BiometricEvaluation::DataInterchange::AN2KRecord, 100
- getNumActiveWorkers
 - BiometricEvaluation::Process::Manager, 258
- getNumCompletedWorkers
 - BiometricEvaluation::Process::Manager, 258
- getNumThreads
 - BiometricEvaluation::Process::Statistics, 334
- getOptionAsInteger
 - BiometricEvaluation::IO::Compressor, 165
- getOptionAsInteger
 - BiometricEvaluation::IO::Compressor, 165
- getOriginatingAgency
 - BiometricEvaluation::DataInterchange::AN2KRecord, 100
- getOriginatingFingerprintReadingSystem
 - BiometricEvaluation::Feature::AN2K7Minutiae, 93
- getPID
 - BiometricEvaluation::Process::ForkWorkerController, 195
- getParameter
 - BiometricEvaluation::Process::Worker, 345
- getParameterAsDouble
 - BiometricEvaluation::Process::Worker, 345
- getParameterAsInteger
 - BiometricEvaluation::Process::Worker, 345
- getParameterAsString
 - BiometricEvaluation::Process::Worker, 346
- getPatternClassificationSet
 - BiometricEvaluation::Feature::AN2K7Minutiae, 93
- getPosition
 - BiometricEvaluation::Finger::INCITSView, 221
- getPositionDescriptors
 - BiometricEvaluation::Finger::AN2KViewVariable-Resolution, 122
- getPositions
 - BiometricEvaluation::Finger::AN2KView, 105
 - BiometricEvaluation::Finger::AN2KViewVariable-Resolution, 121
- getPrintPositionCoordinates
 - BiometricEvaluation::Finger::AN2KViewVariable-Resolution, 122
- getPriority
 - BiometricEvaluation::DataInterchange::AN2KRecord, 101
- getProperties
 - BiometricEvaluation::IO::RecordStore, 315
- getProperty
 - BiometricEvaluation::IO::Properties, 296
- getPropertyAsDouble
 - BiometricEvaluation::IO::Properties, 297
- getPropertyAsInteger
 - BiometricEvaluation::IO::Properties, 296

- getQuality
 - BiometricEvaluation::Finger::INCITSView, 221
- getQualityMetric
 - BiometricEvaluation::View::AN2KViewVariable-Resolution, 126
- getRawData
 - BiometricEvaluation::Image::Image, 208
 - BiometricEvaluation::Image::JPEG, 236
 - BiometricEvaluation::Image::JPEG2000, 238
 - BiometricEvaluation::Image::JPEG, 240
 - BiometricEvaluation::Image::NetPBM, 266
 - BiometricEvaluation::Image::PNG, 286
 - BiometricEvaluation::Image::Raw, 301
 - BiometricEvaluation::Image::WSQ, 353
- getRawGrayscaleData
 - BiometricEvaluation::Image::Image, 208
 - BiometricEvaluation::Image::JPEG, 235
 - BiometricEvaluation::Image::JPEG2000, 238
 - BiometricEvaluation::Image::JPEG, 240
 - BiometricEvaluation::Image::NetPBM, 267
 - BiometricEvaluation::Image::PNG, 286
 - BiometricEvaluation::Image::Raw, 301
 - BiometricEvaluation::Image::WSQ, 354
- getRealMemorySize
 - BiometricEvaluation::System, 82
- getReceivingPipe
 - BiometricEvaluation::Process::Worker, 347
- getRecordType
 - BiometricEvaluation::View::AN2KView, 111
- getRegisteredVendorBlock
 - BiometricEvaluation::Finger::AN2KMinutiaeData-Record, 95
- getResolution
 - BiometricEvaluation::Image::Image, 208
- getScanResolution
 - BiometricEvaluation::Finger::INCITSView, 223
 - BiometricEvaluation::View::AN2KView, 111
 - BiometricEvaluation::View::View, 340
- getSegmentationQualityMetric
 - BiometricEvaluation::Finger::AN2KViewCapture, 115
- getSendingPipe
 - BiometricEvaluation::Process::Worker, 347
- getSize
 - BiometricEvaluation::Memory::IndexedBuffer, 229
- getSourceAgency
 - BiometricEvaluation::View::AN2KViewVariable-Resolution, 125
- getSpaceUsed
 - BiometricEvaluation::IO::ArchiveRecordStore, 134
 - BiometricEvaluation::IO::CompressedRecordStore, 151
 - BiometricEvaluation::IO::DBRecordStore, 171
 - BiometricEvaluation::IO::FileRecordStore, 184
 - BiometricEvaluation::IO::ListRecordStore, 246
 - BiometricEvaluation::IO::RecordStore, 307
 - BiometricEvaluation::IO::SQLiteRecordStore, 326
- getTotalWorkers
 - BiometricEvaluation::Process::Manager, 259
- getTransactionControlNumber
 - BiometricEvaluation::DataInterchange::AN2KRecord, 100
- getUserDefinedField
 - BiometricEvaluation::View::AN2KViewVariable-Resolution, 125
- getVersionNumber
 - BiometricEvaluation::DataInterchange::AN2KRecord, 99
- getWorker
 - BiometricEvaluation::Process::WorkerController, 352
- INCITSMinutiae
 - BiometricEvaluation::Feature::INCITSMinutiae, 216
- INCITSView
 - BiometricEvaluation::Finger::INCITSView, 219, 220
- INPUT_DATA_TYPE
 - BiometricEvaluation::IO::GZip, 204
- INVALIDKEYCHARS
 - BiometricEvaluation::IO::RecordStore, 316
- ISO2005View
 - BiometricEvaluation::Finger::ISO2005View, 234
- identifier
 - BiometricEvaluation::DataInterchange::AN2KRecord-::CharacterSet, 148
 - BiometricEvaluation::DataInterchange::AN2KRecord-::DomainName, 178
- Image
 - BiometricEvaluation::Image::Image, 207
- IndexedBuffer
 - BiometricEvaluation::Memory::IndexedBuffer, 229
- initWithBuffer
 - BiometricEvaluation::IO::Properties, 298
- insert
 - BiometricEvaluation::IO::ArchiveRecordStore, 134
 - BiometricEvaluation::IO::CompressedRecordStore, 152
 - BiometricEvaluation::IO::DBRecordStore, 172
 - BiometricEvaluation::IO::FileRecordStore, 184
 - BiometricEvaluation::IO::ListRecordStore, 242
 - BiometricEvaluation::IO::RecordStore, 307, 308
 - BiometricEvaluation::IO::SQLiteRecordStore, 327

- isAppendixFCompliant
 - BiometricEvaluation::Finger::INCITSView, [221](#)
- isJPEG
 - BiometricEvaluation::Image::JPEG, [236](#)
- isJPEG2000
 - BiometricEvaluation::Image::JPEG2000, [239](#)
- isJPEGL
 - BiometricEvaluation::Image::JPEGL, [241](#)
- isNetPBM
 - BiometricEvaluation::Image::NetPBM, [267](#)
- isPNG
 - BiometricEvaluation::Image::PNG, [287](#)
- isReadable
 - BiometricEvaluation::IO::Utility, [78](#)
- isWSQ
 - BiometricEvaluation::Image::WSQ, [354](#)
- isWorking
 - BiometricEvaluation::Process::ForkWorkerController, [195](#)
 - BiometricEvaluation::Process::POSIXThreadWorkerController, [291](#)
 - BiometricEvaluation::Process::WorkerController, [352](#)
- isWritable
 - BiometricEvaluation::IO::Utility, [78](#)
- iterator
 - BiometricEvaluation::Memory::AutoArray, [141](#)
- JPEG2000
 - BiometricEvaluation::Image::JPEG2000, [237](#)
- KEYLISTFILENAME
 - BiometricEvaluation::IO::ListRecordStore, [246](#)
- keyExists
 - BiometricEvaluation::Memory::OrderedMap, [277](#)
- Kind
 - BiometricEvaluation::Finger::AN2KViewCapture::AmputatedBandaged, [89](#)
 - BiometricEvaluation::Image::Resolution, [318](#)
 - BiometricEvaluation::IO::Compressor, [158](#)
 - BiometricEvaluation::View::AN2KView::DeviceMonitoringMode, [177](#)
- kindToString
 - BiometricEvaluation::IO::Compressor, [158](#)
- LISTTYPE
 - BiometricEvaluation::IO::RecordStore, [317](#)
- length
 - BiometricEvaluation::IO::ArchiveRecordStore, [136](#)
 - BiometricEvaluation::IO::CompressedRecordStore, [153](#)
 - BiometricEvaluation::IO::DBRecordStore, [173](#)
 - BiometricEvaluation::IO::FileRecordStore, [185](#)
 - BiometricEvaluation::IO::ListRecordStore, [243](#)
 - BiometricEvaluation::IO::RecordStore, [310](#)
 - BiometricEvaluation::IO::SQLiteRecordStore, [328](#)
- ListRecordStore
 - BiometricEvaluation::IO::ListRecordStore, [242](#)
- LogCabinet
 - BiometricEvaluation::IO::LogCabinet, [247](#)
- LogSheet
 - BiometricEvaluation::IO::LogSheet, [251](#), [252](#)
- logStats
 - BiometricEvaluation::Process::Statistics, [335](#)
- MEMORY_LEVEL
 - BiometricEvaluation::IO::GZip, [204](#)
- makePath
 - BiometricEvaluation::IO::Utility, [76](#)
- ManifestMap
 - BiometricEvaluation::IO, [72](#)
- MemoryError
 - BiometricEvaluation::Error::MemoryError, [263](#)
- mergeLogSheets
 - BiometricEvaluation::IO::LogSheet, [255](#)
- mergeRecordStores
 - BiometricEvaluation::IO::RecordStore, [314](#)
- method
 - BiometricEvaluation::Feature::AN2K7Minutiae::FingerprintReadingSystem, [188](#)
- NA
 - BiometricEvaluation::Finger::AN2KViewCapture::AmputatedBandaged, [89](#)
 - BiometricEvaluation::Image::Resolution, [319](#)
 - BiometricEvaluation::View::AN2KView::DeviceMonitoringMode, [177](#)
- NAMEPROPERTY
 - BiometricEvaluation::IO::RecordStore, [316](#)
- name
 - BiometricEvaluation::Feature::AN2K7Minutiae::FingerprintReadingSystem, [188](#)
- needsVacuum
 - BiometricEvaluation::IO::ArchiveRecordStore, [138](#)
- newEntry
 - BiometricEvaluation::IO::LogSheet, [253](#)
- newLogSheet
 - BiometricEvaluation::IO::LogCabinet, [248](#)
- NotImplemented
 - BiometricEvaluation::Error::NotImplemented, [270](#), [271](#)
- ObjectDoesNotExist

- BiometricEvaluation::Error::ObjectDoesNotExist, 271
- ObjectExists
 - BiometricEvaluation::Error::ObjectExists, 272
- ObjectIsClosed
 - BiometricEvaluation::Error::ObjectIsClosed, 273
- ObjectIsOpen
 - BiometricEvaluation::Error::ObjectIsOpen, 273
- Observed
 - BiometricEvaluation::View::AN2KView::Device-MonitoringMode, 177
- offset
 - BiometricEvaluation::IO::ManifestEntry, 262
- openImage
 - BiometricEvaluation::Image::Image, 210
- openRecordStore
 - BiometricEvaluation::IO::RecordStore, 313
- operator const T *
 - BiometricEvaluation::Memory::AutoArray, 142
- operator T *
 - BiometricEvaluation::Memory::AutoArray, 142
- operator <<
 - BiometricEvaluation::Finger, 68
 - BiometricEvaluation::Image, 71
 - BiometricEvaluation::View, 87
- operator*
 - BiometricEvaluation::Memory::OrderedMapConst-Iterator, 279
 - BiometricEvaluation::Memory::OrderedMapIterator, 282
- operator++
 - BiometricEvaluation::Memory::OrderedMapConst-Iterator, 280
 - BiometricEvaluation::Memory::OrderedMapIterator, 283
- operator->
 - BiometricEvaluation::Memory::OrderedMapConst-Iterator, 279
 - BiometricEvaluation::Memory::OrderedMapIterator, 282
- operator--
 - BiometricEvaluation::Memory::OrderedMapConst-Iterator, 280
 - BiometricEvaluation::Memory::OrderedMapIterator, 283
- operator=
 - BiometricEvaluation::IO::LogSheet, 255
 - BiometricEvaluation::Memory::AutoArray, 146
- operator==
 - BiometricEvaluation::Memory::OrderedMapConst-Iterator, 280
- BiometricEvaluation::Memory::OrderedMapIterator, 283
- OrderedMap
 - BiometricEvaluation::Memory::OrderedMap, 275
- OrderedMapConstIterator
 - BiometricEvaluation::Memory::OrderedMapConst-Iterator, 279
- OrderedMapIterator
 - BiometricEvaluation::Memory::OrderedMapIterator, 282
- PPCM
 - BiometricEvaluation::Image::Resolution, 319
- PPI
 - BiometricEvaluation::Image::Resolution, 319
- PPMM
 - BiometricEvaluation::Image::Resolution, 319
- POSIXThreadManager
 - BiometricEvaluation::Process::POSIXThreadManager, 288
- PROCESSTIME
 - BiometricEvaluation::Time::Watchdog, 343
- ParameterError
 - BiometricEvaluation::Error::ParameterError, 284
- ParameterList
 - BiometricEvaluation::Process, 81
- parsePositionDescriptors
 - BiometricEvaluation::Finger::AN2KViewVariable-Resolution, 122
- parseUserDefinedField
 - BiometricEvaluation::View::AN2KViewVariable-Resolution, 126
- populateFGP
 - BiometricEvaluation::Finger::AN2KView, 105
- PrintPositionCoordinate
 - BiometricEvaluation::Finger::AN2KViewVariable-Resolution::PrintPositionCoordinate, 292
- Properties
 - BiometricEvaluation::IO::Properties, 294
- PropertiesFile
 - BiometricEvaluation::IO::PropertiesFile, 299
- PropertiesMap
 - BiometricEvaluation::IO, 72
- push_back
 - BiometricEvaluation::Memory::OrderedMap, 275
- REALTIME
 - BiometricEvaluation::Time::Watchdog, 343
- RSREADONLYERROR
 - BiometricEvaluation::IO::RecordStore, 317
- read
 - BiometricEvaluation::IO::ArchiveRecordStore, 135

- BiometricEvaluation::IO::CompressedRecordStore, removeRecordStore
152
- BiometricEvaluation::IO::DBRecordStore, 173
- BiometricEvaluation::IO::FileRecordStore, 185
- BiometricEvaluation::IO::ListRecordStore, 243
- BiometricEvaluation::IO::RecordStore, 308, 309
- BiometricEvaluation::IO::SQLiteRecordStore, 327
- readCoreDeltaData
 - BiometricEvaluation::Finger::ANSI2004View, 128
 - BiometricEvaluation::Finger::ANSI2007View, 131
 - BiometricEvaluation::Finger::INCITSView, 227
 - BiometricEvaluation::Finger::ISO2005View, 234
- readExtendedDataBlock
 - BiometricEvaluation::Finger::INCITSView, 227
- readFMRHeader
 - BiometricEvaluation::Finger::INCITSView, 226
- readFVMR
 - BiometricEvaluation::Finger::INCITSView, 226
- readFile
 - BiometricEvaluation::IO::Utility, 77
- readMinutiaeDataPoints
 - BiometricEvaluation::Finger::INCITSView, 226
- readRidgeCountData
 - BiometricEvaluation::Finger::INCITSView, 227
- readSegments
 - BiometricEvaluation::IO::SQLiteRecordStore, 331
- receiveMessageFromManager
 - BiometricEvaluation::Process::Worker, 348
- recordLocations
 - BiometricEvaluation::DataInterchange::AN2KRecord, 99
- RecordStore
 - BiometricEvaluation::IO::RecordStore, 305
- reference
 - BiometricEvaluation::Memory::AutoArray, 141
- remove
 - BiometricEvaluation::IO::ArchiveRecordStore, 134
 - BiometricEvaluation::IO::CompressedRecordStore, 152
 - BiometricEvaluation::IO::DBRecordStore, 172
 - BiometricEvaluation::IO::FileRecordStore, 184
 - BiometricEvaluation::IO::ListRecordStore, 242
 - BiometricEvaluation::IO::LogCabinet, 249
 - BiometricEvaluation::IO::RecordStore, 308
 - BiometricEvaluation::IO::SQLiteRecordStore, 327
- removeDirectory
 - BiometricEvaluation::IO::Utility, 74
- removeOption
 - BiometricEvaluation::IO::Compressor, 166
- removeProperty
 - BiometricEvaluation::IO::Properties, 296
- BiometricEvaluation::IO::RecordStore, 314
- replace
 - BiometricEvaluation::IO::ArchiveRecordStore, 135
 - BiometricEvaluation::IO::CompressedRecordStore, 153
 - BiometricEvaluation::IO::DBRecordStore, 173
 - BiometricEvaluation::IO::FileRecordStore, 185
 - BiometricEvaluation::IO::ListRecordStore, 243
 - BiometricEvaluation::IO::RecordStore, 309, 310
 - BiometricEvaluation::IO::SQLiteRecordStore, 328
- reset
 - BiometricEvaluation::Process::ForkWorkerController, 195
 - BiometricEvaluation::Process::Manager, 260
 - BiometricEvaluation::Process::POSIXThreadWorkerController, 291
 - BiometricEvaluation::Process::WorkerController, 352
- resetCurrentEntry
 - BiometricEvaluation::IO::LogSheet, 253
- resize
 - BiometricEvaluation::Memory::AutoArray, 145
- Resolution
 - BiometricEvaluation::Image::Resolution, 319
- responsibleFor
 - BiometricEvaluation::Process::ForkManager, 193
- SQLITETYPE
 - BiometricEvaluation::IO::RecordStore, 317
- scan
 - BiometricEvaluation::Memory::IndexedBuffer, 231
- scanBeU16Val
 - BiometricEvaluation::Memory::IndexedBuffer, 230
- scanBeU32Val
 - BiometricEvaluation::Memory::IndexedBuffer, 231
- scanU16Val
 - BiometricEvaluation::Memory::IndexedBuffer, 230
- scanU32Val
 - BiometricEvaluation::Memory::IndexedBuffer, 231
- scanU64Val
 - BiometricEvaluation::Memory::IndexedBuffer, 231
- scanU8Val
 - BiometricEvaluation::Memory::IndexedBuffer, 230
- segment
 - BiometricEvaluation::Finger::AN2KViewVariableResolution::PrintPositionCoordinate, 292
- sendMessageToManager
 - BiometricEvaluation::Process::Worker, 348
- sendMessageToWorker
 - BiometricEvaluation::Process::WorkerController, 350

- sequence
 - BiometricEvaluation::IO::ArchiveRecordStore, [136](#)
 - BiometricEvaluation::IO::CompressedRecordStore, [154](#)
 - BiometricEvaluation::IO::DBRecordStore, [174](#)
 - BiometricEvaluation::IO::FileRecordStore, [186](#)
 - BiometricEvaluation::IO::ListRecordStore, [244](#)
 - BiometricEvaluation::IO::LogSheet, [254](#)
 - BiometricEvaluation::IO::RecordStore, [311](#), [312](#)
 - BiometricEvaluation::IO::SQLiteRecordStore, [329](#)
- setAppendixFCompliance
 - BiometricEvaluation::Finger::INCITSView, [225](#)
- setAsideName
 - BiometricEvaluation::IO::Utility, [75](#)
- setAutoSync
 - BiometricEvaluation::IO::LogSheet, [254](#)
- setCBEFFProductIDs
 - BiometricEvaluation::Finger::INCITSView, [224](#)
- setCanSigJump
 - BiometricEvaluation::Time::Watchdog, [342](#)
- setCaptureEquipmentID
 - BiometricEvaluation::Finger::INCITSView, [224](#)
- setCorePointSet
 - BiometricEvaluation::Feature::INCITSMinutiae, [216](#)
- setCursorAtKey
 - BiometricEvaluation::IO::ArchiveRecordStore, [137](#)
 - BiometricEvaluation::IO::CompressedRecordStore, [155](#)
 - BiometricEvaluation::IO::DBRecordStore, [175](#)
 - BiometricEvaluation::IO::FileRecordStore, [187](#)
 - BiometricEvaluation::IO::ListRecordStore, [245](#)
 - BiometricEvaluation::IO::RecordStore, [312](#)
 - BiometricEvaluation::IO::SQLiteRecordStore, [330](#)
- setDefaultSignalSet
 - BiometricEvaluation::Error::SignalManager, [322](#)
- setDeltaPointSet
 - BiometricEvaluation::Feature::INCITSMinutiae, [216](#)
- setDepth
 - BiometricEvaluation::Image::Image, [212](#)
- setDimensions
 - BiometricEvaluation::Image::Image, [212](#)
- setExpired
 - BiometricEvaluation::Time::Watchdog, [343](#)
- setImageData
 - BiometricEvaluation::Finger::INCITSView, [225](#)
- setImageResolution
 - BiometricEvaluation::Finger::INCITSView, [225](#)
- setImageSize
 - BiometricEvaluation::Finger::INCITSView, [225](#)
- setImpressionType
 - BiometricEvaluation::Finger::AN2KView, [106](#)
- BiometricEvaluation::Finger::INCITSView, [224](#)
- setIndex
 - BiometricEvaluation::Memory::IndexedBuffer, [229](#)
- setInterval
 - BiometricEvaluation::Time::Watchdog, [342](#)
- setMinutiaPoints
 - BiometricEvaluation::Feature::INCITSMinutiae, [216](#)
- setMinutiaeData
 - BiometricEvaluation::Finger::INCITSView, [223](#)
- setNotWorking
 - BiometricEvaluation::Process::ForkManager, [193](#)
- setOption
 - BiometricEvaluation::IO::Compressor, [164](#), [165](#)
- setParameter
 - BiometricEvaluation::Process::Worker, [346](#)
 - BiometricEvaluation::Process::WorkerController, [351](#)
- setParameterFromDouble
 - BiometricEvaluation::Process::WorkerController, [351](#)
- setParameterFromInteger
 - BiometricEvaluation::Process::WorkerController, [351](#)
- setParameterFromString
 - BiometricEvaluation::Process::WorkerController, [351](#)
- setPosition
 - BiometricEvaluation::Finger::INCITSView, [223](#)
- setPositions
 - BiometricEvaluation::Finger::AN2KView, [106](#)
- setProperty
 - BiometricEvaluation::IO::RecordStore, [315](#)
- setProperty
 - BiometricEvaluation::IO::Properties, [295](#)
- setPropertyFromDouble
 - BiometricEvaluation::IO::Properties, [295](#)
- setPropertyFromInteger
 - BiometricEvaluation::IO::Properties, [295](#)
- setQuality
 - BiometricEvaluation::Finger::INCITSView, [224](#)
- setResolution
 - BiometricEvaluation::Image::Image, [212](#)
- setRidgeCountItems
 - BiometricEvaluation::Feature::INCITSMinutiae, [216](#)
- setScanResolution
 - BiometricEvaluation::Finger::INCITSView, [225](#)
- setSigHandled
 - BiometricEvaluation::Error::SignalManager, [323](#)
- setSignalSet
 - BiometricEvaluation::Error::SignalManager, [322](#)
- setViewNumber

- BiometricEvaluation::Finger::INCITSView, 224
- sigHandled
 - BiometricEvaluation::Error::SignalManager, 322
- SignalManager
 - BiometricEvaluation::Error::SignalManager, 321
- Size
 - BiometricEvaluation::Image::Size, 324
- size
 - BiometricEvaluation::IO::ManifestEntry, 262
 - BiometricEvaluation::Memory::AutoArray, 145
 - BiometricEvaluation::Memory::OrderedMap, 277
- size_type
 - BiometricEvaluation::Memory::AutoArray, 141
- skipComment
 - BiometricEvaluation::Image::NetPBM, 268
- skipLine
 - BiometricEvaluation::Image::NetPBM, 268
- split
 - BiometricEvaluation::Text, 84
- sqliteError
 - BiometricEvaluation::IO::SQLiteRecordStore, 330
- standard
 - BiometricEvaluation::Feature::AN2K7Minutiae::-
PatternClassification::Entry, 179
- start
 - BiometricEvaluation::Error::SignalManager, 322
 - BiometricEvaluation::Time::Timer, 337
 - BiometricEvaluation::Time::Watchdog, 342
- startAutoLogging
 - BiometricEvaluation::Process::Statistics, 335
- startWorker
 - BiometricEvaluation::Process::ForkManager, 192
 - BiometricEvaluation::Process::Manager, 259
 - BiometricEvaluation::Process::POSIXThreadManager, 289
- startWorkers
 - BiometricEvaluation::Process::ForkManager, 191
 - BiometricEvaluation::Process::Manager, 259
 - BiometricEvaluation::Process::POSIXThreadManager, 289
- Statistics
 - BiometricEvaluation::Process::Statistics, 333
- stop
 - BiometricEvaluation::Error::SignalManager, 323
 - BiometricEvaluation::Process::Worker, 346
 - BiometricEvaluation::Time::Timer, 337
 - BiometricEvaluation::Time::Watchdog, 342
- stopAutoLogging
 - BiometricEvaluation::Process::Statistics, 335
- stopRequested
 - BiometricEvaluation::Process::Worker, 349
- stopWorker
 - BiometricEvaluation::Process::ForkManager, 192
 - BiometricEvaluation::Process::Manager, 260
 - BiometricEvaluation::Process::POSIXThreadManager, 290
- StrategyError
 - BiometricEvaluation::Error::StrategyError, 336
- stringToKind
 - BiometricEvaluation::IO::Compressor, 159
- swap
 - BiometricEvaluation::Memory::AutoArray, 146
- sync
 - BiometricEvaluation::IO::ArchiveRecordStore, 134
 - BiometricEvaluation::IO::CompressedRecordStore, 151
 - BiometricEvaluation::IO::DBRecordStore, 172
 - BiometricEvaluation::IO::ListRecordStore, 244
 - BiometricEvaluation::IO::LogSheet, 253
 - BiometricEvaluation::IO::PropertiesFile, 300
 - BiometricEvaluation::IO::RecordStore, 307
- TYPEPROPERTY
 - BiometricEvaluation::IO::RecordStore, 316
- Timer
 - BiometricEvaluation::Time::Timer, 337
- trim
 - BiometricEvaluation::IO::LogSheet, 254
- Unattended
 - BiometricEvaluation::View::AN2KView::Device-
MonitoringMode, 177
- units
 - BiometricEvaluation::Image::Resolution, 319
- Unknown
 - BiometricEvaluation::View::AN2KView::Device-
MonitoringMode, 177
- updateCursor
 - BiometricEvaluation::IO::LogSheet, 255
- vacuum
 - BiometricEvaluation::IO::ArchiveRecordStore, 138
- validateKeyValueTable
 - BiometricEvaluation::IO::SQLiteRecordStore, 330
- validateRootName
 - BiometricEvaluation::IO::Utility, 76
- validateSchema
 - BiometricEvaluation::IO::SQLiteRecordStore, 331
- value_type
 - BiometricEvaluation::Memory::AutoArray, 141
 - BiometricEvaluation::Memory::AutoBuffer, 147
- valueInColorspace
 - BiometricEvaluation::Image::Image, 209

- version
 - BiometricEvaluation::DataInterchange::AN2KRecord-
::CharacterSet, [149](#)
 - BiometricEvaluation::DataInterchange::AN2KRecord-
::DomainName, [178](#)
- WINDOW_BITS
 - BiometricEvaluation::IO::GZip, [204](#)
- waitForMessage
 - BiometricEvaluation::Process::Manager, [260](#)
 - BiometricEvaluation::Process::Worker, [349](#)
- Watchdog
 - BiometricEvaluation::Time::Watchdog, [341](#)
- WorkerController
 - BiometricEvaluation::Process::WorkerController,
[350](#)
- workerMain
 - BiometricEvaluation::Process::Worker, [344](#)
- write
 - BiometricEvaluation::IO::LogSheet, [252](#)
- writeComment
 - BiometricEvaluation::IO::LogSheet, [252](#)
- writeFile
 - BiometricEvaluation::IO::Utility, [77](#), [78](#)
- x
 - BiometricEvaluation::Image::Coordinate, [168](#)
- xDistance
 - BiometricEvaluation::Image::Coordinate, [168](#)
- xRes
 - BiometricEvaluation::Image::Resolution, [319](#)
- xSize
 - BiometricEvaluation::Image::Size, [324](#)
- y
 - BiometricEvaluation::Image::Coordinate, [168](#)
- yDistance
 - BiometricEvaluation::Image::Coordinate, [168](#)
- yRes
 - BiometricEvaluation::Image::Resolution, [319](#)
- ySize
 - BiometricEvaluation::Image::Size, [324](#)